Veritas Access Solutions Guide for Software-Defined Storage (SDS) Management Platform

Linux

7.4.2



Veritas Access Solutions Guide for Software-Defined Storage (SDS) Management Platform

Last updated: 2020-09-22

Document version: 7.4.2 Rev 0

Legal Notice

Copyright © 2018 Veritas Technologies LLC. All rights reserved.

Veritas, the Veritas Logo, Veritas InfoScale, and NetBackup are trademarks or registered trademarks of Veritas Technologies LLC or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

This product may contain third-party software for which Veritas is required to provide attribution to the third party ("Third-Party Programs"). Some of the Third-Party Programs are available under open source or free software licenses. The License Agreement accompanying the Software does not alter any rights or obligations you may have under those open source or free software licenses. Refer to the third-party legal notices document accompanying this Veritas product or available at:

https://www.veritas.com/licensing/process

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Veritas Technologies LLC and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. VERITAS TECHNOLOGIES LLC SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, et seq. "Commercial Computer Software and Commercial Computer Software Documentation," as applicable, and any successor regulations, whether delivered by Veritas as on premises or hosted services. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Veritas Technologies LLC

500 E Middlefield Road Mountain View, CA 94043

http://www.veritas.com

Technical Support

Technical Support maintains support centers globally. All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policies. For information about our support offerings and how to contact Technical Support, visit our website:

https://www.veritas.com/support

You can manage your Veritas account information at the following URL:

https://my.veritas.com

If you have questions regarding an existing support agreement, please email the support agreement administration team for your region as follows:

Worldwide (except Japan)

CustomerCare@veritas.com

Japan

CustomerCare_Japan@veritas.com

Documentation

Make sure that you have the current version of the documentation. Each document displays the date of the last update on page 2. The document version appears on page 2 of each guide. The latest documentation is available on the Veritas website:

https://sort.veritas.com/documents

Documentation feedback

Your feedback is important to us. Suggest improvements or report errors or omissions to the documentation. Include the document title, document version, chapter title, and section title of the text on which you are reporting. Send feedback to:

accessdocs@veritas.com

You can also see documentation information or ask a question on the Veritas community site:

http://www.veritas.com/community/

Veritas Services and Operations Readiness Tools (SORT)

Veritas Services and Operations Readiness Tools (SORT) is a website that provides information and tools to automate and simplify certain time-consuming administrative tasks. Depending on the product, SORT helps you prepare for installations and upgrades, identify risks in your datacenters, and improve operational efficiency. To see what services and tools SORT provides for your product, see the data sheet:

https://sort.veritas.com/data/support/SORT_Data_Sheet.pdf

Contents

Chapter 1	Introduction	6
	About Veritas Access About the SDS Management Platform	6 6
Chapter 2	Deploying the SDS Management Platform with Veritas Access	8
	Deploying the SDS Management Platform	8
Chapter 3	Using the SDS Management Platform interface	11
	Using the SDS Management Platform launchpad Using the Infrastructure application Using the Long Term Retention Storage (LTR) application Operation icons on the SDS Management Platform interface	11 13 21 23
Chapter 4	Setting up SSL in the SDS Management Platform	26
	About setting up SSL in the SDS Management Platform Generating and installing a new certificate Creating and upgrading a trust store	26 27 30
Chapter 5	Performing authentication	31
	Authentication modules Certificate-based client authentication	31 32
Chapter 6	System backup and restore	34
	About system backup and restore Automatic backups Manual backups	34 35 35

Chapter 7	Troubleshooting	7
	Log locations	7 8 8 0
	If multiple bucket creation requests with different inputs for attributes such as size and layout are in progress in parallel,	0
	then a bucket can get created with incorrect attributes	9
	change	9
	protocol (such as, https://10.20.30.40), the provider gets added and collects data but running the LTR workflow fails	9
	When you create a bucket, the status of the task appears as	^
	Clicking on a non-mapped Veritas Access cluster directs you to an empty wiki page which shows a table and some data 4 0	U
	If you restart the operating system, the SDS Management Platform does not start automatically	0
	When you add a storage resource or backup server, the added	0
	After the SDS log is rotated, the log messages from either Veritas Access or the SDS plugin go to the rotated file instead of the	Ŭ
	new file	1
	Infrastructure> Storage Resources page	1 1
	Software limitations	1

Chapter

Introduction

This chapter includes the following topics:

- About Veritas Access
- About the SDS Management Platform

About Veritas Access

Veritas Access is a software-defined, scale-out network-attached storage (NAS) solution for unstructured data that works on commodity hardware. Veritas Access provides resiliency, multi-protocol access, and data movement to and from the public and private cloud based on policies. You can reduce your storage costs by using low-cost disks and by storing infrequently accessed data in the cloud.

About the SDS Management Platform

The Software-Defined Storage (SDS) Management Platform when integrated with Veritas Access provides a platform to integrate data from various sources within an enterprise (not just the data center), which presents a single, integrated view in to the whole environment. The SDS Management Platform brings together Veritas Access and Veritas NetBackup using a simple and intuitive platform to address long-term retention and other use cases.

The SDS Management Platform provides a platform for products like Veritas Access and Veritas NetBackup to work seamlessly to address your storage requirements. In the first iteration of the SDS Management Platform, you can manage Veritas Access and NetBackup deployments and address a critical use case for providing long-term retention storage for Veritas NetBackup using Veritas Access through a single interface. You can also provision and manage storage across your Veritas Access clusters using the power of SDS. In the future, other integrations for Veritas products will be introduced using the SDS Management Platform with the goal of simplifying the user experience.

Chapter

Deploying the SDS Management Platform with Veritas Access

This chapter includes the following topics:

Deploying the SDS Management Platform

Deploying the SDS Management Platform

Supported operating system: RHEL 7.4

Supported NetBackup server versions: 8.1 and later

Note: If you are using NetBackup 8.1, you have to add a Veritas Access cloud instance. For more information, see https://www.veritas.com/support/en_US/article.000125094.

Prerequisite

- Ensure that you have installed Java version 1.8.0u152. You can find out the existing version of Java present in your system. If you have not installed Java, then, you can install it using the yum install
 java-1.8.0-openjdk command. If any other versions of Java are installed, you have to set the 1.8.0 version as the default. You can set the default using the alternatives --config java option and selecting the required version.
- Add Veritas Access cluster details to the /etc/hosts file of the NetBackup master server.

The SDS Management Platform RPMs are available at

/dvdl-redhatlinux/rhel7_x86_64/fluidops/rpms. You are required to install the following packages:

- RPM containing the core platform: VRTSFOPS-platform-9.0.0.XXXX.noarch.rpm
- RPM containing the modules for the SDS Management Platform (VDL branding, Infrastructure Application, Providers and the User Interface):
 VRTSFOPS-bundled-sds-mgmt-platform-1.0.XXXX.rpm
- RPM containing the Long Term Retention Storage application: VRTSFOPS-bundled-sds-ltr-1.0.183.rpm
- RPM containing the SDS module: VRTSsds-fops-1.0.xxxxx.rpm

To deploy the SDS Management Platform

1 Install the core platform rpm.

rpm -Uv VRTSFOPS-platform*.rpm

2 Install the bundled application.

rpm -Uv VRTSFOPS-bundled-sds*.rpm

3 Install the SDS module.

rpm -Uv VRTSsds_fops*.rpm

4 Check whether all the SDS services are running using the following command:

/etc/init.d/sds_fops status

/etc/init.d/sds-access_fops status

5 Start the platform using the following command:

/etc/init.d/fops start

Note: The applications can be updated without updating the core platform.

6 Check whether all the services are running using the following command:

/etc/init.d/fops status

7 After you install the SDS Management Platform RPMs on any Veritas Access cluster node, you have to open the 50443 port. You can open the port using the following command:

iptables -I INPUT 1 -p tcp --dport 50443 -j ACCEPT

The SDS Management Platform server takes some time to start. Wait for a few minutes.

After installing the SDS Management Platform RPMs, you can verify if the 50443 port is open using the following command:

netstat -plunt | grep 50443

If the command does not return any output, then you have to reload the systemct1 daemon and restart the SDS Management Platform server.

systemctl daemon-reload systemctl restart fops

- 8 After a few minutes, you can access the platform in a browser using the https://<host>:50443 URL.
- 9 The default credentials are:

User: admin

Password: 5D5C+r1!

You can change the password on the **User Management** page. Go to **Settings** > **User Management**.

Chapter

Using the SDS Management Platform interface

This chapter includes the following topics:

- Using the SDS Management Platform launchpad
- Using the Infrastructure application
- Using the Long Term Retention Storage (LTR) application
- Operation icons on the SDS Management Platform interface

Using the SDS Management Platform launchpad

Once you log on successfully, the SDS Management Platform launchpad is the first interface that appears. The launchpad shows the applications that are installed. If you have installed only the base platform, no applications appear in the launchpad. When you select a specific application, you can see the content specific to your application.



Figure 3-1

You can add a new Veritas Access cluster. Get details on each cluster and the provider that collects the data.

You can add a new NetBackup server. Get details on each server, and policies.

In the current release, the two main applications that are available are the **Infrastructure** application and the **Long Term Retention Storage** application.

The menu is also specific to an application. The menu always includes **Back to Launchpad** as the first option. If you want to switch to a different application, you can go back to the launchpad using this menu option and select a different application in the launchpad.

Figure 3-2 SDS Management Platform launchpad

Veritas SDS Management Platform Launchpad		۵ پ	? 0	0
Home				
Apps You can install new Apps as per your use case and we can help you with better solution.	Infrastructure Here you can manage your infrastructure.			
Long Term Retention Storage	Infrastructure Version and infrastructure Version and university of the first state of the second state o	Add Backup Servers You can add NBU servers from here for moving data to cost effective storage provided by Storage Resources.		
data.	monitor Storage Resources and Backup Servers. Storage Resources Backup Servers	Add Backup Server		
Total Storage Allocated 906.00 GB	4 4 0 3 3 0 Total Healthy At risk Total Storage Capacity 6:69 TB	Add Storage Resources You can add an Access Cluster as a storage resource here.		
G8 G8	Used 1.21 TB Free 5.48 TB	Add Storage Resource		

If you install the Veritas Access solution, you can see the **Add Backup Servers** and the **Add Storage Resources** pane.

Using the Infrastructure application

This section describes the Infrastructure application.

	Infrastructure Overview				
Back to Launchpad			11-1-(70)	And a start	
Overview	Storage Resources	Backup Servers	Alerts (58)	THEY BE DECLE	
Infrastructure			OCluster data is not backed up	Missing NBU media server	
Provisioned Storage	Health	Health	2010-04-06-07:07:01		
	4 4 0	3 3 0	OCluster data is not backed up.	Missing NBU master	
	Total Healthy Atriak	Total Healthy Atriak	server configuration. 2018-04-35-07-07-30		
	Storage Summary	Storage Summary	OCIES in allian		
	Total Storage Capacity 6.69 TB	On-premise	2018-04-05-07-06-25		
	18%	Total Storage Capacity 71,73 GB	ONFS is offline		
		Used 0.00 Bytes D Free 71.73 GB	2018-04-36-07-06.33		
		Cloud	OCluster data is not backed up.	Missing NBU master	
		<u></u>	2018-04-05-05:04:02		
			Oluster data is not backed up	Missing NBU media server	
	Provisioned Storage		configuration.		
	All Paralante - Paralante	No. 1 August	O CIES is offline		
	All Buckets Buckets	a anocated as Storage for LTH	2018-04-26-05:02:20		
	43 30 13 10 Total Meeting At sink Total M	10 0	ONES is offline		
		early Action	2010-04-36 03:02:17		
	File Systems Shares		OCuster data is not backed up	Missing NBU master	
	49 30 19 0	0 0	2018/04/25/21:41.14		
	Total Healthy Atrisk Total H	ealthy At risk	Oluster data is not backed up	Missing NBU media server	
			configuration.		

Figure 3-3 Infrastructure application

The Infrastructure application has the following menu entries:

- Back to Launchpad
- Overview
- Infrastructure
- Provisioned Storage

Back to Launchpad

Use this option to go back to the launchpad and switch to another application.

Overview

This page displays the following information:

 Displays the health and storage overview for the storage resources and the backup servers.

The storage summary shows the storage utilization of all the Veritas Access clusters and the NetBackup servers.

You can interpret the storage summary as follows:

Total	The total number of Veritas Access clusters (storage resources) and NetBackup servers (backup servers) known to the platform.
Healthy	If data is collected successfully from the system, the system is healthy.
At risk	If no connection is established with the system, the system is at risk.

Health overview for provisioned storage.

Displays the details for all the buckets, the buckets that are used as LTR storage, file systems, and shares. A resource is denoted as healthy if the resource is online or in running state. Otherwise, the resource is said to be at risk.

Alert overview

Lists the alerts coming from the Veritas Access installation. Only a limited number of alerts are shown on the **Overview** page. The alerts are sorted by severity and date. You can view all the alerts by selecting **View all alerts**.

Infrastructure

This has two sub-menu items:

- Storage Resources
- Backup servers

Storage Resources

This page shows an overview of the Veritas Access clusters known to the platform.

Figure 3-4	Storage Resources
------------	-------------------

	Store	ige Resources						
III Back to Leunchged								
📫 Overview		to Storage Resource						
ntiastructure:	× 125	erit.						Q
& Storage Resources		Dutter	Tittal Number of Holes	At Suk Nodes	Barage Otheritors	Connected Backup Servers		Actions
III Backup Servers	.0	10.102.008.027	- N.		8.17% of 350.00 OB	10.100.070.121		/0×0
Provisioned Storage		10 10 101 100 200	1	A	1054712618	10.102.104.107		/0×0
	•	10.10.102.070.110	1.0		16.82% of 500.00 18	10.102.100.107		/0×0
		10.162.102.170.100			26 225 of 4 10 28	10102100107		/0×0

You can see the following information:

 An icon shows whether the cluster is at risk or healthy. For each cluster, details such as the total number of nodes, number of nodes at risk, storage utilization, and the connected backup servers are shown.

- You can perform the following actions on a cluster:
 - Edit the provider that collects data from the Veritas Access installation.
 For example, you can change the password that is required to log on to Veritas Access.
 - Delete all the data for the Veritas Access cluster and the provider that collects the data.
 - Run the provider.
- The information icon shows when the data was last collected, the duration of the data collection, and if there were any errors during the last provider run and how much data was collected.
- You can add a new Veritas Access cluster using the Add Storage Resource option.

To add a new storage resource

- 1 Click on Add Storage Resource.
- 2 In the pop-up window, enter the host name or IP address of the Veritas Access cluster (or the management console), the credentials (master user name and password needed to log on to Veritas Access), and the port number of the Veritas Access installation (the default port number is already pre-set, but can be changed if needed).

If you have enabled S3 on the Veritas Access cluster and the S3 bucket user is different from the user name provided in the credentials, you have to provide the S3 bucket user credentials. Else, you can ignore these fields.

If you want to immediately validate your configuration details (before the provider is added), check the **Validate provider** checkbox.

lort *	14161	
Iser *		
assword *		
a won a - are required		
is enabled on the Access of provided above, the creder w. Otherwise the fields can 3 Bucket User	cluster and the S3 bucket user is differentials of the S3 bucket user need to be be left empty.	ent from the provided
i is enabled on the Access i provided above, the creder w. Otherwise the fields can 3 Bucket User 3 Bucket Password	cluster and the S3 bucket user is different titals of the S3 bucket user need to be be left empty.	ent from the provided

3 After you submit the form, a provider is created that tries to collect data from the Veritas Access installation. If this is successful, the Veritas Access cluster is listed in the table that lists the storage resources. Go to Infrastructure > Storage Resources to verify if the new storage resource appears in the table.

Note: You have to reload the page after a short waiting period to see this information. If a connection to the Veritas Access cluster cannot be established, a notification is shown above the table. You have the option to edit the provider to fix the issue. For example, you can re-enter the password or to delete the provider.

You can get more details on a specific Veritas Access cluster by clicking on it. The detail page of a specific Veritas Access cluster shows an overview of the cluster at the top. There are tables for the nodes, disks, storage pools, buckets, shares, and file systems of the cluster showing detailed information. Even if one of these resources is at risk, a red exclamation mark appears in the tab of the respective resource.

< .	Backup Servers					
III Back to Launchped	And a second sec					
Overstew	Add Backup Server					
antentructure	A Depth.					Q
Storage Resources	Name	MBU Pulaine	Storage Resources	Previsional Storage		Artimu
E Backup Servers	© 16.162.164.167	Total 3 / In Line 3	36 182 199 299, 16 182 175 198, 16 182, 176	274% of 743 24 08		/0×0
Provisioned Storage	O NEMALITYAT	Total 3 / In the 3	16.165.169.227	18.80% of 15.00 DB		-0.0
		Total 9 / In the 6		1.425 of 10.20 OR		/0×0

Backup servers

This page shows an overview of the NetBackup servers known to the platform. You can see the following information:

- A table shows the details for each NetBackup server, such as the health status of the server (whether the platform can collect data from the server), the total number of NetBackup policies and the number of policies in use, the connected storage resources, and the storage utilization.
- You can perform the following actions on a server:
 - Edit the server that collects data from the NetBackup server.
 For example, you can change the password that is required to log on to Veritas Access.
 - Delete all the data for the Veritas Access cluster and the provider that collects the data.

- Run the provider.
- You can add a new NetBackup server using the Add Backup Server option.

To add a new backup server

- 1 Click on Add Backup Server.
- 2 In the pop-up window, enter the host name or IP address of the NetBackup server, the credentials (user name is **root** and password needed to log on to NetBackup server), and the port number (the default port number is already pre-set, but can be changed if needed).

Host *	
Port *	22
User *	
Password *	()
Validate provider	
lds with a * are required	

3 After you submit the form, a provider is created that tries to collect data from the NetBackup server. If this is successful, the backup server is listed in the table that lists the backup servers. Go to Infrastructure > Backup Servers to verify if the new backup server appears in the table.

Note: You have to reload the page after a short waiting period to see this information. If a connection to the Veritas Access cluster cannot be established, a notification is shown above the table. You have the option to edit the provider to fix the issue. For example, you can re-enter the password or to delete the provider.

You can get more details on a specific NetBackup servers by clicking on it. The detail page of a NetBackup server shows an overview at the top and shows the

connected storage resources, total number of NetBackup policies, and how many are used for LTR.

The table has three tabs that gives the following details:

- Backup Policies: Lists the policy name, policy type, bucket (if the bucket has been used with the respective policy in LTR).
- Storage Lifecycle Policies: Lists the policy name and policy type. When selecting the information icon, a popup shows the information on the operations of the policy, the operation type, source, and storage unit (STU).
- Buckets and their storage utilization.

Provisioned Storage

This page lists all the buckets, shares, and the file systems of all the known Veritas Access clusters.

Figure 3-5 Provisioned Storage

Veritas SDS Managemen	t Platform Infrastructur	e					0	7	۰	6
<	Provisioned Storage									
🔡 Beck to Launchped										
Overview										
💼 infrastructure 🔹 🗸	Sect.								Q	
Proviacened Storage	Bachat	File Spetare	Storage Pool	Bailup Servere	Dampe Rosentia	Monope Websetter		A	diam.	
	04403156 (ves-4748 kuks st.,	02561524409174	These	10.182.109.707	90.102.120.104	1.17% of 3.00 GB			1	
	0125675-1203-4307-0074-574.	02511324482400	peer		90.102.170.104	2,005-0717-02-08				
	171017c9-0127-0154-054-054-0	0351/124552754	pearl	10.102.109.107	10.102.170.108	2 27% of 7 00 GB			1	
	9129543a Taka 46526375453.	02511224422448	peart		10.140.170.108	1.94% of 13.00 GB			1	
	2015/14/5-227/6-49(2) 444/6 1984	335/1324564414	post1	10.102.109.107	10.102.129.108	1 KT% OF 4 00 DB			1	
	4240704-024-024-0240-0	33917324486389	pa(d)		10,102,129,108	2.00% of 11.00 GB			1	
	629471256414440367534	305/152-050171	post?		10.102.125.126	2115-0712-02-08			1	
	All Process of the Hold Backal of T.	33961824489022	pad)	10.102120-021	10.102.169.227	47.40%.07.5.00.08			1	
	93624121-0-04-4282-9474-44.	83511234549210	pauli	10,140,120,121	10.102/149(227	1.0%.0710.00.08			1	
	1004264103654242424474335	References and	pedl		90.100.120.100	1174 0 100 00	-		1	
	belon the wet with a rate atta	8341324488002	post		50.102.100.227	1.61% of 5.00 DB			1	
	shaces the schelar state.	8351104572903	post	10-182 100-107	10.102.1um.225	8.645 of 25.00 SB				

You can get more details on a specific bucket by clicking on it

The bucket page shows an overview of the bucket and provides an option to grow the bucket storage.

Search				
Operation	Туре	Source	Storage	Buckets
RealSLP BACKUP Operation 1	BACKUP	0	accessProvider_10.182.170.188,2e4e3,	bec1115a-3909-4cd5-b659-c69d6/b3dc6.
RealSLP DUPLICATE Operation 2	DUPLICATE	accessProvider_10.182.170.188_2e4e3	accessProvider_10.182.170.188_62182	a803abcb-c85d-4bca-8914-6cd9ff28922.

Using the Long Term Retention Storage (LTR) application

The LTR application has the following menu entries:

Back to Launchpad

Use this option to go back to the launchpad, and switch to another application.

Overview

Displays the bucket health overview, storage utilization, and a bar chart showing the top ten buckets with the highest storage utilization. An alert overview with LTR-specific alerts is also displayed, if the details are available.

Long Term Retention Storage

Shows a table of all the buckets with information on the file system, storage pool, backup server (if the bucket is used for LTR), storage resource, and storage utilization.



Figure 3-6 Long Term Retention Storage application

You can use the LTR wizard to configure storage for long-term retention.

To configure storage for long-term retention using the LTR wizard

- 1 Click on **Provision Storage** to start the LTR wizard. An infographic for the LTR workflow appears on the screen.
- 2 All the NetBackup servers known to the platform are shown in a table. Select any one server.
- **3** All the backup policies of the selected NetBackup server are shown in a table. Select any one policy.
- 4 Select whether you want to use an existing bucket for LTR or create a new one by choosing either **Select existing bucket** or **Create new bucket**.

If you select **Select existing bucket**, all the available buckets are listed in a table. Select any one bucket.

If you select **Create new bucket**, you are prompted to enter the following details:

Bucket size: The size of the bucket to be created.

- File system layout: Select any one of the values mirrored, simple, or erasure-coded from the drop-down menu.
- Device protection: If you have selected erasure-coded as the file system layout, select either disk or node from the drop-down menu. If any other file system layout has been selected, you can ignore this field.
- Policy: LTR On-premises is pre-selected. Currently, you cannot change this value.
- **5** A summary report is displayed that shows all the details.

The SDS module creates the bucket intelligently on the available clusters based on your inputs.

The bucket size can be increased either directly on the **Long Term Retention Storage** page using the respective action in the table or on the detail page of a bucket.

Note: The SDS module updates the /etc/hosts system file with the IP of the Veritas Access cluster.

Operation icons on the SDS Management Platform interface

Table 3-1 describes the operation icons visible on the SDS Management Platform interface.

 Table 3-1
 Operation icons on the SDS Management Platform interface

lcon	Name	Description	
0	Job	Displays a log of various actions on the system. The details include the description of the job, run time, s time, progress status, and messages (informational about actions that are performed or errors that have occurred), and the user who has performed an action. The progress status can be:	
		 The percentage of the progress if the job is still running. Done, if the job is successful. Error, if there was an error during execution. 	

Table 3-1	Operation icons on the SDS Management Platform interface
	(continued)

lcon	Name	Description
	Event	Displays the events collected from the Veritas Access installations.
?	Help	Displays the available documentation.
	Settings	Links to the following pages:
\$		 User Management: You can add and delete users and change passwords. Veritas recommends that you change the default admin password after you log in for the first time. Backup: You can create or restore backups for the database of the platform. Authentication set up: You can configure authentication options for the platform. For example, you can configure whether authentication against LDAP should be used. SSL configuration: You can configure the SSL configuration for the web server and API. Diagnostic Information: You can collect the information required to diagnose problems and get product support.
0	Account	Links to the account page and the logout option.

User Management

You can also add ACLs for different users.

- If the user belongs to the SDS LTR User group, then the user has access only to the LTR application.
- If the user belongs to the Access Infrastructure User group, then the user has access only to the Infrastructure application.

 If the user is an admin, then the user has access to all applications and can perform any operation.

Figure 3-7 User Management page

💮 Veritas SDS Mana;	gement Platform Settings		0 • 7 • 0
. د	User Management		
E Back to Laurchped	Add Deat		
	Search.		Q
	0mm	Groups	Antines
	atem	atro	÷*
	179	105 UTI (164	**
		Access officialization loss	**
	Doing 11 of 3		

Chapter

Setting up SSL in the SDS Management Platform

This chapter includes the following topics:

- About setting up SSL in the SDS Management Platform
- Generating and installing a new certificate
- Creating and upgrading a trust store

About setting up SSL in the SDS Management Platform

SDS Management Platform instances can be set up to authenticate and communicate securely amongst themselves using SSL certificates. The SSLs can be publically signed or self-signed certificates from your own CA (Certificate Authority). In the case of publically signed certificates, Internet access may be required to verify the authenticity of the certificate. The SDS Management Platform can make use of any certificates compatible with X509 and Java, but Veritas recommends the use of Privacy Enhanced Mail (PEM) certificates. The certificates are stored in a local Java keystore in each installation instance. In the SDS Management Platform, we distinguish between certificates of the HTTP(S) web server and internal API communication. For both configurations, distinct sets of keystores are used.

Generating and installing a new certificate

You can generate certificates in many different ways. Veritas recommends using the KeyStore Explorer, a graphical UI for the Java Keytool. You can also use the Java Keytool.

Veritas Access requires three files to work with the external certificates.

- Key file: The private key file which is used to create the CSR.
 In the example used in this section, the key.pem file refers to the key file.
- Certificate file: The certificate file which CA authority provides after signing the CSR.

In the example used in this section, the ${\tt cert.pem}$ file refers to the certificate file.

CA certificate file: The certificate file which identifies the CA authority.
 In the example used in this section, the ca-cert.pem file refers to the CA certificate file.

Using KeyStore Explorer to generate a new certificate

You can generate and install a new certificate in the SDS Management Platform using the KeyStore Explorer.

To generate and install a new certificate with the KeyStore Explorer

- 1 Open the KeyStore Explorer.
- 2 You are prompted to select the type of the new KeyStore. Select JKS. Click OK.
- **3** Generate a new key pair. Right-click > **Generate Key Pair**.

It is recommended to use RSA with a size of 2048 bits.

- 4 Configure the certificate settings.
 - It is recommended to use SHA256 with RSA (or stronger) as the signature algorithm. Modern browsers do not support MD5 or SHA-1 RC4.
 - Choose a suitable validity period.
 - A serial number is generated automatically.
 - Give a suitable name. Click on the address book icon to add name entities.

5 Add Subject Alternative Names (SANs).

As mentioned in RFC 2818, the use of CN to match the host's identity is deprecated and SAN should be used instead. To do this, click on **Add Extensions** in the certificate settings dialog, add an extension with the plus icon and choose **Subject Alternative Name** as the extension type. In the dialog, add at least one DNS entry that matches the host name to access the SDS Management Platform.

6 Enter the alias.

Veritas recommends using **jetty** as the alias though this is not strictly required. You can externally configure the actual alias that is used by the web server.

7 Enter the key pair password.

Note: The password of the keystore and the key need to be the same

- 8 Check the certificate details. Double-click on the key pair in the list to see its properties. Also check that the Subject Alternative Names are visible in the extensions.
- 9 Generate CSR. Right-click on the certificate -> Generate CSR.
- **10** Export the private key file (key.pem) in .pem format from the generated key pair.
- **11** Send the CSR to a certificate authority and let it be signed. The CA signs the CSR and provides the certificate (cert.pem) file. It also provides the CA certificate (ca-cert.pem) file.
- 12 Copy the three files (cert.pem, ca-cert.pem and key.pem) to the Veritas Access server.
- 13 Login to the Access CLISH and run System > gui_servercertficate > Add. The Veritas Access GUI server now runs with the external certificate. Enter the details of the certificates when prompted.
- 14 If a trusted CA certificate is used, then the browser does not show the *Insecure* webpage messages. If the CA certificate is not trusted, add the ca-cert.pem file to your browser.

Using the Java Keytool to generate a new certificate

The Java Keytool is a command-line tool for certificate management that is bundled with the JDK. The SDS Management Platform bundles a JRE in the installation folder.

1. Generate keys.

This creates a new key pair in a new or existing Java Keystore, which can be used to create a CSR, and obtain an SSL certificate from a Certificate Authority (CA). The following command generates a 2048-bit RSA key pair, under the specified alias (domain), in the specified keystore file (keystore.jks):

```
keytool -genkeypair -alias <domain> -keyalg RSA -keystore keystore
```

If the specified keystore does not already exist, it is created after the requested information is supplied. You are prompted for the keystore password (new or existing), followed by a Distinguished Name prompt (for the private key), then the desired private key password.

If you want your certificate to not only accept the given common name but rather additional names or IPs, you can use the keytool's SAN (Subject Alternative Names) extension.

```
keytool -genkeypair -alias <domain> -keyalg RSA -keystore keystore
-ext SAN=dns:example.com,dns:localhost,ip:127.0.0.1
```

2. Generate CSR for existing private key.

Use this method if you want to generate a CSR that you can send to a CA to request the issue of a CA-signed SSL certificate. It requires that the keystore and alias already exist. You can use the previous command to ensure this. You can use the following command to create a CSR (domain.csr) signed by the private key identified by the alias (domain) in the (keystore.jks) keystore:

keytool -certreq -alias <domain> -file <domain.csr> -keystore keystore

After you enter the keystore's password, the CSR is generated.

- 3. Extract the private key from the keystore.
 - Convert the keystore (jks) file to PKCS12 format.

```
# keytool -importkeystore -srckeystore keystore -destkeystore
keystore_pksc12 -deststoretype pkcs12
```

Where *keystore_pksc12* is the converted keystore file.

Extract the key.pem file.
 If you use Open SSL, you can use the following command:

openssl pkcs12 -in keystore_pksc12 -nodes -nocerts
-out key.pem

4. Provide the CSR file to CA and get the certificate and also the root/intermediate CA certificate files.

- 5. Copy the three files (cert.pem, ca-cert.pem and key.pem) to the Veritas Access server.
- Login to the Access CLISH and run System > gui_servercertficate > Add. The Veritas Access GUI server now runs with the external certificate. Enter the details of the certificates when prompted.
- If a trusted CA certificate is used, then the browser does not show the *Insecure* webpage messages. If the CA certificate is not trusted, add the ca-cert.pem file to your browser.

Creating and upgrading a trust store

A trust store defines the certificates of authorities that are generally trusted. The SDS Management Platform ships a default API trust store that contains the root certificates of the JDK, as well as the self-signed certificate used in default installations. Veritas recommends that you create such a trust store based on an existing trust store.

When you perform an upgrade, custom trust stores are copied over to the new installation. Unmodified bundled trust stores are automatically upgraded. If during an upgrade, the installer detects that the bundled trust store was modified, it is copied over to the new installation, and the new version is kept with a .original extension.

Chapter

Performing authentication

This chapter includes the following topics:

- Authentication modules
- Certificate-based client authentication

Authentication modules

The SDS Management Platform implements a powerful security concept that supports different directory services. The authentication mechanism is associated with a role concept. There are different authentication modules and this section gives best practices for their configuration.

An authentication module authenticates users against a specific directory service. The SDS Management Platform supports the following authentication modules:

- Local SDS Management Platform users
- LDAP Authentication

These modules can be combined into an authentication chain. The SDS Management Platform evaluates the modules in the configured order until one module succeeds or all of them have failed. If one of the modules is not configured properly, it is ignored and the evaluation continues with the next module in the chain.

Local SDS Management Platform users

This authentication module lets you authenticate the local SDS Management Platform users. Within the **authConfigOptions** parameter, you can specify an optional value called the *local.domain* value. When this value is set, the user needs to specify this value as the domain during authentication. The passwords of local users are hashed by default. The configuration setting, *hashUserPasswords* can be used to change the default behavior.

LDAP Authentication

This module lets you authenticate users against an LDAP server. The location of the server is configured with the *authConfigOptions* parameter. You can either use the **Authentication** Wizard or compile the configuration string manually.

ldap.url	Specifies the LDAP server's URL, for example Idap://my.Idap.server:389. You cannot specify the LDAP endpoint using the IP address. You can specify the LDAP endpoint only by a fully qualified domain name. If you want to authenticate against an Active Directory where the users are in the global catalog, use port 3268.
ldap.domain (OPTIONAL)	Specifies the LDAP domain. If specified, only users with the exact domain are allowed.
ldap.admingroup (OPTIONAL)	Specifies the admin group (defaults to Administrators) within the domain. Can be used to specify other admin groups (for example, if localized names are in place).

Example configuration string:

```
authConfigOptions=ldap.url\=ldap\://mt.company.corp\:389, ldap.domain\
=my.company.corp, ldap.guestgroup\=LDAPGuests,
ldap.admingroup\=LDAPAdmins:LDAPManagement,
ldap.sesusergroup\=LDAPExternalUsers
```

It is possible to customize the rights of user groups using the LDAP module. To use authentication, each LDAP group that is granted access must be mapped to an SDS Management Platform group. This mapping is a prerequisite for you to be able to log on to the system.

Certificate-based client authentication

The SDS Management Platform supports HTTP SSL certificate-based client authentication. If enabled, it is activated on an additional port in the web server (default: 50444), and clients must provide a valid certificate that is accepted by the web server.

You can configure a certificate-based client using the following settings:

Settings	Description
enableHttpSslCert	Enables HTTP SSL certificate-based authentication for the web server. If enabled, certificate-based authentication is activated on the configured <i>httpSslCertPort</i> .
httpSslCertPort	Secures (SSL) HTTP port for certificate-based authentication to the web interface. Default: 50444
httpTrustStore	SSL TrustStore used by the web server. For example, for client-based certificate authentication, see <i>enableHttpSslCert</i> setting. Default: etc/truststore
httpTrustStorePassword	SSL TrustStore password used by the web server.
httpKeyStore	SSL KeyStore used by the web server. Default: etc/keystore
httpKeyStorePassword	SSL KeyStore password used by the web server.

Table 5-1

By default, the SDS Management Platform ships an empty TrustStore. To establish trust, a valid CA certificate must be added to the TrustStore; alternatively, an existing trust store can be used.

Note: Certificate-based authentication can only be activated if the configured TrustStore contains at least one valid certificate. According to the protocol, clients require a certificate that is signed by a trusted CA.

To import a public CA key to an existing TrustStore, you can use the following command:

keytool -import -v -trustcacerts -alias my_ca -file ca.crt -keystore
truststore

Chapter

System backup and restore

This chapter includes the following topics:

- About system backup and restore
- Automatic backups
- Manual backups

About system backup and restore

The system state consists of:

- User Resource Description Framework (RDF) data
- Imported data
- Configuration
- Wiki edits
- Credentials (stored in the encrypted file secrets.xml)

You can obtain the imported data from the respective source, but provider parameters, user passwords, and other information required for the individual instance are recorded in various files that are present in the installation folder. All of these customer-specific configuration files should be backed up once the installation and configuration is completed, or whenever any updates are made. By default, this is done automatically by the system service itself every hour.

Automatic backups

Complete data backups are performed automatically at regular intervals by the system. The backup path, interval, and number of backups to keep are specified with the following configuration parameters:

- backupPath
- backupFrequencyInHours
- numberOfBackupsToKeep

By default, these parameters are written to a local disk folder called backup, which is located parallel to the installation folder, once every hour, with a rolling window of 100 backups. The oldest backups are removed automatically once the number is arrived at. You can specify the backup path to use a mounted network share rather than the local disk. The service owner or user should have write privileges on that target. Very large data centers can produce large backup files that may consume all the available space on the disk. Hence, the backup folder or disk should be dimensioned accordingly, or the number of retained backups reduced accordingly.

Note: The backups are of the data only, not the software installation.

The automatic backup is a folder named with a date and timestamp, containing zip files, and all the configuration files required to restore the object database, the RDF datastore, and all instance-specific configuration parameters, providers, and authentication data. The object database (which is in-memory at run-time) is saved to the db-core.zip file, and the RDF datastore, wiki pages, and ontology are saved in the timestamp_diagnosticfeedback.zip file. These files collectively offer a consistent backup set from which the data can be restored to the time of the backup.

Note: The in-memory DB is persisted at intervals of one minute in between the hourly backups to /db/dbcore.zip.temp.#. If these files are still available after an incident, there is no loss of persisted data. However, all of the data that has originated from providers is reloaded at the next provider run if it is no longer in the database. Hence, it is not critical to maintain the data in this database from backups.

Manual backups

You can take a manual backup of the system at any time using the backup command from the CLI. The backup is available in the standard format at /backup/timestamp/dbcore.zip.

You can backup the semantic datastore using the following command:

getSemanticService getbackupService backupDBs

The backup is available in the standard format in the /backup/ date-timestamp/ date-timestamp_diagnosticfeedback.zip folder. This functionality is also available through **Settings** -> **Backup**. The backup mechanism allows for saving the database at any time and restoring it when needed. You can save the history repository or the central database by selecting the type of backup. You have an option to make a diagnostic feedback backup. The diagnostic backup saves the database, the history repository, wiki pages, the config folder, and the config.prop file. This can be kept for later use or downloaded for making a diagnosis about the application.

You can also take a full backup which save all the data, pages, and configuration of the SDS Management Platform.

To take a manual backup

- 1 Go to Settings -> Backup.
- 2 Select the database that you want to back up from the menu. Select **dbmodel** if you want to backup the main database where imported and authored triples are stored. Select **historymodel** if you want to backup the database that stores the historical data that is created by the historical data provider.
- 3 Click **Backup**. The backup of the database is available and can be used in the future to restore the database to the current state or be downloaded as a .trig file.

Chapter

Troubleshooting

This chapter includes the following topics:

- Log locations
- Diagnostic reports
- Java Virtual Machine (JVM) parameters
- SDS Management Platform known issues
- Software limitations

Log locations

Messages related to the platform are logged to specific log files in the Install Folder/logs file. You can decide the number of log files to keep before recycling them by changing the MaxBackupIndex parameter in the Install Folder/etc/log4j.properties file.

- The wrapper.log contains information pertaining to the service start.
- The startup.log shows the product version and start parameters for the Java Virtual Machine (JVM) in which the system runs.
- The service.log shows all current messages relating to the started and running service, and is the main source of information for troubleshooting.
- The service.log.# are older incarnations that are cycled through 20 files before they are deleted automatically.
- The job.log lists all the transactions performed by the system and can be used for auditing purposes.
- The datestamp-request.log shows UI page requests.
- The performance.log. # details performance statistics relating to the service.

- The rule-engine.log. # shows rule engine runs and the time required for them to complete.
- The install.log records information from updating the system or when installing a solution.
- The /var/log/sds_fops.log shows the logs related to the SDS module.

Diagnostic reports

You can trigger the diagnostic report from **Settings** ->**Diagnostic Information**. It is a general-purpose tool that streamlines the interaction with the SDS Management Platform support. The backend service runs within a Java Virtual Machine (JVM), that in turn runs within a service wrapper which ensures that the JVM is kept running. The service is normally started and stopped using the Windows services.msc or by a Linux service init script. If the service has completely stopped responding, first attempt to connect to the service using the Command Line Interface (CLI) and, if this is possible, produce a diagnostic feedback zip file (which causes the in-memory DB to be persisted) with the following command:

getDiagnosticService createDiagnosticFeedback -addMemoryDump false

The diagnostic zip file is written to the /webapps/ROOT/diag folder and is named diag+ timestamp.zip. This causes the in-memory DB and the RDF triple store to be written to disk. Then, try to restart the service within the CLI using the restartService command. If all else fails, shutdown the operating system cleanly and restart. The database is always written in a consistent way, so it should always be readable.

Java Virtual Machine (JVM) parameters

The main Java VM parameters are defined in the <code>backend.conf</code> file. You can find the JVM parameters in the <code>%INSTALL_DIR%/backend.conf</code> folder. The most frequent use case is to assign more memory to the backend process.

- wrapper.java.additional.10=-Xmx3G
- wrapper.java.additional.4=-XX:MaxPermSize=256m

Veritas recommends that you apply the user changes in the backend-user.conf file by defining new values for the respective settings.

SDS Management Platform known issues

This section describes known issues related to the SDS Management Platform.

If multiple bucket creation requests with different inputs for attributes such as size and layout are in progress in parallel, then a bucket can get created with incorrect attributes

> If you try to create multiple buckets in parallel, wherein you have different inputs for attributes such as size and layout, then it is possible that a bucket is created with attributes that are specified for some other bucket. This happens because there is a race condition between setting bucket attributes and creating bucket operations.

Workaround:

If you want to create multiple buckets in parallel, ensure that you verify that the bucket has been created with the correct attributes. If there is a mismatch, recreate the bucket.

When editing a storage resource or backup server, an Advanced button is available that shows options that you should not change

When editing a storage resource or backup server, an **Advanced** button is available which shows options that you are not required to change. The dialogs are generic for different kinds of integrations where these options are sometimes required.

Workaround:

You can ignore the Advanced button. Do not change any of the advanced options

If you add a Veritas Access cluster where the host includes the protocol (such as, https://10.20.30.40), the provider gets added and collects data but running the LTR workflow fails

Specifying the host with the protocol when you add a Veritas Access cluster is not supported in this release.

Workaround:

When adding a Veritas Access cluster, specify the host without protocol (such as, 10.20.30.40 instead of https://10.20.30.40).

When you create a bucket, the status of the task appears as DONE, even though the creation is still in progress

The SDS Management Platform creates a job for creating a bucket and directly sets the status of the task as DONE. The task information is given to SDS which waits for the task to be completed.

Workaround:

You can ignore the state of this task or job. You can find the real status in the child jobs of the Configure Storage for Long Term Retention job.

Clicking on a non-mapped Veritas Access cluster directs you to an empty wiki page which shows a table and some data

A Veritas Access cluster which is discovered by the NetBackup provider and for which a Veritas Access provider is not configured may show as a link similar to the IP of the Veritas Access provider. This link may yield an empty page with some data.

Workaround:

Add a Veritas Access provider for the cluster.

If you restart the operating system, the SDS Management Platform does not start automatically

Currently, the SDS Management Platform is not automatically registered as a service. Hence, it is not automatically started after an operating system restart.

Workaround:

Register the SDS Management Platform as a service using the chkconfig --add fops and chkconfig fops on commands. Or, you can start the SDS Management Platform manually using the /etc/init.d/fops start command.

When you add a storage resource or backup server, the added resource is not automatically visible

When you add a storage resource or backup server, a provider is created that collects data from the Veritas Access cluster or NetBackup server respectively. This process takes some time. Therefore, the resource is not listed immediately in the table. Also, the page does not get refreshed automatically.

Workaround:

After adding a storage resource or backup server, reload the page manually after a few minutes.

After the SDS log is rotated, the log messages from either Veritas Access or the SDS plugin go to the rotated file instead of the new file

The SDS log (located at /var/log/sds_fops.log) is rotated every day. SDS contains two services, the SDS plugin and the Veritas Access plugin, which share the log file. Because of bug in Python, a race condition occurs and one of the two services starts logging to a new file while the other service continues logging in the rotated file.

Workaround:

Check the last updated timestamps of the current log file and the rotated log file and the, co-relate the logs from different services for debugging.

Some of the storage resources may appear as faulted and a warning sign appears next to the cluster IP address in the Infrastructure> Storage Resources page

If you perform operations continuously on the Veritas Access cluster, then some of the storage resources may appear as faulted and a warning sign appears next to the cluster IP address in the **Infrastructure**> **Storage Resources** page.

Workaround:

There is no action required. The warning sign disappears automatically after some time.

Creation of STU fails if the S3 user is changed

After you create a bucket, if you change the S3 user, the **Create STU** operation fails.

Workaround:

Map the bucket with the NetBackup server using the same S3 user name for which the storage server is created.

Software limitations

The following limitations relate to the SDS Management Platform.

- While setting the S3 parameters, the value of SSL should be set as Yes. Veritas Access supports S3 over HTTP only. Currently, Veritas Access has a limitation of not working with third-party signed certificates.
- If the S3 user is changed after bucket creation, then the Create STU operation fails.
- The SLP and backup policy should be already created and present on the NetBackup server.