

Veritas™ Cluster Server Agent for Sybase Installation and Configuration Guide

Solaris

6.0.1

Veritas Cluster Server Agent for Sybase Installation and Configuration Guide

The software described in this book is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Product version: VCS 6.0.1

Document version: 6.0.1 Rev 0

Legal Notice

Copyright © 2012 Symantec Corporation. All rights reserved.

Symantec, the Symantec logo, Veritas, Veritas Storage Foundation, CommandCentral, NetBackup, Enterprise Vault, and LiveUpdate are trademarks or registered trademarks of Symantec corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation
350 Ellis Street
Mountain View, CA 94043
<http://www.symantec.com>

Technical Support

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our Web site at the following URL:

www.symantec.com/business/support/index.jsp

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

Contacting Technical Support

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/contact_techsupp_static.jsp

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

- Product release level

- Hardware information
- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
 - Error messages and log files
 - Troubleshooting that was performed before contacting Symantec
 - Recent software configuration changes and network changes

Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs or manuals

Support agreement resources

If you want to contact Symantec regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan customercare_apac@symantec.com

Europe, Middle-East, and Africa semea@symantec.com

North America and Latin America [supportolutions@symantec.com](mailto:supportsolutions@symantec.com)

Documentation

Product guides are available on the media in PDF format. Make sure that you are using the current version of the documentation. The document version appears on page 2 of each guide. The latest product documentation is available on the Symantec Web site.

<https://sort.symantec.com/documents>

Your feedback on product documentation is important to us. Send suggestions for improvements and reports on errors or omissions. Include the title and document version (located on the second page), and chapter and section titles of the text on which you are reporting. Send feedback to:

doc_feedback@symantec.com

For information regarding the latest HOWTO articles, documentation updates, or to ask a question regarding product documentation, visit the Storage and Clustering Documentation forum on Symantec Connect.

<https://www-secure.symantec.com/connect/storage-management/forums/storage-and-clustering-documentation>

About Symantec Connect

Symantec Connect is the peer-to-peer technical community site for Symantec's enterprise customers. Participants can connect and share information with other product users, including creating forum posts, articles, videos, downloads, blogs and suggesting ideas, as well as interact with Symantec product teams and Technical Support. Content is rated by the community, and members receive reward points for their contributions.

<http://www.symantec.com/connect/storage-management>

Contents

Technical Support	4	
Chapter 1	Introducing the Veritas Cluster Server for Sybase	11
	About the Veritas Cluster Server for Sybase	11
	Supported software for the VCS agent for Sybase	12
	How the agent makes Sybase highly available	12
	How the Sybase and SybaseBk agents support intelligent resource monitoring	13
	About the Sybase agent functions	14
	Sybase agent functions	14
	SybaseBk agent functions	17
	Using the IPC Cleanup feature for the Sybase agent	18
	Monitoring options for the Sybase agent	20
	Monitoring Sybase instances running in Solaris 10 zones	21
	Action function for the VCS agent for Sybase	21
	Typical Sybase configuration in a VCS cluster	22
Chapter 2	Installing and configuring Sybase	25
	VCS requirements for installing Sybase	25
	Sybase installation directory	25
	SYBASE directory on shared disks	26
	System Group and User for Sybase home directory	26
	Database dbspaces	26
	Transparent TCP/IP failover	26
	Language settings for the Sybase agent	26
	Installing Sybase in a VCS environment	27
	Configuring Sybase for detail monitoring	27
Chapter 3	Installing, upgrading, and removing the agent for Sybase	31
	Before you install or upgrade the agent for Sybase	31
	Installing the agent for Sybase	32
	Disabling the agent for Sybase	33

	Removing the agent for Sybase	34
	Upgrading the agent for Sybase	35
Chapter 4	Configuring VCS service groups for Sybase	39
	About configuring service groups for Sybase	39
	Before configuring the service group for Sybase	40
	Importing the SybaseTypes.cf file	40
	Configuring the service groups for Sybase	42
	Configuring the service group for Sybase from Cluster Manager (Java console)	42
	Configuring the service group for Sybase using the command line	44
	Encrypting passwords for Sybase	46
	About setting up detail monitoring for the agent for Sybase	46
	Disabling detail monitoring for the agent for Sybase	47
	Enabling detail monitoring for the agent for Sybase	47
	Enabling and disabling intelligent resource monitoring for agents	48
	Administering the AMF kernel driver	50
Chapter 5	Administering VCS service groups for Sybase	53
	About administering service groups for Sybase	53
	Bringing the Sybase service group online	53
	Taking the Sybase service group offline	54
	Switching the Sybase service group	54
	Modifying the Sybase service group configuration	54
	Viewing the agent log for Sybase	55
Appendix A	Resource type definitions for Sybase	57
	About the resource type and attribute definitions for Sybase	57
	Sybase resource type	57
	Type definition for the Sybase agent	58
	Attribute definitions for the Sybase agent	58
	SybaseBk resource type	67
	Type definition for the SybaseBk agent	67
	Attribute definitions for the SybaseBk agent	68
Appendix B	Sample configurations for Sybase	75
	About the sample configuration for the Sybase agent	75
	Resource dependency graph for the Sybase agent	75

Resource dependency for Sybase configured in Solaris zones	76
Sample configuration for agent for Sybase on Solaris systems	78
Sample main.cf files for Sybase ASE CE configurations	80
Sample main.cf for a basic Sybase ASE CE cluster configuration under VCS control with shared mount point on CFS for Sybase binary installation	81
Sample main.cf for a basic Sybase ASE CE cluster configuration with local mount point on VxFS for Sybase binary installation	85
Sample main.cf for a primary CVM VVR site	89
Sample main.cf for a secondary CVM VVR site	96
Sample configuration for the Sybase agent in Solaris zones	102
Appendix C Changes introduced in previous releases	103
Changes introduced in the previous release	103
Index	105

Introducing the Veritas Cluster Server for Sybase

This chapter includes the following topics:

- [About the Veritas Cluster Server for Sybase](#)
- [Supported software for the VCS agent for Sybase](#)
- [How the agent makes Sybase highly available](#)
- [How the Sybase and SybaseBk agents support intelligent resource monitoring](#)
- [About the Sybase agent functions](#)
- [Monitoring options for the Sybase agent](#)
- [Action function for the VCS agent for Sybase](#)
- [Typical Sybase configuration in a VCS cluster](#)

About the Veritas Cluster Server for Sybase

The Veritas Cluster Server for Sybase brings the configured Sybase servers online, monitors them, and takes them offline.

For Sybase ASE enterprise edition, the following agents work together to make Sybase highly available in a VCS cluster.

- Agent for SQL Server- Sybase
- Agent for Backup Server- SybaseBk

The agents include type declarations and agent executables, and are represented with Sybase and SybaseBk resource types, respectively.

For Sybase ASE cluster edition, the VCS agent for Sybase makes Sybase adaptive server highly available in a VCS cluster. The VCS agent for Sybase backup server (SybaseBk agent) is not supported for Sybase ASE cluster edition.

Note: For ASE Enterprise Edition, the VCS agent for Sybase provides "active/passive" support. For "active/active" support for ASE Enterprise Edition, contact Sybase for their agent.

Supported software for the VCS agent for Sybase

The VCS for Sybase agent for Sybase supports the following software versions:

Sybase Sybase Adaptive Server Enterprise (ASE) Enterprise Edition 12.5.x and 15.x

 Sybase ASE cluster edition 15.5

Veritas Cluster Server VCS 6.0.1 on Solaris

Note: The Sybase cluster edition is not supported on HP-UX and AIX platforms.

Refer to the *Veritas Cluster Server Release Notes* for information on supported platform versions.

How the agent makes Sybase highly available

The Veritas Cluster Server agent for Sybase continuously monitors the Sybase database and SybaseBk processes to verify they function properly.

The agent for Sybase can perform different levels of monitoring and different actions which you can configure.

- **Primary or Basic monitoring:** In the basic monitoring mode, the agent detects an application failure if a configured Sybase server process is not running.
- **Detail monitoring:** In the optional detail monitoring mode, the agent detects application failure if it cannot perform a transaction in the test table in the Sybase database server.
- **Intelligent monitoring framework (IMF):** The Sybase agent also supports intelligent monitoring framework (IMF) in the process check mode of basic monitoring. The Sybase agent is IMF-aware and uses asynchronous monitoring framework (AMF) kernel driver for resource state change notifications.

See [“How the Sybase and SybaseBk agents support intelligent resource monitoring”](#) on page 13.

For Sybase cluster edition, the agent uses the Sybase-provided utility, `qrmutil`, to know if the status of the instance is up or down. If `qrmutil` reports the status as failure pending, the agent reboots the node and the instance is automatically started again.

When the Sybase agent detects that the configured Sybase server is not running on a system, based on the value of `OnlineRetryLimit` attribute of the Sybase server group, the service group is restarted on the same system on which the group faulted.

For ASE Enterprise edition when the agent detects that the configured Sybase server is not running on a system, the Sybase service group is failed over to the next available system in the service group's `SystemList`. The configured Sybase servers are started on the new system, thus ensuring high availability for the Sybase server and data.

How the Sybase and SybaseBk agents support intelligent resource monitoring

With intelligent monitoring framework (IMF), VCS supports intelligent resource monitoring in addition to the poll-based monitoring. Poll-based monitoring polls the resources periodically whereas intelligent monitoring performs asynchronous monitoring.

You can enable or disable the intelligent resource monitoring functionality of the VCS agents for Sybase and SybaseBk using `haimfconfig` script or manually.

See [“Enabling and disabling intelligent resource monitoring for agents”](#) on page 48.

When an IMF-enabled agent starts up, the agent initializes the asynchronous monitoring framework (AMF) kernel driver. After the resource is in a steady state, the agent registers the details that are required to monitor the resource with the AMF kernel driver. For example, the Sybase agent registers the PIDs of the processes with the AMF kernel driver. The agent's `imf_getnotification` function waits for any resource state changes. When the AMF kernel driver module notifies the `imf_getnotification` function about a resource state change, the agent framework runs the monitor agent function to ascertain the state of that resource. The agent notifies the state change to VCS which takes the appropriate action.

See the *Veritas Cluster Server Administrator's Guide* for more information.

About the Sybase agent functions

The functions an agent performs are called entry points. The Veritas agent for Sybase can perform different operations or functions on the database. These functions are online, offline, monitor, clean, and action.

Review the functions for the following agents that are part of the Veritas Cluster Server agent suite for Sybase:

- Sybase (SQL server) agent functions
See [“Sybase agent functions”](#) on page 14.
- SybaseBk (Backup Server) agent functions
See [“SybaseBk agent functions”](#) on page 17.

Sybase agent functions

The agent for Sybase starts a Sybase ASE dataserver, monitors the server processes, and shuts down the server.

The Sybase agent is IMF-aware.

[Table 1-1](#) lists the Sybase agent for SQL server functions.

Table 1-1 Sybase agent for SQL server functions

Agent function	Description
Online	<p>Starts the Sybase ASE dataserver by using the following command.</p> <pre>startserver -f \$SYBASE/\$SYBASE_ASE/install/RUN_\$Server</pre> <p>where \$Server is the instance_name, and \$SYBASE/\$SYBASE_ASE/install/RUN_\$Server is the default location of the Run server file. If you specify the value of the Run_ServerFile attribute, then the value that you specify is used instead of the default location.</p> <p>If the WaitForRecovery attribute is enabled, the agent waits either till recovery has been completed and all databases that can be made online are brought online. The agent queries the recovery status by connecting to the isql session. The OnlineTimeout attribute must be set to a sufficiently large value so that the recovery completes before the OnlineTimeout is reached.</p> <p>By default, the WaitForRecovery attribute is not enabled.</p> <p>If the interfaces file location is specified using the interfaces_File attribute, agent uses [-I interfaces file] option while connecting to the isql session.</p> <p>When DelayAfterOnline attribute is set, the monitor function is invoked after completion of online function, and after the number of seconds specified in DelayAfterOnline attribute have elapsed.</p>
Monitor	<p>In the basic monitoring mode, agent scans the process table for the dataserver process. In the detail monitoring mode, agent runs the script that is specified in MonScript as an option.</p> <p>The agent uses the Sybase provided utility, qrmutil, to know if the status of the instance is up or down. If qrmutil reports the status as failure pending, the agent reboots the node and the instance is automatically started again.</p> <p>See “Monitoring options for the Sybase agent” on page 20.</p>

Table 1-1 Sybase agent for SQL server functions (*continued*)

Agent function	Description
Offline	<p>Stops the Sybase SQL server by using the <code>isql</code> command in the following manner.</p> <p>If interfaces file location is specified using the <code>interfaces_File</code> attribute, agent uses the specified file while connecting to isql session.</p> <p>The agent first executes the <code>shutdown with wait</code> command.</p> <p>Sybase agent uses the <code>timeout</code> option during shutdown of Sybase dataserver if this option is supported.</p> <p>For Sybase ASE Enterprise edition the <code>timeout</code> option for shutdown command is supported for versions 12.5.4 and 15.0.2 onwards. If this <code>timeout</code> option is not supported for Sybase ASE Enterprise edition, the offline script waits in a loop till the dataserver completely stops. The agent waits for up to the <code>OfflineTimeout</code> duration. If the process is still running, the offline script issues a <code>shutdown with nowait</code> command.</p> <p>For Sybase ASE Cluster edition the <code>timeout</code> option for shutdown command is supported from versions 15.5 ESD #1 onwards. If the <code>timeout</code> option is not supported for Sybase ASE Cluster edition, the offline script waits in a loop till the dataserver completely stops. The agent waits for up to the <code>OfflineTimeout</code> duration. If the process is still running, the offline script kills it.</p> <p>When <code>DelayAfterOffline</code> attribute is set, the monitor function is invoked after completion of offline function and after the number of seconds specified in <code>DelayAfterOffline</code> attribute have elapsed.</p>
sybase_imf_init	<p>Initializes the agent to interface with the AMF kernel driver, which is the IMF notification module for Sybase agent. This function runs when the agent starts up.</p>
sybase_imf_register	<p>Registers or unregisters resource entities with the AMF kernel module. This function runs for each resource after the resource goes into steady state (online or offline).</p>
sybase_imf_getnotification	<p>Gets notification about resource state changes. This function runs after the agent initializes with the AMF kernel module. This function continuously waits for notification and takes action on the resource upon notification.</p>

Table 1-1 Sybase agent for SQL server functions (*continued*)

Agent function	Description
Clean	<p>Forcefully stops the Sybase SQL server by using the <code>isql</code> command in the following manner.</p> <p>The agent first executes the <code>shutdown with wait</code> command.</p> <p>For Sybase ASE Enterprise edition, if the <code>isql</code> command fails, the clean script executes the <code>shutdown with nowait</code> command. If the process does not respond to the <code>shutdown</code> command, the agent kills the Sybase <code>dataserver</code> process.</p> <p>For Sybase ASE Cluster edition, if the <code>shutdown with wait</code> command does not stop the <code>dataserver</code>, the agent directly proceeds to kill the <code>dataserver</code> process.</p>
Action	<p>Performs the predefined actions on a resource.</p> <p>See “Action function for the VCS agent for Sybase” on page 21.</p>

SybaseBk agent functions

The agent for SybaseBk starts a Sybase Backup server, monitors the server process, and shuts down the server.

The SybaseBk agent is IMF-aware.

[Table 1-2](#) lists the Sybase agent for Backup server functions.

Table 1-2 Sybase agent for Backup server functions

Agent operation	Description
Online	<p>Starts the Sybase Backup server by using the following command.</p> <pre>startserver -f \$SYBASE/\$SYBASE_ASE/ install/RUN_\$BackupServer</pre> <p>Where <code>\$SYBASE/\$SYBASE_ASE/install/RUN_\$BackupServer</code> is the default location of the Run server file. If you specify the value of the <code>Run_ServerFile</code> attribute, then the value that you specify is used instead of the default location.</p>

Table 1-2 Sybase agent for Backup server functions (*continued*)

Agent operation	Description
Monitor	Scans the process table for the backupserver process.
Offline	<p>Stops the Sybase Backup server by using the <code>isql</code> command in the following manner.</p> <p>If interfaces file location is specified using the <code>interfaes_File</code> attribute, agent uses the specified file while connecting to <code>isql</code> session.</p> <p>The agent first executes the command <code>shutdown SYB_BACKUP</code> with <code>wait</code>. If this command fails, the offline script executes <code>shutdown SYB_BACKUP</code> with <code>nowait</code>.</p>
Clean	<p>Forcefully stops the Sybase Backup server by using the <code>isql</code> command in the following manner.</p> <p>The agent first executes the command <code>shutdown SYB_BACKUP</code> with <code>wait</code>. If this command fails, the clean script executes <code>shutdown SYB_BACKUP</code> with <code>nowait</code>.</p> <p>If the process does not respond to the <code>shutdown</code> command, the agent scans the process table for the processes that are associated with the configured Sybase Backup server and kills them.</p>
SybaseBk_imf_init	Initializes the agent to interface with the AMF kernel driver, which is the IMF notification module for SybaseBk agent. This function runs when the agent starts up.
SybaseBk_imf_register	Registers or unregisters resource entities with the AMF kernel module. This function runs for each resource after the resource goes into steady state (online or offline).
SybaseBk_imf_getnotification	Gets notification about resource state changes. This function runs after the agent initializes with the AMF kernel module. This function continuously waits for notification and takes action on the resource upon notification.

Using the IPC Cleanup feature for the Sybase agent

When the Adaptive Server starts, it creates shared memory files in \$SYBASE to store information about the shared memory segments that it uses. Adaptive Server

start-up parameter `-M` can be used to change the location of directory that stores shared memory files. The start-up parameter `-M` should be updated in `RUN_$Server` file.

If the Sybase home directory is unmounted, the Sybase clean script cannot access the shared memory files and does not clean the IPC resources that are allocated by the Sybase processes. Hence, the agent requires shared memory files to be present in the following directory on local system `/var/tmp/sybase_shm/$Server`.

In the `$$SYBASE/$SYBASE_ASE/install` directory, edit the `RUN_$Server` file. Change the location of the directory that stores shared memory files to `/var/tmp/sybase_shm/$Server` using the `-M` option.

For example, the file `RUN_Sybase_Server` resembles the following before the change:

```
/home/sybase/ASE-15_0/bin/dataserver \  
  
-sSybase_Server \  
  
-d/home/sybase/data/master.dat \  
  
-e/home/sybase/ASE-15_0/install/Sybase_Server.log \  
  
-c/home/sybase/ASE-15_0/Sybase_Server.cfg \  
  
-M/home/sybase/ASE-15_0 \  

```

After the replacement, the file resembles:

```
/home/sybase/ASE-15_0/bin/dataserver \  
  
-sSybase_Server \  
  
-d/home/sybase/data/master.dat \  
  
-e/home/sybase/ASE-15_0/install/Sybase_Server.log \  
  
-c/home/sybase/ASE-15_0/Sybase_Server.cfg \  
  
-M/var/tmp/sybase_shm/Sybase_Server \  

```

Here `Sybase_Server` is the name of the Adaptive server.

Note: Make sure you create the `/var/tmp/sybase_shm/Sybase_Server` directory with proper permissions.

Monitoring options for the Sybase agent

The Veritas agent for Sybase provides two levels of application monitoring: basic and detail.

In the basic monitoring mode, the agent for Sybase monitors the Sybase daemon processes to verify whether they are running.

For Sybase cluster edition, the agent uses `qrmutil` utility that Sybase provides to get the status of the Sybase instance. If the state returned by `qrmutil` utility is 'failure pending', the agent panics the node. When the Sybase agent detects that the configured Sybase server is not running on a system, based on the value of the `OnlineRetryLimit` attribute of the Sybase service group, the service group is restarted on the same system on which the group faulted.

For example:

```
# qrmutil --quorum_dev=/quorum/quorum.dat --monitor=ase1
Executing 'monitor' command for instance 'ase1'
Instance 'ase1' has a failure pending.
# echo $?
99
```

In this example instance 'ase1' has a failure pending state. The agent will panic the node running the instance 'ase1'. The node will automatically rejoin the cluster after reboot.

In the detail monitoring mode, the agent performs a transaction on a test table in the database to ensure that Sybase functions properly. The agent uses this test table for internal purposes. Symantec recommends that you do not perform any other transaction on the test table.

See [“About setting up detail monitoring for the agent for Sybase”](#) on page 46.

For the Sybase ASE Enterprise edition, when the agent detects that the configured Sybase server is not running on a system, the Sybase service group is failed over to the next available system in the service group's `SystemList`. The configured Sybase servers are started on the new system, thus ensuring high availability for the Sybase server and data.

Monitoring Sybase instances running in Solaris 10 zones

VCS provides high availability to applications running in non-global zones by extending the failover capability to zones. VCS is installed in a global zone and all VCS agents and engine components run in the global zone. For applications running within non-global zones, agents run entry points inside the zones. If a zone configured under VCS control faults, VCS fails over the entire service group containing the zone.

For the Sybase ASE Enterprise edition, the VCS agent for Sybase is zone-aware and can monitor Sybase instances running in non-global zones.

Note: For Sybase ASE Cluster edition, the VCS agent for Sybase provides high availability to Sybase dataserver in global zone.

For more information on using zones in your VCS environment, refer to the *Veritas Cluster Server Administrator's Guide*.

Action function for the VCS agent for Sybase

The agent for Sybase supports the Action function, which enables you to perform predefined actions on a resource.

To perform an action on a resource, type the following command:

```
# hares -action res token [-actionargs arg1 ...] \  
[-sys system] [-clus cluster]
```

You can also add custom actions for the agent.

For more information, refer to the *Veritas Cluster Server Agent Developer's Guide*.

[Table 1-3](#) describes the agent's predefined action.

Table 1-3 Predefined agent action

Action	Description
checkpoint_all	Performs "checkpoint all" for the Sybase dataserver by connecting to isql session. Note: The checkpoint_all action function is not applicable for Sybase Cluster Edition.

Typical Sybase configuration in a VCS cluster

In a typical configuration, VCS is configured in a two node cluster. The Sybase data is installed on shared disks. The Sybase server binaries can be installed locally on both nodes or on shared disks. The agent for Sybase is installed on both the nodes. The shared disks can be managed using Veritas Volume Manager (VxVM).

Figure 1-1 illustrates a sample configuration in which the Sybase servers, including binaries and data are installed completely on shared disks or shared cluster disk groups managed using VxVM.

Figure 1-1 Sybase binaries and data on shared disks





Figure 1-2 illustrates a sample configuration in which Sybase binaries are installed locally on each node in the cluster and the Sybase data is on shared disks or shared cluster disk groups managed using VxVM.

Figure 1-2 Binaries on local disk and Sybase data on shared disks



Installing and configuring Sybase

This chapter includes the following topics:

- [VCS requirements for installing Sybase](#)
- [Installing Sybase in a VCS environment](#)
- [Configuring Sybase for detail monitoring](#)

VCS requirements for installing Sybase

Review the following requirements before you install Sybase in a VCS cluster. Before installing Sybase, make sure that the systems in the cluster have adequate resources to run Sybase and VCS.

Sybase installation directory

The Sybase installation directory can be located on a local disk or a shared storage.

Review the following prerequisites:

- If the Sybase binaries are installed on a local disk, verify that the installation path is same on all the nodes in the cluster. Make sure the Sybase configuration files are identical on all the nodes in the cluster.
- If the Sybase binaries are installed on shared disks, make sure the mount points for the shared disks are same on all the nodes. The Sybase installation directory is specified by the environment variable \$SYBASE. Create the same \$SYBASE mount points on each system.

SYBASE directory on shared disks

All database devices, including master devices, sybssystemprocs, and information about Sybase user must be located on shared disks. If the database devices are created on file systems, the file systems must also be located on shared disks. Create the same file system mount points on each system to access the shared disks.

For Sybase ASE cluster edition, use Storage Foundation clustered file system (SFCFS) for the Sybase ASE quorum device.

System Group and User for Sybase home directory

Make sure you have a system group and user, with the same name and ID, on all cluster nodes. Also, the system user should have the ownership of the Sybase home directory on the shared disk. Type the following commands:

```
# groupadd -g group_id group_name
# useradd -u user_id -g group_name user_name
# chown -R user_name:group_name $SYBASE
```

Database dbspaces

If you use shared disks for dbspaces, change the permissions, or access mode on the disk groups that store the Sybase data. Change the permissions for sybase to 660.

For example, if you use Veritas Volume Manager, type

```
# vxedit -g diskgroup_name set group=dba\
user=sybase mode=660 volume_name
```

Transparent TCP/IP failover

For Sybase server failover to be transparent to Sybase clients, create an IP address as part of the Sybase service group. This IP address must match the dataserver and backup server entries in the \$SYBASE/interfaces file.

For information on the format for adding entries to the \$SYBASE/interfaces file, refer to the Sybase documentation.

Language settings for the Sybase agent

For the Veritas agent for Sybase to function with the desired locale, make sure that the Sybase installation has the correct localization files. For example, if the

Sybase server requires 'LANG=en_US.UTF-8' environment variable, verify that the localization files corresponding to language 'en_US.UTF-8' are installed with Sybase.

Also, edit the file `$VCS_HOME/bin/vcsenv` to contain the following:

```
LANG=en_US.UTF-8;export LANG
```

This change affects all the agents that are configured on the nodes.

Installing Sybase in a VCS environment

For information on how to install Sybase, refer to Sybase documentation.

Configuring Sybase for detail monitoring

This section describes the tasks to be performed to configure a Sybase server for detail monitoring.

See [“About setting up detail monitoring for the agent for Sybase”](#) on page 46.

Note: The steps that are described here are specific to the sample script, `SqlTest.pl`, provided with the agent. If you use a custom script for detail monitoring, you must configure the Sybase database accordingly.

Perform these steps only once in a Sybase cluster.

To configure Sybase for detail monitoring

- 1 Source the `SYBASE.sh` file or `SYBASE.csh` file (depending on the user shell) to set the `$SYBASE` and `$SYBASE_ASE` environment variables.

- 2 Start the Sybase server.

```
# startserver -f ./SYBASE/$SYBASE_ASE/install/RUN_server_name
```

- 3 Start the Sybase client on any cluster node.

```
# isql -Usa -SSYBASE_SERVER_NAME
```

Enter the administrator password when prompted to do so.

- 4 Connect to the master database.

```
# use master
# go
```

5 Create a Sybase user account.

```
# sp_addlogin user_name, password  
# go
```

The detail monitor script should use this account to make transactions on the database.

6 Create a database.

```
# create database database_name  
# go
```

The detail monitor script should make transactions on this database.

7 If required, restrict the size of the log file for the database.

```
# sp_dboption database_name, "trunc log on chkpt", true  
# go
```

8 Connect to the database that is created in step 6.

```
# use database_name  
# go
```

9 Associate the user created in step 5 with the database created in step 6.

```
# sp_adduser user_name  
# go
```

10 Change the user to the one created in step 5.

```
# setuser user_name  
# go
```

11 Create a table in the database.

```
# create table table_name (lastupd datetime)  
# go
```

The detail monitor script should make transactions on this table.

If you use the SqlTest.pl for detail monitoring, make sure you create a table with a lastupd field of type datetime.

12 Verify the configuration by adding an initial value to the table.

```
# insert into table_name (lastupd) values (getdate())  
# go
```

13 Exit the database.

```
# exit
```


Installing, upgrading, and removing the agent for Sybase

This chapter includes the following topics:

- [Before you install or upgrade the agent for Sybase](#)
- [Installing the agent for Sybase](#)
- [Disabling the agent for Sybase](#)
- [Removing the agent for Sybase](#)
- [Upgrading the agent for Sybase](#)

Before you install or upgrade the agent for Sybase

Ensure that you meet the following prerequisites to install the Veritas agent for Sybase:

- Verify that VCS is installed and configured. If required, review the *Veritas Cluster Server Installation Guide*.
- Verify that Sybase is installed and configured on all cluster nodes on which you will install the agent. Review the Sybase documentation for more information.
See [“VCS requirements for installing Sybase”](#) on page 25.
- Verify that the sybase account is valid and identical on all cluster systems that will run Sybase. Verify that the sybase user account has permissions to execute Sybase binaries.

See [“System Group and User for Sybase home directory”](#) on page 26.

Installing the agent for Sybase

The agent binaries for Veritas Cluster Server agent for Sybase are a part of the VRTSvcsea package. The VRTSvcsea package is already installed if you chose to install all packages or recommended packages during VCS installation. You must manually install the VRTSvcsea package if you installed minimal packages during VCS installation. For Sybase ASE cluster edition, the VCS product installer installs the Sybase agent VRTSvcsea package along with other components

You can also install the Veritas Cluster Server agent for Sybase from the product disc.

Install the agent for Sybase on each node in the cluster.

To install the agent on Solaris systems

- 1 Log in as superuser.
- 2 Make sure that the agent is not already installed.

Navigate to `/opt/VRTSagents/ha/bin` and list the contents of the directory. If the command returns the VCS agents for Sybase, you can skip this procedure.

- 3 Create a temporary directory for installation.

```
# mkdir /tmp/install
```

- 4 Insert the software disc into the system's disc drive.

- If you are running Solaris volume-management software, the software automatically mounts the disc as `/cdrom/cdrom0`. Type the following to go to the location.

```
# cd /cdrom
```

- If you are not running Solaris volume-management software, you must mount the disc manually. For example,

```
# mount -F hsfs -o ro /dev/dsk/c0t6d0s2 /cdrom
```

In this example, `/dev/dsk/c0t6d0s2` is the default for the disc drive. After the disc is mounted, type the following command to go to the location.

```
# cd /cdrom
```


- 5 To navigate to the directory that contains the packages, and then install the agent, run the following commands:

```
# cd pkgs
```

Caution: The VRTSvcsea package includes the agent binaries for the Sybase agent. The package also installs the VCS agents for DB2 and Oracle.

```
# pkgadd -d VRTSvcsea.pkg
```

- 6 Copy the file SybaseTypes.cf from /etc/VRTSagents/ha/conf/Sybase/ directory to /etc/VRTSvcscs/conf/config directory.

To install the Japanese language pack on Solaris systems

- 1 After you have installed the agent, insert the "Language" disc into a drive connected to the system.
 - If you are running Solaris volume-management software, the software automatically mounts the disc as /cdrom/cdrom0. Type the following to go to the location.

```
# cd /cdrom
```

- If you are not running Solaris volume-management software, you must mount the disc manually. For example:

```
# mount -F hsfs -o ro /dev/dsk/c0t6d0s2 /cdrom
```

Where, in this example, /dev/dsk/c0t6d0s2 is the default for the disc drive. After the disc is mounted, type the following commands to go to the location.

```
# cd /cdrom
```

- 2 Install the Japanese package.

```
# pkgadd -d VRTSjacse.pkg
```

Disabling the agent for Sybase

To disable the agent on a system, you must first change the Sybase service group to an OFFLINE state. You can stop the application completely, or switch the service group to another system.

To disable the agent

- 1 Determine if the service group is online. At the prompt, type:

```
# hagrps -state service_group -sys system_name
```

- 2 If the service group is online, switch the service group to another system or take it offline. At the prompt, type:

```
# hagrps -switch service_group -to system_name
```

Or

```
# hagrps -offline service_group -sys system_name
```

- 3 Stop the agent on the system. At the prompt, type:

```
# haagent -stop Sybase -sys system_name  
# haagent -stop SybaseBk -sys system_name
```

- 4 When you get the message "Please look for messages in the log file," check the file `/var/VRTSvcS/log/engine_A.log` for a message confirming the agent has stopped.

You can also use the `ps` command to verify that the agent has stopped.

- 5 When the agent has stopped, you can remove the system, the service group, or the resource type from the VCS configuration.

For more information, refer to the chapter on reconfiguring VCS from the command line in *Veritas Cluster Server Administrator's Guide*.

Removing the agent for Sybase

This section provides steps to remove the agent from the cluster.

Warning: The VRTSvcsea package includes the VCS agents for Oracle, Sybase, and DB2. So, the following procedure to remove the VCS agent for Sybase removes all the other agents also.

To remove the agent for Sybase

- 1 Take the Sybase and SybaseBk resources offline.
- 2 Stop the agent for Sybase.

```
# haagent -stop Sybase -sys system_name
```

Perform this step on all nodes on which the agent for Sybase is running.

- 3 Stop the agent for SybaseBk.

```
# haagent -stop SybaseBk -sys system_name
```

Perform this step on all nodes on which the agent for SybaseBk is running.

- 4 Type the following command to remove the agent from all nodes in the cluster. Answer prompts accordingly.

```
# pkgrm VRTSvcsea
```

If you installed the Japanese language package, type the following command:

```
# pkgrm VRTSjacse
```

Upgrading the agent for Sybase

This section describes the procedure to upgrade the Veritas agent for Sybase in a Veritas Cluster Server (VCS) cluster. Execute the following steps on each node of the VCS cluster.

Note: You can upgrade the VCS agent for Sybase from versions 5.0, 5.1, 6.0, to 6.0.1. See [“Installing the agent for Sybase”](#) on page 32.

To upgrade the VCS agent for Sybase

- 1 Save the VCS configuration and stop the VCS engine.

```
# haconf -dump -makero  
# hastop -all -force
```

- 2 Back up the configuration file, `main.cf` to a location on the cluster node.
- 3 Based on your current VCS Agent version for Sybase, perform the appropriate steps on all systems that have the agent installed:

To	Perform the following steps
Upgrade the VCS agent from a version earlier than 5.1	<ol style="list-style-type: none"><li data-bbox="585 279 1208 390">1 Remove the VCS agent for Sybase, by using the following command: <pre data-bbox="635 361 852 383"># pkgrm VRTSvcssy</pre><li data-bbox="585 425 1208 536">2 If you installed the Japanese language package, use the following command: <pre data-bbox="635 508 852 531"># pkgrm VRTSjacss</pre><li data-bbox="585 569 1208 680">3 Take backup of SybaseTypes.cf <pre data-bbox="635 621 1208 673"># mv /etc/VRTSvcs/conf/config/SybaseTypes.cf /etc/VRTSvcs/conf/config/SybaseTypes.cf_bkp</pre><li data-bbox="585 713 1208 788">4 Navigate to the directory that contains the packages: <pre data-bbox="635 765 749 788"># cd pkgs</pre><li data-bbox="585 829 1208 1010">5 Install the VCS agent for Sybase by running the following command: Caution: If you run the following command, the VCS agents for Oracle and DB2 are also upgraded. <pre data-bbox="635 986 888 1008"># pkgadd -d VRTSvsea</pre>

- | | |
|-----------|------------------------------------|
| To | Perform the following steps |
|-----------|------------------------------------|
- Upgrade the VCS agent from 5.1 or later
- 1** Remove the VCS agent for Sybase using the following command:

```
# pkgrm VRTSvcsea
```
 - 2** If you have installed the Japanese language package, run the following command:

```
# pkgrm VRTSjacse
```
 - 3** Take backup of SybaseTypes.cf

```
# mv /etc/VRTSvcscs/conf/config/SybaseTypes.cf /etc/VRTSvcscs/conf/config/SybaseTypes.cf_bkp
```
 - 4** Navigate to the directory that contains the packages:

```
# cd pkgs
```
 - 5** Install the VCS agent for Sybase by running the following command:
Caution: If you run the following command, the VCS agents for Oracle and DBw are also upgraded.

```
# pkgadd -d VRTsvsea.pkg
```
- 4** Make sure that you have copied the SybaseTypes.cf file from the /etc/VRTSagents/ha/conf/Sybase/ directory to /etc/VRTSvcscs/conf/config directory.
- Make sure to update the newly copied SybaseTypes.cf file with all the type-level changes that you had made to the older SybaseTypes.cf file.
- For example, if you had changed the value of the MonitorInterval attribute from the default 60 to 120 seconds, the SybaseTypes.cf file gets updated. You must apply these type-level changes manually to the newly copied SybaseTypes.cf file.
- 5** Copy the main.cf file from the backed up location to /etc/VRTSvcscs/conf/config directory.
 - 6** Edit the main.cf file located under /etc/VRTSvcscs/conf/config.
 - If you configured detail monitoring, make sure the Monscript attribute of the Sybase resource type is properly configured.

- Remove the Monscript attribute for the SybaseBk resource type, if configured.
 - Replace the password specified for the SAPswd attribute (of Sybase and SybaseBk resources) and UPword attribute (of Sybase resource) with encrypted passwords.
See [“Encrypting passwords for Sybase”](#) on page 46.
 - Save the main.cf file.
- 7** Verify the configuration.
- ```
cd /etc/VRTSvcs/conf/config
hacf -verify
```
- 8** Start VCS on the local node.
- 9** Start VCS on the other nodes.

# Configuring VCS service groups for Sybase

This chapter includes the following topics:

- [About configuring service groups for Sybase](#)
- [Before configuring the service group for Sybase](#)
- [Configuring the service groups for Sybase](#)
- [Configuring the service group for Sybase from Cluster Manager \(Java console\)](#)
- [Configuring the service group for Sybase using the command line](#)
- [Encrypting passwords for Sybase](#)
- [About setting up detail monitoring for the agent for Sybase](#)
- [Enabling and disabling intelligent resource monitoring for agents](#)
- [Administering the AMF kernel driver](#)

## About configuring service groups for Sybase

Configuring the Sybase service group involves configuring service group resources and defining attribute values for the configured resources. You must have administrator privileges to create and configure a service group. Before you configure the agent, review the Sybase resource types and their attributes.

## Before configuring the service group for Sybase

Before you configure the Sybase service group, you must meet the following prerequisites:

- Verify that VCS is installed and configured on all nodes in the cluster where you plan to configure the service group. For more information on installing VCS see the *Veritas Cluster Server Installation Guide*.

---

**Caution:** In Sybase cluster edition, the Sybase agent assumes that the **membership-mode** is set to **vcs**. When Sybase instances are configured under VCS control, the installer automatically sets the **membership-mode** to **vcs**. If the Sybase server instances are configured manually under VCS control or if the quorum device is rebuilt in 'native' mode, ensure that the **membership-mode** is set to **vcs**.

---

- Verify that Sybase is installed and configured identically on all nodes in the cluster.  
See [“VCS requirements for installing Sybase”](#) on page 25.
- Verify that the Veritas agent for Sybase is installed on all nodes in the cluster.  
See [“Installing the agent for Sybase”](#) on page 32.
- Verify the type definition for Veritas agent for Sybase is imported into the VCS engine.  
See [“Importing the SybaseTypes.cf file”](#) on page 40.

---

**Note:** From VCS 6.0 onwards, you need not encrypt passwords if you use the VCS Cluster Manager (Java Console) to configure attributes.

---

---

**Caution:** If you do not set the `Quorum_dev` attribute for Sybase Cluster Edition, the Sybase agent does not perform the `qrmutil`-based checks. This error in configuration may lead to undesirable results. For example, if `qrmutil` returns failure pending, the agent does not panic the system. Thus, the Sybase agent does not perform `qrmutil`-based checks because the `Quorum_dev` attribute is not set.

---

## Importing the SybaseTypes.cf file

Before you configure the Sybase service group, you must import the `SybaseTypes.cf` file to the VCS engine.



---

**Note:** Before you start the following procedure, for more instructions on Java GUI, refer to the *Veritas Cluster Server 6.0.1 Installation Guide*.

---

#### To import the SybaseTypes.cf file using the Cluster Manager (Java Console)

- 1 On one of the nodes in the cluster, start the Cluster Manager (Java Console).
- 2 Log in to the cluster and wait for the Cluster Explorer to launch.
- 3 From the **File** menu select **Import Types**. Switch to the read/write mode if prompted.
- 4 In the Import Types dialog box, select the file:

```
/etc/VRTSagents/ha/conf/Sybase/SybaseTypes.cf
```

- 5 Click **Import** and wait for the file to import.
- 6 Save the configuration.

#### To import the SybaseTypes.cf file using the command line

- 1 Log in to a cluster system as superuser.
- 2 Make the cluster configuration as read-only. This action ensures that all changes to the existing configuration have been saved and further changes are prevented while you modify main.cf:

```
haconf -dump -makero
```

- 3 To ensure that VCS is not running while you edit main.cf, issue the following command to stop the VCS engine on all systems. Leave the resources that are available online.

```
hstop -all -force
```

- 4 Make a backup copy of the main.cf file.

```
cd /etc/VRTSvcs/conf/config
cp main.cf main.cf.orig
```

- 5 Edit the main.cf file to include the SybaseTypes.cf file.

```
include "/etc/VRTSagents/ha/conf/Sybase/SybaseTypes.cf"
```

The Sybase types definition is imported to the VCS engine. The agent for Sybase can be configured without interrupting or stopping VCS.

## Configuring the service groups for Sybase

You can configure the service groups for Sybase using the following methods:

- By using VCS Cluster Manager (Java Console) to edit a resource group template for the agent.  
See [“Configuring the service group for Sybase from Cluster Manager \(Java console\)”](#) on page 42.
- By using the types configuration files and directly editing the sample main.cf file supplied with the agent. This method requires you to restart VCS before the configuration takes effect.  
See [“Configuring the service group for Sybase using the command line”](#) on page 44.
- By using the Veritas Operations Manager (VOM).  
For more information, see VOM documentation.

## Configuring the service group for Sybase from Cluster Manager (Java console)

A template for the Sybase resource groups is automatically installed with the Veritas agent for Sybase. Using the VCS cluster Manager (Java console), you can view the template, which displays the Sybase service group, its resources and their attributes. You can dynamically modify the attributes' values as necessary for your configuration.

---

**Note:** Before you start the following procedure, for more instructions on Java GUI, refer to the *Veritas Cluster Server 6.0.1 Installation Guide*.

---

### To configure a service group from the Java console

- 1 Make sure that the Sybase type definition file SybaseTypes.cf is imported in your configuration.  
See [“Configuring the service groups for Sybase”](#) on page 42.
- 2 Launch the Cluster Configuration wizard using any of the following ways:
  - From the Cluster Explorer menu, select **Tools > Configuration Wizard**.
  - If no service groups exist on the system, Cluster Explorer prompts you to launch the Cluster Configuration wizard. Click **Yes** when prompted.The Loading Templates Information window appears, and launches the wizard.
- 3 Review the information in the Welcome dialog box and click **Next**.



- 4 Click **OK**.
- 5 Repeat the procedure for each resource and click **Finish**. Edit the attributes for all the resources according to your configuration.
- 6 Follow the wizard instructions to complete the configuration. Click **Finish** to quit the wizard.

---

**Caution:** For added security, you must always provide a secure value for passwords.

---

See [“Encrypting passwords for Sybase”](#) on page 46.

## Configuring the service group for Sybase using the command line

The Veritas agent for Sybase contains a sample configuration file that can be used as reference to directly modify your present configuration file. This method requires you to restart VCS before the configuration takes effect.

### To configure a service group for Sybase from the command line

- 1 Log in to a cluster system as superuser.
- 2 Make sure the Sybase type definition is imported into VCS engine.  
See [“Configuring the service groups for Sybase”](#) on page 42.
- 3 Edit the main.cf file at `/etc/VRTSvcs/conf/config/main.cf`. For reference, use the sample files at `/etc/VRTSagents/ha/conf/Sybase`.
  - Create a Sybase service group.
  - Create the Sybase and SybaseBk resources.  
See [“Sybase resource type”](#) on page 57.  
See [“SybaseBk resource type”](#) on page 67.
  - Edit the default attributes to match the parameters in your configuration.  
For added security, you must always provide a secure value for passwords.  
See [“Encrypting passwords for Sybase”](#) on page 46.
  - Assign dependencies to the newly created resources. Refer to the sample file at `/etc/VRTSagents/ha/conf/Sybase/`.  
See the *Veritas Cluster Server Administrator’s Guide* for more information on assigning dependencies.
- 4 Save and close the file.

- 5** Verify the syntax of the file `/etc/VRTSvcs/conf/config/main.cf`

```
cd /etc/VRTSvcs/conf/config
hacf -verify .
```

- 6** Start VCS on the local node.

```
hstart
```

- 7** Start VCS on the other nodes.

- 8** If the system is listed in `AutoStartList` attribute of the Sybase service group, verify that all Sybase service group resources are brought online.

```
hagr -state
```

- 9** Take the service group offline and verify that all the resources are stopped.

```
hagr -offline service_group -sys system_name
hagr -state
```

- 10** Bring the service group online again and verify that all the resources are available.

```
hagr -online service_group -sys system_name
hagr -state
```

- 11** Switch the Sybase service group to the other node.

```
hagr -switch service_group -to system_name
```

- 12** Verify that all Sybase service group resources are brought online on the other node.

```
hagr -state
```

- 13** On all systems, look at the following log files for any errors or status.

```
/var/VRTSvcs/log/engine_A.log
/var/VRTSvcs/log/Sybase_A.log
/var/VRTSvcs/log/SybaseBk_A.log
```

## Encrypting passwords for Sybase

VCS provides a `vcscrypt` utility to encrypt user passwords. Encrypt passwords before specifying them for Sybase and SybaseBk resource type definition.

The `vcscrypt` utility also allows you to encrypt the agent passwords using a security key. The security key supports AES (Advanced Encryption Standard) encryption which creates a more secure password for the agent. See the *Veritas Cluster Server Administrator's Guide* for more information.

### To encrypt passwords

- 1 From the path `$VCS_HOME/bin/`, run the `vcscrypt` utility.
- 2 Type the following command.

```
vcscrypt -agent
```

The utility prompts you to enter the password twice. Enter the password and press Return.

```
Enter Password:
Enter Again:
```

- 3 The utility encrypts the password and displays the encrypted password.
- 4 Enter this encrypted password as the value for the attribute.

Copy the encrypted password for future reference.

## About setting up detail monitoring for the agent for Sybase

The Veritas agent for Sybase provides two levels of application monitoring: basic and detail. In basic monitoring, Sybase resource monitors the Sybase daemon processes to verify that they are continuously active.

In detail monitoring, the Sybase resource performs transactions on a test table in the database to ensure that the Sybase server functions properly. The agent uses this test table for internal purposes. Symantec recommends that you do not perform any other transaction on the test table. The agent uses the script that is defined in the attribute `Monscript` of the Sybase resource. During detail monitoring, the agent executes the specified script. If the script successfully executes, the agent considers the database available. You can customize the default script according to your configurations.

To activate detail monitoring, the `LevelTwoMonitorFreq` attribute must be set to a positive integer and `User`, `UPword`, `Db`, and `Table` attributes must not be empty (""). The attribute `Monscript`, which contains the path of the detail monitor script, must also exist and must have execute permissions for the root.

## Disabling detail monitoring for the agent for Sybase

- 1 Make the VCS configuration writable with:

```
haconf -makerw
```

- 2 To disable detail monitoring for Sybase run the following command:

```
hatype -modify Sybase LevelTwoMonitorFreq 0
```

- 3 Save the configuration with:

```
haconf -dump -makero
```

## Enabling detail monitoring for the agent for Sybase

Perform the following steps to enable detail monitoring on a database.

### To enable detail monitoring

- 1 Make sure the Sybase server is configured for detail monitoring.

See [“Configuring Sybase for detail monitoring”](#) on page 27.

- 2 Make the VCS configuration writable.

```
haconf -makerw
```

### 3 Enable detail monitoring for Sybase.

```
hatype -modify Sybase LevelTwoMonitorFreq <value>
hares -modify Sybase_resource User user_name
hares -modify Sybase_resource UPword encrypted-password
hares -modify Sybase_resource Db database_name
hares -modify Sybase_resource Table table_name
hares -modify Sybase_resource Monscript
"/opt/VRTSagents/ha/bin/Sybase/SqlTest.pl"
```

---

**Note:** To enable detail monitoring, the `LevelTwoMonitorFreq` attribute must be set to a positive value. You can also override the value of this attribute at the resource level.

---

### 4 Save the configuration.

```
haconf -dump -makero
```

---

**Note:** If detail monitoring is configured and the database is full, the SQL queries take considerable time to commit the results. In such a case, the monitor routine for the agent fails and attempts to fail over the service group. This issue is not encountered if detail monitoring is not configured.

---

## Enabling and disabling intelligent resource monitoring for agents

Review the following procedures to enable or disable intelligent resource monitoring manually. The intelligent resource monitoring feature is enabled by default. The IMF resource type attribute determines whether an IMF-aware agent must perform intelligent resource monitoring.

---

**Note:** VCS provides `haimfconfig` script to enable and disable IMF for agents. You can use the script when VCS is running or when VCS is stopped. Use the script to enable or disable IMF for the IMF-aware bundled agents, enterprise agents, and custom agents.

---

For additional information, refer to *Enabling and disabling IMF for agents by using script* section in *Veritas Cluster Server Administrator's Guide*.



See [“How the Sybase and SybaseBk agents support intelligent resource monitoring”](#) on page 13.

### To enable intelligent resource monitoring

- 1 Make the VCS configuration writable.

```
haconf -makerw
```

- 2 Run the following command to enable intelligent resource monitoring.

- To enable intelligent monitoring of offline resources:

```
hatype -modify resource_type IMF -update Mode 1
```

- To enable intelligent monitoring of online resources:

```
hatype -modify resource_type IMF -update Mode 2
```

- To enable intelligent monitoring of both online and offline resources:

```
hatype -modify resource_type IMF -update Mode 3
```

You can also change the values of the MonitorFreq key and the RegisterRetryLimit key of the IMF attribute.

See [“Attribute definitions for the Sybase agent”](#) on page 58.

See [“Attribute definitions for the SybaseBk agent”](#) on page 68.

- 3 Save the VCS configuration

```
haconf -dump -makero
```

- 4 Make sure that the AMF kernel driver is configured on all nodes in the cluster.

- On Solaris 10:

```
■ svcs -l amf
```

Configure the AMFdriver if the command output returns that the AMFdriver is not loaded or not configured.

See [“Administering the AMF kernel driver”](#) on page 50.

- 5 Restart the agent. Run the following commands on each node.

```
haagent -stop agent_name -force -sys sys_name
haagent -start agent_name -sys sys_name
```

### To disable intelligent resource monitoring

- 1 Make the VCS configuration writable.

```
haconf -makerw
```

- 2 To disable intelligent resource monitoring for all the resources of a certain type, run the following command:

```
hatype -modify Sybase IMF -update Mode 0
```

- 3 To disable intelligent resource monitoring for a specific resource, run the following command:

```
hares -override resource_name IMF
hares -modify resource_name IMF -update Mode 0
```

- 4 Save the VCS configuration.

```
haconf -dump -makero
```

---

**Note:** For Sybase cluster edition, the agent performs a monitoring check based on `qrmutil` whenever the monitor entry point is executed, either because `IMF MonitorFreq` is reached or `LevelTwoMonitorFreq` is reached. For example, if `IMF MonitorFreq` is set to a higher value such as 10, monitoring check based on `qrmutil` is performed after 10 x `MonitorInterval` seconds.

---

## Administering the AMF kernel driver

Perform the following procedures to start or stop the MF kernel driver.

### To start the AMF kernel driver

- 1 Set the value of the `AMF_START` variable to 1 in the following file:

```
/etc/default/amf
```

- 2 Start the AMF kernel driver. Run the following command:

- On Solaris 10:

```
svcadm enable amf
```

### To stop the AMF kernel driver

1 Run the following command:

- On Solaris 10:

```
svcadm disable -t amf
```

2 Set the value of the AMF\_START variable to 0 (zero) in the following file:

```
/etc/default/amf
```



# Administering VCS service groups for Sybase

This chapter includes the following topics:

- [About administering service groups for Sybase](#)
- [Bringing the Sybase service group online](#)
- [Taking the Sybase service group offline](#)
- [Switching the Sybase service group](#)
- [Modifying the Sybase service group configuration](#)
- [Viewing the agent log for Sybase](#)

## About administering service groups for Sybase

You can administer service groups with the Cluster Manager (Java Console), the Veritas Operations Manager, or from the command line. The following procedures use the Cluster Manager (Java Console).

## Bringing the Sybase service group online

Perform the following steps to bring a service group online. Note that in the initial few cycles of bringing a service group online, the memory usage by the agent can spike.

#### To bring a service group online

- 1 From Cluster Explorer, click the **Service Groups** tab in the configuration tree.
- 2 Right-click the service group and click **Enable Resources** to enable all the resources in this group.
- 3 Right-click the service group, hover over **Enable**, and select either the node or all the nodes where you want to enable the service group.
- 4 Save and close the configuration. Click **File > Save Configuration**, then **Close Configuration**.
- 5 Right-click the service group, pause over **Online**, and select the system where you want to bring the service group online.

## Taking the Sybase service group offline

Perform the following procedure from Cluster Manager (Java Console) to take the service group offline. Note that in the initial few cycles of taking a service group offline, the agent's memory usage can spike.

#### To take a service group offline

- 1 In the Cluster Explorer configuration tree with the Service Groups tab selected, right-click the service group that you want to take offline.
- 2 Choose **Offline**, and select the appropriate system from the pop-up menu.

## Switching the Sybase service group

The process of switching a service group involves taking it offline on its current system and bringing it online on another system. Perform the following procedure from Cluster Manager (Java Console) to switch the service group.

#### To switch a service group

- 1 In the Cluster Explorer configuration tree with the Service Groups tab selected, right-click the service group.
- 2 Choose **Switch To**, and select the appropriate system from the pop-up menu.

## Modifying the Sybase service group configuration

You can dynamically modify the Sybase agent using several methods, including the Cluster Manager (Java Console), Veritas Operations Manager, and the command line.

See the *Veritas Cluster Server Administrator's Guide* for more information.

## Viewing the agent log for Sybase

The VCS agent for Sybase logs messages to the following files:

`/var/VRTSvcs/log/engine_A.log`

`/var/VRTSvcs/log/Sybase_A.log`

`/var/VRTSvcs/log/SybaseBk_A.log`





# Resource type definitions for Sybase

This appendix includes the following topics:

- [About the resource type and attribute definitions for Sybase](#)
- [Sybase resource type](#)
- [SybaseBk resource type](#)

## About the resource type and attribute definitions for Sybase

The resource type represents the VCS configuration definition of the agent. It also specifies how the configuration file, `main.cf`, defines the agent. Configuring the agent involves assigning values to the resource type attributes.

For the resource type attributes:

See “[Attribute definitions for the Sybase agent](#)” on page 58.

See “[Attribute definitions for the SybaseBk agent](#)” on page 68.

For the sample `main.cf` configuration files:

See “[Sample configuration for agent for Sybase on Solaris systems](#)” on page 78.

## Sybase resource type

The type definitions and attribute definitions for the Sybase resource type are described as follows.

## Type definition for the Sybase agent

The resource type definition for the agent for Sybase is as follows.

```
type Sybase (
 static boolean AEPTIMEOUT = 1
 static keylist SupportedActions = { "checkpoint_all" }
 str Server
 str Owner
 str Home
 str Version
 str SA
 str SAPswd
 str Run_ServerFile
 int DetailMonitor = 0
 str User
 str UPword
 str Db
 str Table
 str Monscript = "/opt/VRTSagents/ha/bin/Sybase/SqlTest.pl"
 boolean WaitForRecovery = 0
 str Quorum_dev
 str interfaces_File
 int ShutdownWaitLimit = 60
 int DelayAfterOnline = 10
 int DelayAfterOffline = 2
 static int ToleranceLimit = 1
 static str ArgList[] = { Server, Owner, Home, Version, SA,
 SAPswd, User, UPword, Db, Table, Monscript, DetailMonitor,
 WaitForRecovery, Run_ServerFile, Quorum_dev, State,
 interfaces_File, ShutdownWaitLimit, DelayAfterOnline,
 DelayAfterOffline }
 static int IMF{} = { Mode=3, MonitorFreq=5, RegisterRetryLimit=3 }
 static str IMFRegList[] = { Server, Owner, Quorum_dev }
 static int ContainerOpts{} = { RunInContainer=1, PassCInfo=0 }
 static str AgentDirectory = "/opt/VRTSagents/ha/bin/Sybase"
)
```

## Attribute definitions for the Sybase agent

Review the description of the Sybase agent attributes. The agent attributes are classified as required, optional, and internal.

[Table A-1](#) lists the required attributes.

**Table A-1** Required attributes

| Required Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|---------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Server              | <p>The \$DSQUERY ASE name. Only one server should be configured in a Sybase service group. The advantage of configuring Sybase resources in a separate service group is, each Sybase data server can failover independently.</p> <p>When multiple Sybase resources are configured in a single service group, even if one of the “n” data servers fail, the whole service group will be failed over.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p> |
| Owner               | <p>Sybase user as the defined owner of executables and database files in any of the sources (such as NIS+, /etc/hosts, and so on) specified in the /etc/nsswitch.conf file for passwd entry. The Sybase executables and database files are accessed in the context of this user.</p> <p>Type and dimension: string-scalar</p> <p>See “<a href="#">System Group and User for Sybase home directory</a>” on page 26.</p>                                                                  |
| Home                | <p>The \$SYBASE path to Sybase binaries and configuration files.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p>                                                                                                                                                                                                                                                                                                                                    |
| Version             | <p>Version of Sybase ASE.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p> <p><b>Caution:</b> Once the Sybase resource is online in VCS, you must not modify the Home and Version attributes. For the Sybase cluster edition, setting invalid values for Home and Version attributes when the resource is in Online state causes the node to panic.</p>                                                                                              |
| SA                  | <p>Sybase database administrator. This attribute is required to connect to the ASE for shutdown.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p>                                                                                                                                                                                                                                                                                                    |

**Table A-1** Required attributes (*continued*)

| Required Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| SApswd              | <p>Encrypted password for Sybase database administrator. This password is required to connect to the ASE for shutdown.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p> <p>See “<a href="#">Encrypting passwords for Sybase</a>” on page 46.</p> <p><b>Note:</b> You need not specify a value for this attribute if the SA user does not require a password.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
| Quorum_dev          | <p>The quorum device manages the cluster membership, stores cluster configuration data, and contains information shared among server instances and nodes. The quorum device is a disk that is accessible to all the nodes in the cluster. Specify a fully qualified quorum device name.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p> <p>Note: This attribute should be specified only for the cluster edition.</p> <p><b>Caution:</b> If you do not set the Quorum_dev attribute for Sybase Cluster Edition, the Sybase agent does not perform the qrmutil-based checks. This error in configuration may lead to undesirable results. For example, if qrmutil returns failure pending, the agent does not panic the system. Thus, the Sybase agent does not perform qrmutil-based checks because the Quorum_dev attribute is not set.</p> |

[Table A-2](#) lists the optional attributes.

**Table A-2** Optional attributes

| Optional Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| DetailMonitor       | <p>Specifies whether the Sybase server is monitored in detail. A positive integer value indicates that the resource monitors the Sybase server in detail. Value 0 denotes it does not. Default is 0.</p> <p>Type and dimension: int-scalar</p> <p><b>Note:</b> The DetailMonitor attribute is deprecated in VCS 6.0.1. Instead, LevelTwoMonitorFreq attribute of Sybase agent may be used. The default value of LevelTwoMonitorFreq attribute is 0 (zero).</p> |
| User                | <p>The database user, in the context of which, the transactions are performed on the database. You must specify a value for this attribute if LevelTwoMonitorFreq is set to a positive integer value.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p>                                                                                                                                                                      |
| UPword              | <p>Encrypted password for the database user. You must specify a value for this attribute if LevelTwoMonitorFreq is set to a positive integer value. However, you need not specify a value for this attribute if the database user does not require a password.</p> <p>See <a href="#">“Encrypting passwords for Sybase”</a> on page 46.</p> <p>intercType and dimension: string-scalar</p> <p>Default value: No default value</p>                              |
| Db                  | <p>Name of the database used for detailed monitoring. The table used by the detail monitor script resides in this database. You must specify a value for this attribute if LevelTwoMonitorFreq is set to a positive integer value.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p>                                                                                                                                         |
| Table               | <p>Name of the table on which the detail monitoring script performs the transactions. You must specify a value for this attribute if LevelTwoMonitorFreq is set to a positive integer value.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p>                                                                                                                                                                               |

**Table A-2** Optional attributes (*continued*)

| Optional Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Monscript           | <p>The path to the detail monitor script; the default value for this attribute is the path for the script, SqlTest.pl, provided with the agent. You must specify a value for this attribute if LevelTwoMonitorFreq is set to a positive integer value.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p> <p><b>Note:</b> By default, SqlTest.pl script has the execute permission set. If you specify custom detail monitor script, ensure that custom detail monitor script also has the execute permissions set.</p> |
| WaitForRecovery     | <p>The recovery procedures rebuild the server's databases from the transaction logs. This boolean attribute indicates if the agent should wait during Online agent function, till recovery has been completed and all databases that can be made online are brought online. This feature is not supported for pre-12.5.1 Sybase ASE server.</p> <p>Type and dimension: boolean-scalar</p> <p>Default value: 0</p>                                                                                                                                        |
| Run_ServerFile      | <p>Specifies the location of the RUN_SERVER file for the Sybase instance. The default location of this file is used if no value is specified for this attribute.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p>                                                                                                                                                                                                                                                                                                     |

**Table A-2** Optional attributes (*continued*)

| Optional Attributes | Definition |
|---------------------|------------|
| IMF                 |            |

**Table A-2** Optional attributes (*continued*)

| Optional Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                     | <p>This resource-type level attribute determines whether the Sybase agent must perform intelligent resource monitoring. You can also override the value of this attribute at resource-level.</p> <p>This attribute includes the following keys:</p> <ul style="list-style-type: none"> <li>■ <b>Mode:</b> Define this attribute to enable or disable intelligent resource monitoring.<br/> Valid values are as follows: <ul style="list-style-type: none"> <li>■ 0—Does not perform intelligent resource monitoring</li> <li>■ 1—Performs intelligent resource monitoring for offline resources and performs poll-based monitoring for online resources</li> <li>■ 2—Performs intelligent resource monitoring for online resources and performs poll-based monitoring for offline resources</li> <li>■ 3—Performs intelligent resource monitoring for both online and for offline resources</li> </ul> Default: 3</li> <li>■ <b>MonitorFreq:</b> This key value specifies the frequency at which the agent invokes the monitor agent function. The value of this key is an integer.<br/> Default: 5<br/> You can set this key to a non-zero value for cases where the agent requires to perform both poll-based and intelligent resource monitoring. If the value is 0, the agent does not perform poll-based process check monitoring.<br/> After the resource registers with the AMF kernel driver, the agent calls the monitor agent function as follows: <ul style="list-style-type: none"> <li>■ After every (MonitorFreq x MonitorInterval) number of seconds for online resources</li> <li>■ After every (MonitorFreq x OfflineMonitorInterval) number of seconds for offline resources</li> </ul> </li> <li>■ <b>RegisterRetryLimit:</b> If you enable intelligent resource monitoring, the agent invokes the <code>sybase_imf_register</code> agent function to register the resource with the AMFkernel driver. The value of the RegisterRetryLimit key determines the number of times the agent must retry registration for a resource. If the agent cannot register the resource within the limit that is specified, then intelligent monitoring is disabled until the resource state changes or the value of the Mode key changes.<br/> Default: 3</li> </ul> |



**Table A-2** Optional attributes (*continued*)

| Optional Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                     | <p>See “<a href="#">Enabling and disabling intelligent resource monitoring for agents</a>” on page 48.</p> <p>Type and dimension: Integer-association.</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
| interfaces_File     | <p>Specifies the location of interfaces file, including the directory name and the file name for the Sybase instance. If this attribute is configured, [-I interfaces file] option is used when connecting to the isql session. If this attribute is not configured, the agent does not use the -I option.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p> <p>For example: /sybase/my_interfaces_file</p> <p><b>Note:</b> It is assumed that you have modified the RUN_ServerFile with the non-default interface file location if the interfaces_File attribute is configured.</p> |
| DelayAfterOnline    | <p>Specifies the number of seconds that elapse after the Online entry point is complete and before the next monitor cycle is invoked.</p> <p>Type and dimension: integer-scalar</p> <p>Default value: 10</p>                                                                                                                                                                                                                                                                                                                                                                                                           |
| DelayAfterOffline   | <p>Specifies the number of seconds that elapse after the Offline entry point is complete and before the next monitor cycle is invoked.</p> <p>Type and dimension: integer-scalar</p> <p>Default value: 2</p>                                                                                                                                                                                                                                                                                                                                                                                                           |
| ShutdownWaitLimit   | <p>Maximum number of seconds for which the agent waits for the Sybase instance to stop after issuing the <code>shutdown with wait</code> command, and before attempting to issue the <code>kill -15 &lt;data server-pid&gt;</code> command, if required.</p> <p>Type and dimension: integer-scalar</p> <p>Default value: 60</p>                                                                                                                                                                                                                                                                                        |

**Table A-2** Optional attributes (*continued*)

| Optional Attributes                | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                         |
|------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| ContainerOpts<br>(Only Solaris 10) | <p>This resource-type level attribute specifies the container options for the Sybase instances that run in the context of Solaris containers (zones or projects). This attribute has the following keys, which can take values 0 or 1:</p> <ul style="list-style-type: none"> <li> <p>■ RunInContainer (RIC)<br/>               Set the key value as 1 for the Sybase agent to monitor Sybase instances running in the context of Solaris container.<br/>               Set the key value as 0 if you do not want to run the Sybase resource in the context of Solaris container.<br/>               Default is 1.</p> </li> <li> <p>■ PassCInfo (PCI)<br/>               Set the key value as 1 for the Sybase resource to get the container information defined in the VCS service group's ContainerInfo attribute.<br/>               Set the key value as 0 if you do not want to get the container information.<br/>               Default is 1.</p> </li> <li> <p>■ PassLoadInfo (PLI)<br/>               Set the key value as 1 for the Sybase resource to get the load dimensions defined in the VCS service group's Load attribute.<br/>               Set the key value as 0 if you do not want to get the load information.<br/>               Default is 0.</p> <p>See <i>Veritas Cluster Server Administrator's Guide</i> and the <i>Veritas Storage Foundation and High Availability Solutions Virtualization Guide</i>.</p> <p>Type and dimension: static-assoc-int</p> </li> </ul> |

**Table A-2** Optional attributes (*continued*)

| Optional Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Quorum_dev          | <p>The quorum device manages the cluster membership, stores cluster configuration data and contains information shared among server instances and nodes. It must be a disk accessible to all nodes in the cluster. Specify fully qualified quorum device name.</p> <p><b>Caution:</b> If you do not set the Quorum_dev attribute for Sybase Cluster Edition, the Sybase agent does not perform the qrmutil-based checks. This error in configuration may lead to undesirable results. For example, if qrmutil returns failure pending, the agent does not panic the system. Thus, the Sybase agent does not perform qrmutil-based checks because the Quorum_dev attribute is not set.</p> <p>Type and dimension: String-scalar<br/>Default value: No default value</p> |
| Run_ServerFile      | <p>Specifies the location of the RUN_SERVER file of the Sybase instance. The default location of the file is used if no value is specified for this attribute.</p> <p>Type and dimension: String-scalar<br/>Default value: No default value</p>                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                        |

[Table A-3](#) lists the internal attribute for Sybase agent.

This attribute is for internal use only. Symantec recommends not to modify the value of this attribute.

**Table A-3** Internal attribute

| Internal attribute | Definition                                                                                                                                        |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------|
| AgentDirectory     | <p>Specifies the location of the binaries, scripts, and other files related to the agent for Sybase.</p> <p>Type and dimension: static-string</p> |

## SybaseBk resource type

### Type definition for the SybaseBk agent

The resource type definition for the agent for Sybase is as follows.

```

type SybaseBk (
 str Backupserver
 str Owner
 str Home
 str Version
 str Server
 str SA
 str SApwd
 str Run_ServerFile
 str interfaces_File
 static str ArgList[] = { Backupserver, Owner, Home, Version,
 Server, SA, SApwd, Run_ServerFile, interfaces_File }
 static int IMF{} = { Mode=3, MonitorFreq=5, RegisterRetryLimit=3 }
 static str IMFRegList[] = { Backupserver, Owner }
 static int ContainerOpts{} = { RunInContainer=1, PassCInfo=0 }
 static str AgentDirectory = "/opt/VRTSagents/ha/bin/SybaseBk"
)

```

## Attribute definitions for the SybaseBk agent

Review the description of the SybaseBk agent attributes. The agent attributes are classified as required and internal.

[Table A-4](#) lists the required attributes for SybaseBk resource.

**Table A-4** Required attributes

| Required Attributes | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                   |
|---------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Server              | <p>The \$DSQUERY Backup name. Only one server should be configured in a Sybase service group. The advantage of configuring Sybase resources in a separate service group is, each Sybase data server can failover independently. When multiple Sybase resources are configured in a single service group, even if one of the “n” data servers fail, the whole service group will be failed over.</p> <p>Type and dimension: string-scalar</p> |
| Owner               | <p>Sybase user as the defined owner of executables and database files in any of the sources (such as NIS+, /etc/hosts, and so on) specified in the /etc/nsswitch.conf file for passwd entry. The Sybase executables and database files are accessed in the context of this user.</p> <p>Type and dimension: string-scalar</p>                                                                                                                |

**Table A-4** Required attributes (*continued*)

| Required Attributes | Definition                                                                                                                                                                                                                                                                                                                               |
|---------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Home                | The \$SYBASE path to Sybase binaries and configuration files.<br>Type and dimension: string-scalar                                                                                                                                                                                                                                       |
| Version             | Version of Sybase Backup Server.<br>Type and dimension: string-scalar                                                                                                                                                                                                                                                                    |
| Backupserver        | The \$BACKUP SYBASE Backup Server name.<br>Type and dimension: string-scalar                                                                                                                                                                                                                                                             |
| SA                  | Sybase database administrator. This attribute is required to connect to the ASE for shutdown.<br>Type and dimension: string-scalar                                                                                                                                                                                                       |
| SAPswd              | Encrypted password of Sybase database administrator. This password is required to connect to the ASE for shutdown.<br>Type and dimension: string-scalar<br>See <a href="#">“Encrypting passwords for Sybase”</a> on page 46.<br><b>Note:</b> You need not specify a value for this attribute if the SA user does not require a password. |

[Table A-5](#) lists the optional attribute for SybaseBk agent.

**Table A-5** Optional attribute

| Optional attribute | Definition                                                                                                                                                                                                                            |
|--------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Run_ServerFile     | Specifies the location of the RUN_SERVER file for the Sybase instance. The default location of this file is used if no value is specified for this attribute.<br>Type and dimension: String-scalar<br>Default value: No default value |

**Table A-5** Optional attribute (*continued*)

| Optional attribute | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                             |
|--------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| interfaces_File    | <p>Specifies the location of interfaces file for the Sybase instance. If this attribute is configured, [-I interfaces file] option is used when connecting to the isql session. If this attribute is not configured, the agent does not use the -I option.</p> <p>Type and dimension: string-scalar</p> <p>Default value: No default value</p> <p>For example: /sybase/my_interfaces_file</p> <p><b>Note:</b> It is assumed that you have modified the RUN_ServerFile with the non-default interface file location if the interfaces_File attribute is configured.</p> |

**Table A-5** Optional attribute (*continued*)

| Optional attribute | Definition |
|--------------------|------------|
| IMF                |            |

**Table A-5** Optional attribute (*continued*)

| Optional attribute | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                     |
|--------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                    | <p>This resource-type level attribute determines whether the Sybase agent must perform intelligent resource monitoring. You can also override the value of this attribute at resource-level.</p> <p>This attribute includes the following keys:</p> <ul style="list-style-type: none"> <li>■ <b>Mode:</b> Define this attribute to enable or disable intelligent resource monitoring.<br/> Valid values are as follows: <ul style="list-style-type: none"> <li>■ 0—Does not perform intelligent resource monitoring</li> <li>■ 1—Performs intelligent resource monitoring for offline resources and performs poll-based monitoring for online resources</li> <li>■ 2—Performs intelligent resource monitoring for online resources and performs poll-based monitoring for offline resources</li> <li>■ 3—Performs intelligent resource monitoring for both online and for offline resources</li> </ul> Default: 3</li> <li>■ <b>MonitorFreq:</b> This key value specifies the frequency at which the agent invokes the monitor agent function. The value of this key is an integer.<br/> Default: 5<br/> You can set this key to a non-zero value for cases where the agent requires to perform both poll-based and intelligent resource monitoring. If the value is 0, the agent does not perform poll-based process check monitoring.<br/> After the resource registers with the AMF kernel driver, the agent calls the monitor agent function as follows: <ul style="list-style-type: none"> <li>■ After every (MonitorFreq x MonitorInterval) number of seconds for online resources</li> <li>■ After every (MonitorFreq x OfflineMonitorInterval) number of seconds for offline resources</li> </ul> </li> <li>■ <b>RegisterRetryLimit:</b> If you enable intelligent resource monitoring, the agent invokes the oracle_imf_register agent function to register the resource with the AMF kernel driver. The value of the RegisterRetryLimit key determines the number of times the agent must retry registration for a resource. If the agent cannot register the resource within the limit that is specified, then intelligent monitoring is disabled until the resource state changes or the value of the Mode key changes.<br/> Default: 3</li> </ul> |



**Table A-5** Optional attribute (*continued*)

| Optional attribute                 | Definition                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    |
|------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
|                                    | Type and dimension: Integer-association.                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                      |
| ContainerOpts<br>(Only Solaris 10) | <p>This resource-type level attribute specifies the container options for the Sybase instances that run in the context of Solaris containers (zones or projects). This attribute has the following keys, which can take values 0 or 1:</p> <ul style="list-style-type: none"> <li>■ RunInContainer (RIC)<br/>Set the key value as 1 for the Sybase agent to monitor Sybase instances running in the context of Solaris container.<br/>Set the key value as 0 if you do not want to run the Sybase resource in the context of Solaris container.<br/>Default is 1.</li> <li>■ PassCInfo (PCI)<br/>Set the key value as 1 for the Sybase resource to get the container information defined in the VCS service group's ContainerInfo attribute.<br/>Set the key value as 0 if you do not want to get the container information.<br/>Default is 1.</li> <li>■ PassLoadInfo (PLI)<br/>Set the key value as 1 for the Sybase resource to get the load dimensions defined in the VCS service group's Load attribute.<br/>Set the key value as 0 if you do not want to get the load information.<br/>Default is 0.<br/>See <i>Veritas Cluster Server Administrator's Guide</i> and the <i>Veritas Storage Foundation and High Availability Solutions Virtualization Guide</i>.</li> </ul> <p>Type and dimension: static-assoc-int</p> |

[Table A-6](#) lists the internal attribute for SybaseBk agent.

This attribute is for internal use only. Symantec recommends not to modify the value of this attribute.

**Table A-6** Internal attribute

| Internal attribute | Definition                                                                                                                                          |
|--------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|
| AgentDirectory     | <p>Specifies the location of the binaries, scripts, and other files related to the agent for SybaseBk.</p> <p>Type and dimension: static-string</p> |



# Sample configurations for Sybase

This appendix includes the following topics:

- [About the sample configuration for the Sybase agent](#)
- [Resource dependency graph for the Sybase agent](#)
- [Sample configuration for agent for Sybase on Solaris systems](#)
- [Sample main.cf files for Sybase ASE CE configurations](#)
- [Sample configuration for the Sybase agent in Solaris zones](#)


## About the sample configuration for the Sybase agent

After Sybase agent installation, several sample `main.cf` file types can be viewed in the `/etc/VRTSagents/ha/conf/Sybase`. This appendix describes a typical service group that is configured to monitor the state of Sybase servers in a VCS cluster. The sample configuration graphically depicts the resource types, resources, and resource dependencies within the service group. Review these dependencies carefully before you configure the agent. For more information about these resource types, see the *Veritas Cluster Server Bundled Agents Reference Guide*.

## Resource dependency graph for the Sybase agent

[Figure B-1](#) illustrates the configuration's dependency graph for Solaris.

Figure B-1 Dependency graph



The dependency graph depicts a single Sybase instance configuration. The configuration contains a disk group with a single volume. The volume is monitored using a Volume resource and mounted using a Mount resource. The Mount resource requires Volume resource, which in turn requires the DiskGroup resource. The service group IP address for Sybase server is monitored using the IP and NIC resource types. The Sybase server can be started after each of these resources are brought online. The Backup Server is started after the Sybase SQL Server is online.

## Resource dependency for Sybase configured in Solaris zones


The following examples describe a typical service group that is configured to monitor the state of a Sybase instance that is configured in a Solaris zone.

- Zone root on local disk
- Zone root on shared disk

If the root file system of a zone is on the local disk of each node, the file system is mounted when the system is booted. Hence, the service group does not need to have separate DiskGroup and Volume resources for the zone.

Figure B-2 shows a configuration in which zone root is on the local disk.


Figure B-2 Zone root on local disk



If the root file system of a zone is on a shared disk, VCS should mount the file system. Hence, separate DiskGroup and Volume resources are required for the zone.

Figure B-3 shows a configuration in which zone root is on the shared disk.

Figure B-3 Zone root on shared disk



## Sample configuration for agent for Sybase on Solaris systems

The following sample depicts a basic configuration with a Sybase service group configured with one NIC, one database instance configured with detail monitoring, and one backup instance.

```
include "types.cf"
include "/etc/VRTSagents/ha/conf/Sybase/SybaseTypes.cf"

cluster vcscluster (
 UserNames = { admin = anoGniNkoJooMwoIn1 }
 Administrators = { admin }
 CounterInterval = 5
)
system system1 (
)

system system2 (
```

```
)

group Sybase_group (
 SystemList = { system1 = 0, system2 = 1 }
 AutoStartList = { system1, system2 }
)

DiskGroup dgres (
 DiskGroup = sybasedg
)

IP ipres (
 Device = le0
 Address = "16.9.1.9"
 NetMask = "255.255.0.0"
)

NIC nicres (
 Device = le0
 NetworkType = ether
)

Mount sybase_mount (
 MountPoint = "/opt/Sybase"
 BlockDevice = "/dev/vx/dsk/sybasedg/ase1103"
 FsckOpt = "-n"
 FSType = vxfs
 MountOpt = rw
)

Sybase sybase_agent (
 Server = SYBASE
 Owner = sybase
 Home = "/opt/Sybase"
 Version = sybase11
 SA = sa
 SApwd = sybase
 User = abcd
 UPword = xxxxxxxx
 Db = testdb1
 Table = testtab
 Monscript = "/opt/VRTSagents/ha/bin/Sybase/SqlTest.pl"
 Run_ServerFile = "/opt/sybase/RUN_SYBASE_SERVER"
```

```
WaitForRecovery = 1
interfaces_File = "/newfs/interfaces"
)

SybaseBk sybase_bk_agent (
 Server = SYBASE
 Owner = sybase
 Home = "/opt/Sybase"
 Version = sybase11
 Backupserver = SYB_BACKUP
 SA = sa
 SApwd = sybase
 Run_ServerFile = "/opt/sybase/RUN_SYBASE_SERVER_BS"
 interfaces_File = "/newfs/interfaces"
)

Volume sybasedg_vol (
 Volume = ase1103
 DiskGroup = dgres
)

sybase_agent requires sybase_mount
sybase_agent requires ipres
sybase_bk_agent requires sybase_agent
sybase_mount requires sybasedg_vol
ipres requires nicres
sybasedg_vol requires dgres
```

## Sample main.cf files for Sybase ASE CE configurations

Sample main.cf file examples are provided for the following Sybase ASE CE configurations:

- Basic cluster configuration
  - With shared mount point on CFS for Sybase binary installation
  - With local mount point on VxFS for Sybase binary installation
- Replicating data between two clusters
  - For a primary site in a CVM VVR configuration
  - For a secondary site in a CVM VVR configuration



## Sample main.cf for a basic Sybase ASE CE cluster configuration under VCS control with shared mount point on CFS for Sybase binary installation

This sample main.cf is for a single site with a basic cluster configuration with shared mount point on CFS for Sybase binary installation.

The following are the configuration details for this Sybase ASE CE configuration sample main.cf:

- File name: sybasece\_main.cf
- File location: /etc/VRTSagents/ha/conf/Sybase/

```
include "types.cf"
include "CFSTypes.cf"
include "CVMTypes.cf"
include "SybaseTypes.cf"

cluster cluster101 (
 UserNames = { admin = HopHojOlpKppNxpJom }
 Administrators = { admin }
 HacliUserLevel = COMMANDROOT
 UseFence=SCSI3
)

system system1 (
)

system system2 (
)

// binmounts group for configuring CFS mounts for Sybase binaries.

group binmnt (
 SystemList = { system1 = 0, system2 = 1 }
 Parallel = 1
 AutoStartList = { system1, system2 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

CFSMount sybbindg_101_sybbinvol_mnt (
 MountPoint = "/sybase"
 BlockDevice = "/dev/vx/dsk/sybbindg_101/sybbin_vol"
```

```
)

 CVMVolDg sybbindg_101_voldg (
 CVMDiskGroup = sybbindg_101
 CVMVolume = { sybbin_vol }
 CVMActivation = sw
)

requires group cvm online local firm
sybbindg_101_sybbinvol_mnt requires sybbindg_101_voldg

// resource dependency tree
//
// group binmnt
// {
// CFSMount sybbindg_101_sybbinvol_mnt
// {
// CVMVolDg sybbindg_101_voldg
// }
// }

// cvm group for CVM and CFS specific agents.

group cvm (
 SystemList = { system1 = 0, system2 = 1 }
 AutoFailOver = 0
 Parallel = 1
 AutoStartList = { system1, system2 }
)

CFSfsckd vxfsckd (
)

CVMCluster cvm_clus (
 CVMClustName = sfsyb_90
 CVMNodeId = { system1 = 0, system2 = 1 }
 CVMTransport = gab
 CVMTimeout = 200
)

CVMVxconfigd cvm_vxconfigd (
 Critical = 0
```

```
CVMVxconfigdArgs = { syslog }
)

cvm_clus requires cvm_vxconfigd
vxfsckd requires cvm_clus

// resource dependency tree
//
// group cvm
// {
// CFSfsckd vxfsckd
// {
// CVMCluster cvm_clus
// {
// CVMVxconfigd cvm_vxconfigd
// }
// }
// }

// sybasece group for:
// 1. CVM volumes for Sybase database and quorum device
// 2. CFS mount for Sybase database and quorum device
// 3. Process agent for vxfsck process.
// 4. Sybase database instance.

group sybasece (
 SystemList = { system1 = 0, system2 = 1 }
 Parallel = 1
 AutoStartList = { system1, system2 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

CFSMount quorum_101_quorumvol_mnt (
 MountPoint = "/quorum"
 BlockDevice = "/dev/vx/dsk/quorum_101/quorumvol"
)

CFSMount sybdata_101_sybvol_mnt (
 MountPoint = "/sybdata"
 BlockDevice = "/dev/vx/dsk/sybdata_101/sybvol"
)
```

```
CVMVolDg quorum_101_voldg (
 CVMDiskGroup = quorum_101
 CVMVolume = { quorumvol }
 CVMActivation = sw
)

CVMVolDg sybdata_101_voldg (
 CVMDiskGroup = sybdata_101
 CVMVolume = { sybvol }
 CVMActivation = sw
)

Process vxfend (
 PathName = "/sbin/vxfend"
 Arguments = "-m sybase -k /tmp/vcmp_socket"
)

Sybase ase (
 Server @system1 = ase1
 Server @system2 = ase2
 Owner = sybase
 Home = "/sybase"
 Version = 15
 SA = sa
 Quorum_dev = "/quorum/q.dat"
)

requires group binmnt online local firm
ase requires quorum_101_quorumvol_mnt
ase requires sybdata_101_sybvol_mnt
ase requires vxfend
quorum_101_quorumvol_mnt requires quorum_101_voldg
sybdata_101_sybvol_mnt requires sybdata_101_voldg

// resource dependency tree
//
// group sybasece
// {
// Sybase ase
// {
// CFSMount quorum_101_quorumvol_mnt
```

```
// {
// CVMVolDg quorum_101_voldg
// }
// CFSSMount sybdata_101_sybvol_mnt
// {
// CVMVolDg sybdata_101_voldg
// }
// Process vxfsend
// }
// }
```

## Sample main.cf for a basic Sybase ASE CE cluster configuration with local mount point on VxFS for Sybase binary installation

This sample main.cf is for a single site with a basic cluster configuration with local mount point on VxFS for Sybase binary installation.

The following are the configuration details for this Sybase ASE CE configuration sample main.cf:

- File name: sybasece\_main.cf
- File location: /etc/VRTSagents/ha/conf/Sybase/

```
include "types.cf"
include "CFSTypes.cf"
include "CVMTTypes.cf"
include "SybaseTypes.cf"

cluster cluster101 (
 UserNames = { admin = HopHojOlpKppNxpJom }
 Administrators = { admin }
 HacliUserLevel = COMMANDROOT
 UseFence=SCSI3
)

system system1 (
)

system system2 (
)

// binmounts group for configuring VxFS mounts for Sybase binaries.
```

```
group binlocalmnt (
 SystemList = { system1 = 0, system2 = 1 }
 AutoFailOver = 0
 Parallel = 1
 AutoStartList = { system1, system2 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

DiskGroup sybbindg_101_voldg (
 DiskGroup = sybbindg
)

Mount sybbindg_101_sybbinvol_mnt (
 MountPoint = "/sybase"
 BlockDevice = "/dev/vx/dsk/sybbindg_101/sybbin_vol"
 FSType = vxfs
 FsckOpt = "-y"
)

Volume sybbindg_101_vol (
 DiskGroup = sybbindg
 Volume = sybbinvol
)

requires group cvm online local firm
sybbindg_101_sybbinvol_mnt requires sybbindg_101_vol
sybbindg_101_vol requires sybbindg_101_voldgdg

// resource dependency tree
//
// group binlocalmnt
// {
// Mount sybbindg_101_sybbinvol_mnt
// {
// Volume sybbindg_vol
// {
// DiskGroup sybbindg_101_voldg
// }
// }
// }
```

```
// cvm group for CVM and CFS specific agents.

group cvm (
 SystemList = { system1 = 0, system2 = 1 }
 AutoFailOver = 0
 Parallel = 1
 AutoStartList = { system1, system2 }
)

CFSfsckd vxfsckd (
)

CVMCluster cvm_clus (
 CVMClustName = cluster101
 CVMNodeId = { system1 = 0, system2 = 1 }
 CVMTransport = gab
 CVMTimeout = 200
)

CVMVxconfigd cvm_vxconfigd (
 Critical = 0
 CVMVxconfigdArgs = { syslog }
)

cvm_clus requires cvm_vxconfigd
vxfsckd requires cvm_clus

// resource dependency tree
//
// group cvm
// {
// CFSfsckd vxfsckd
// {
// CVMCluster cvm_clus
// {
// CVMVxconfigd cvm_vxconfigd
// }
// }
// }

// sybasece group for:
```

```
// 1. CVM volumes for Sybase database and quorum device
// 2. CFS mount for Sybase database and quorum device
// 3. Process agent for vxfend process.
// 4. Sybase database instance.

group sybasece (
 SystemList = { system1 = 0, system2 = 1 }
 Parallel = 1
 AutoStartList = { system1, system2 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

CFSMount quorum_101_quorumvol_mnt (
 MountPoint = "/quorum"
 BlockDevice = "/dev/vx/dsk/quorum_101/quorumvol"
)

CFSMount sybdata_101_sybvol_mnt (
 MountPoint = "/sybdata"
 BlockDevice = "/dev/vx/dsk/sybdata_101/sybvol"
)

CVMVolDg quorum_101_voldg (
 CVMDiskGroup = quorum_101
 CVMVolume = { quorumvol }
 CVMActivation = sw
)

CVMVolDg sybdata_101_voldg (
 CVMDiskGroup = sybdata_101
 CVMVolume = { sybvol }
 CVMActivation = sw
)

Process vxfend (
 PathName = "/sbin/vxfend"
 Arguments = "-m sybase -k /tmp/vcmp_socket"
)

Sybase ase (
 Server @system1 = ase1
 Server @system2 = ase2
)
```



```
 Owner = sybase
 Home = "/sybase"
 Version = 15
 SA = sa
 Quorum_dev = "/quorum/q.dat"
)

requires group binlocalmnt online local firm
ase requires quorum_101_quorumvol_mnt
ase requires sybdata_101_sybvol_mnt
ase requires vxfsend
quorum_101_quorumvol_mnt requires quorum_101_voldg
sybdata_101_sybvol_mnt requires sybdata_101_voldg

// resource dependency tree
//
// group sybasece
// {
// Sybase ase
// {
// CFMount quorum_101_quorumvol_mnt
// {
// CVMVolDg quorum_101_voldg
// }
// CFMount sybdata_101_sybvol_mnt
// {
// CVMVolDg sybdata_101_voldg
// }
// Process vxfsend
// }
// }
```

## Sample main.cf for a primary CVM VVR site

This sample main.cf is for a primary site in a CVM VVR configuration. It is one of two sample main.cfs for replicating data between two clusters.

The following are the configuration details for this Sybase ASE CE configuration sample main.cf:

- File name: sybasece\_cvmvvr\_primary\_main.cf

■ File location: /etc/VRTSagents/ha/conf/Sybase

```
include "types.cf"
include "CFSTypes.cf"
include "CVMTypes.cf"
include "VVRTypes.cf"
include "SybaseTypes.cf"

cluster cluster101 (
 UserNames = { admin = HopHojOlpKppNxpJom }
 ClusterAddress = "10.180.88.188"
 Administrators = { admin }
 HacliUserLevel = COMMANDROOT
 UseFence=SCSI3
)

remotecluster syb_cluster102 (
 ClusterAddress = "10.190.99.199"
)

heartbeat Icmp (
 ClusterList = { syb_cluster102 }
 Arguments @syb_cluster102 = { "10.190.99.199" }

)

system system1 (
)

system system2 (
)

group ClusterService (
 SystemList = { system1 = 0, system2 = 1 }
 AutoStartList = { system1, system2 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

Application wac (
 StartProgram = "/opt/VRTSvc/bin/wacstart"
 StopProgram = "/opt/VRTSvc/bin/wacstop"
 MonitorProcesses = { "/opt/VRTSvc/bin/wac" }
)
```

```
RestartLimit = 3
)

IP gcoip (
 Device = eth0
 Address = "10.180.88.188"
 NetMask = "255.255.255.0"
)

NIC csgnic (
 Device = eth0
)

gcoip requires csgnic
wac requires gcoip

// resource dependency tree
//
// group ClusterService
// {
// Application wac
// {
// IP gcoip
// {
// NIC csgnic
// }
// }
// }
// }

group RVGgroup (
 SystemList = { system1 = 0, system2 = 1 }
 Parallel = 1
 AutoStartList = { system1, system2 }
)

CVMVolDg sybdata_voldg (
 CVMDiskGroup = sybdata_101
 CVMActivation = sw
)

RVGShared sybdata_rvg (
```

```
 RVG = syb_rvg
 DiskGroup = sybdata_101
)

requires group binmnt online local firm
sybdata_rvg requires sybdata_voldg

group binmnt (
 SystemList = { system1 = 0, system2 = 1 }
 Parallel = 1
 AutoStartList = { system1, system2 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

CFSMount sybbindg_101_sybbinvol_mnt (
 MountPoint = "/sybase"
 BlockDevice = "/dev/vx/dsk/sybbindg_101/sybbin_vol"
)

CVMVolDg sybbindg_101_voldg (
 CVMDiskGroup = sybbindg_101
 CVMVolume = { sybbin_vol }
 CVMActivation = sw
)

requires group cvm online local firm
sybbindg_101_sybbinvol_mnt requires sybbindg_101_voldg

group cvm (
 SystemList = { system1 = 0, system2 = 1 }
 AutoFailOver = 0
 Parallel = 1
 AutoStartList = { system1, system2 }
)

CFSfsckd vxfsckd (
)

CVMCluster cvm_clus (
 CVMClustName = syb_cluster101
 CVMNodeId = { system1 = 0, system2 = 1 }
 CVMTransport = gab
)
```

```
 CVMTimeout = 200
)

 CVMVxconfigd cvm_vxconfigd (
 Critical = 0
 CVMVxconfigdArgs = { syslog }
)

 cvm_clus requires cvm_vxconfigd
 vxfsckd requires cvm_clus

 // resource dependency tree
 //
 // group cvm
 // {
 // CFSfsckd vxfsckd
 // {
 // CVMCluster cvm_clus
 // {
 // CVMVxconfigd cvm_vxconfigd
 // }
 // }
 // }
 // }

group logowner (
 SystemList = { system1 = 0, system2 = 1 }
 AutoStartList = { system1, system2 }
)

IP logowner_ip (
 Device = eth0
 Address = "10.10.9.101"
 NetMask = "255.255.255.0"
)

NIC nic (
 Device = eth0
)

RVGLogowner rvg_logowner (
 RVG = syb_rvg
```

```
 DiskGroup = sybdata_101
)

requires group RVGgroup online local firm
logowner requires logowner_ip
logowner_ip requires nic

// resource dependency tree
//
// group logowner
// {
// RVGLogowner rvg_logowner
// {
// IP logowner_ip
// {
// NIC nic
// }
// }
// }
// }

group sybasece (
 SystemList = { system1 = 0, system2 = 1 }
 Parallel = 1
 ClusterList = { syb_cluster101 = 0, syb_cluster102 = 1 }
 AutoStartList = { system1, system2 }
 ClusterFailOverPolicy = Manual
 Authority = 1
 OnlineRetryLimit = 3
 TriggerResStateChange = 1
 OnlineRetryInterval = 120
)

CFSMount quorum_101_quorumvol_mnt (
 MountPoint = "/quorum"
 BlockDevice = "/dev/vx/dsk/quorum_101/quorumvol"
)

CFSMount sybdata_101_sybvol_mnt (
 MountPoint = "/sybdata"
 BlockDevice = "/dev/vx/dsk/sybdata_101/sybvol"
)
```

```
CVMVolDg quorum_101_voldg (
 CVMDiskGroup = quorum_101
 CVMVolume = { quorumvol }
 CVMActivation = sw
)

Process vxfsend (
 PathName = "/sbin/vxfsend"
 Arguments = "-m sybase -k /tmp/vcmp_socket"
)

RVGSharedPri syb_vvr_shpri (
 RvgResourceName = sybdata_rvg
 OnlineRetryLimit = 0
)

Sybase ase (
 Server @system1 = ase1
 Server @system2 = ase2
 Owner = sybase
 Home = "/sybase"
 Version = 15
 SA = sa
 Quorum_dev = "/quorum/q.dat"
)

requires group RVGgroup online local firm
sybdata_101_sybvol_mnt requires syb_vvr_shpri
ase requires vxfsend
ase requires sybdata_101_sybvol_mnt
ase requires quorum_101_quorumvol_mnt
quorum_101_quorumvol_mnt requires quorum_101_voldg

// resource dependency tree
//
// group sybasece
// {
// Sybase ase
// {
// CFSMount sybdata_101_sybvol_mnt
// {
// RVGSharedPri syb_vvr_shpri
// }
// }
// }
// }
```

```
// Process vxfsend
// CFSSMount quorum_101_quorumvol_mnt
// {
// CVMVolDg quorum_101_voldg
// }
// }
// }
```

## Sample main.cf for a secondary CVM VVR site

This sample main.cf is for a secondary site in a CVM VVR configuration. It is the second of two sample main.cfs for replicating data between two clusters.

The following are the configuration details for this Sybase ASE CE configuration sample main.cf:

- File name: sybasece\_cvmvvr\_secondary\_main.cf
- File location: /etc/VRTSagents/ha/conf/Sybase

This is main.cf for CVM VVR configuration on Secondary site.

```

include "types.cf"
include "CFSTypes.cf"
include "CVMTypes.cf"
include "VVRTypes.cf"
include "SybaseTypes.cf"

cluster cluster102 (
 UserNames = { admin = HopHojOlpKppNxpJom }
 ClusterAddress = "10.190.99.199"
 Administrators = { admin }
 HacliUserLevel = COMMANDROOT
 UseFence=SCSI3
)

remoteclass syb_cluster101 (
 ClusterAddress = "10.180.88.188"
)

heartbeat Icmp (
 ClusterList = { syb_cluster101 }
 Arguments @syb_cluster101 = { "10.180.88.188" }
)
```



```
system system3 (
)

system system4 (
)

group ClusterService (
 SystemList = { system3 = 0, system4 = 1 }
 AutoStartList = { system3, system4 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

Application wac (
 StartProgram = "/opt/VRTSvcs/bin/wacstart"
 StopProgram = "/opt/VRTSvcs/bin/wacstop"
 MonitorProcesses = { "/opt/VRTSvcs/bin/wac" }
 RestartLimit = 3
)

IP gcoip (
 Device = eth0
 Address = "10.190.99.199"
 NetMask = "255.255.255.0"
)

NIC csgnic (
 Device = eth0
)

gcoip requires csgnic
wac requires gcoip

// resource dependency tree
//
// group ClusterService
// {
// Application wac
// {
// IP gcoip
// {
// NIC csgnic
```

```
// }
// }
// }

group RVGgroup (
 SystemList = { system3 = 0, system4 = 1 }
 Parallel = 1
 AutoStartList = { system3, system4 }
)

CVMVolDg sybdata_voldg (
 CVMDiskGroup = sybdata_101
 CVMActivation = sw
)

RVGShared sybdata_rvg (
 RVG = syb_rvg
 DiskGroup = sybdata_101
)

requires group binmnt online local firm
sybdata_rvg requires sybdata_voldg

group binmnt (
 SystemList = { system3 = 0, system4 = 1 }
 Parallel = 1
 AutoStartList = { system3, system4 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
)

CFSMount sybbindg_101_sybbinvol_mnt (
 MountPoint = "/sybase"
 BlockDevice = "/dev/vx/dsk/sybbindg_101/sybbin_vol"
)

CVMVolDg sybbindg_101_voldg (
 CVMDiskGroup = sybbindg_101
 CVMVolume = { sybbin_vol }
 CVMActivation = sw
)

requires group cvm online local firm
```

```
sybbindg_101_sybbinvol_mnt requires sybbindg_101_voldg

group cvm (
 SystemList = { system3 = 0, system4 = 1 }
 AutoFailOver = 0
 Parallel = 1
 AutoStartList = { system3, system4 }
)

CFSfsckd vxfsckd (
)

CVMCluster cvm_clus (
 CVMClustName = syb_cluster102
 CVMNodeId = { system3 = 0, system4 = 1 }
 CVMTransport = gab
 CVMTimeout = 200
)

CVMVxconfigd cvm_vxconfigd (
 Critical = 0
 CVMVxconfigdArgs = { syslog }
)

cvm_clus requires cvm_vxconfigd
vxfsckd requires cvm_clus

// resource dependency tree
//
// group cvm
// {
// CFSfsckd vxfsckd
// {
// CVMCluster cvm_clus
// {
// CVMVxconfigd cvm_vxconfigd
// }
// }
// }
// }

group logowner (
 SystemList = { system3 = 0, system4 = 1 }
```

```
AutoStartList = { system3, system4 }
)

IP logowner_ip (
 Device = eth0
 Address = "10.11.9.102"
 NetMask = "255.255.255.0"
)

NIC nic (
 Device = eth0
)

RVGLogowner rvg_logowner (
 RVG = syb_rvg
 DiskGroup = sybdata_101
)

requires group RVGgroup online local firm
logowner requires logowner_ip
logowner_ip requires nic

// resource dependency tree
//
// group logowner
// {
// RVGLogowner rvg_logowner
// {
// IP logowner_ip
// {
// NIC nic
// }
// }
// }

group sybasece (
 SystemList = { system3 = 0, system4 = 1 }
 Parallel = 1
 ClusterList = { syb_cluster102 = 0, syb_cluster101 = 1 }
 AutoStartList = { system3, system4 }
 OnlineRetryLimit = 3
 OnlineRetryInterval = 120
```

```
)

CFSMount quorum_101_quorumvol_mnt (
 MountPoint = "/quorum"
 BlockDevice = "/dev/vx/dsk/quorum_101/quorumvol"
)

CVMVolDg quorum_101_voldg (
 CVMDiskGroup = quorum_101
 CVMVolume = { quorumvol }
 CVMActivation = sw
)

CFSMount sybdata_101_sybvol_mnt (
 MountPoint = "/sybdata"
 BlockDevice = "/dev/vx/dsk/sybdata_101/sybvol"
)

Process vxfsend (
 PathName = "/sbin/vxfsend"
 Arguments = "-m sybase -k /tmp/vcmp_socket"
)

RVGSharedPri syb_vvr_shpri (
 RvgResourceName = sybdata_rvg
 OnlineRetryLimit = 0
)

Sybase ase (
 Server @system3 = ase1
 Server @system4 = ase2
 Owner = sybase
 Home = "/sybase"
 Version = 15
 SA = sa
 Quorum_dev = "/quorum/q.dat"
)

requires group RVGgroup online local firm
sybdata_101_sybvol_mnt requires syb_vvr_shpri
ase requires vxfsend
ase requires sybdata_101_sybvol_mnt
ase requires quorum_101_quorumvol_mnt
```

```
quorum_101_quorumvol_mnt requires quorum_101_voldg
```

## Sample configuration for the Sybase agent in Solaris zones

A resource of type Zone is added to the sample configuration if the Sybase agent is configured to run in Solaris zones, irrespective of whether the root file system of the zone is on local or shared disks.

```
Zone ORA_zone (
 ZoneName = z-ora
)
```

Along with this resource addition, the service group configuration would also change to have the NIC and Mount resources to depend on the Zone resource.

# Changes introduced in previous releases

This appendix includes the following topics:

- [Changes introduced in the previous release](#)

## Changes introduced in the previous release

The enhancements in the previous releases of Veritas Cluster Server Agent for Sybase are as follows:

- The VCS agent binaries for Sybase are now part of VRTSvcsea package. This package also includes the VCS agent binaries for DB2 and Oracle.
- If you installed the VCS agent binaries using the installer program, the program updates the `main.cf` file to include the appropriate agent `types.cf` files.
- The Sybase agent supports the IPC cleanup feature.
- The agent supports a new attribute `WaitForRecovery`. If this attribute is enabled, during the online function, the agent waits till recovery has been completed and all databases that can be made online are brought online.
- The attributes `ContainerName` and `ContainerType` are replaced with resource type-level attribute `ContainerOpts`, and a service group-level attribute `ContainerInfo`.
- The agent supports a new action called `checkpoint_all`. Performs "checkpoint\_all" for the Sybase dataserver by connecting to an isql session.
- The agent supports a new optional attribute `Run_ServerFile`. The attribute specifies the location of the `RUN_SERVER` file for a Sybase instance. If this attribute is not specified, the default location of this file is accessed while starting Sybase server instances.





# Index

## Symbols

\$SYBASE 26

## A

agent for Backup server

- functions 17
- resource type 67
- type definition 67

agent for SQL server

- attribute definitions 58
- functions 14
- resource type 57
- type definition 57

## B

Backup server agent attributes

- AgentDirectory 69, 73
- Backupserver 69
- home 69
- owner 68
- SA 69
- SAPswd 69
- server 68
- version 69

## C

cluster manager 42

commands

- hagrp 33
- hagui 40

configuration

- typical setup 22

configuration wizard 42

configuring service groups 42

- about 42
- cluster manager (Java Console) 42
- command line 44
- prerequisites 42

## D

database dbspaces 26

detail monitoring

- disabling 47
- enabling 47

## H

hagrp command 33

hagui command 40

## I

IMF 13

installing Sybase 27

installing Sybase agent

- Japanese language pack 32
- Solaris 32

## M

monitoring

- basic 20
- detail 20

monitoring options

- Solaris zones 21

## R

removing Sybase agent 34

## S

sample configuration

- Solaris 78
- Solaris zones 102

service group

- viewing log 55

SQL server agent attributes

- AgentDirectory 67
- Db 61
- DelayAfterOffline 65
- DelayAfterOnline 65
- DetailMonitor 61

- SQL server agent attributes (*continued*)
  - home 59
  - monscript 62
  - owner 59
  - Quorum\_dev 60
  - Run\_ServerFile 62
  - SA 59
  - SAPswd 60
  - server 59
  - ShutdownWaitLimit 65
  - table 61
  - UPword 61
  - user 61
  - version 59
  - WaitForRecovery 62
- support for intelligent resource monitoring 13
- supported software 12
- Sybase
  - database dbspaces 26
  - directory on shared disks 26
  - installation directory 25
  - installation prerequisites 25
  - installing 27
  - language settings 26
  - setting up for detail monitoring 27
  - transparent TCP/IP failover 26
- Sybase agent
  - about 11
  - agent functions 14
  - configuring using cluster manager 42
  - configuring using command line 44
  - detail monitoring 46
  - disabling 34
  - installation prerequisites 31
  - installing 32
  - monitoring options 20
  - removing 34
  - supported software 12
  - typical setup 22
  - uninstalling 34
  - upgrading 35
- Sybase high availability 12
- SybaseTypes.cf file
  - importing 40

## T

- transparent TCP/IP failover 26
- type definition 58

## U

- uninstalling Sybase agent 34