NetBackup[™] Web UI Cloud Administrator's Guide

Release 10.2



Last updated: 2023-03-31

Legal Notice

Copyright © 2023 Veritas Technologies LLC. All rights reserved.

Veritas, the Veritas Logo, and NetBackup are trademarks or registered trademarks of Veritas Technologies LLC or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

This product may contain third-party software for which Veritas is required to provide attribution to the third party ("Third-party Programs"). Some of the Third-party Programs are available under open source or free software licenses. The License Agreement accompanying the Software does not alter any rights or obligations you may have under those open source or free software licenses. Refer to the Third-party Legal Notices document accompanying this Veritas product or available at:

https://www.veritas.com/about/legal/license-agreements

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Veritas Technologies LLC and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. Veritas Technologies LLC SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, et seq. "Commercial Computer Software and Commercial Computer Software Documentation," as applicable, and any successor regulations, whether delivered by Veritas as on premises or hosted services. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Veritas Technologies LLC 2625 Augustine Drive Santa Clara, CA 95054

http://www.veritas.com

Technical Support

Technical Support maintains support centers globally. All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policies. For information about our support offerings and how to contact Technical Support, visit our website:

https://www.veritas.com/support

You can manage your Veritas account information at the following URL:

https://my.veritas.com

If you have questions regarding an existing support agreement, please email the support agreement administration team for your region as follows:

Worldwide (except Japan)

CustomerCare@veritas.com

Japan

CustomerCare_Japan@veritas.com

Documentation

Make sure that you have the current version of the documentation. Each document displays the date of the last update on page 2. The latest documentation is available on the Veritas website:

https://sort.veritas.com/documents

Documentation feedback

Your feedback is important to us. Suggest improvements or report errors or omissions to the documentation. Include the document title, document version, chapter title, and section title of the text on which you are reporting. Send feedback to:

NB.docs@veritas.com

You can also see documentation information or ask a question on the Veritas community site:

http://www.veritas.com/community/

Veritas Services and Operations Readiness Tools (SORT)

Veritas Services and Operations Readiness Tools (SORT) is a website that provides information and tools to automate and simplify certain time-consuming administrative tasks. Depending on the product, SORT helps you prepare for installations and upgrades, identify risks in your datacenters, and improve operational efficiency. To see what services and tools SORT provides for your product, see the data sheet:

https://sort.veritas.com/data/support/SORT_Data_Sheet.pdf

Contents

Chapter 1	Managing and protecting cloud assets	7
	About protecting cloud assets	8
	Limitations and considerations	10
	Configure Snapshot Manager's in NetBackup	11
	Configure a third-party CA certificate	12
	Add a Snapshot Manager	13
	Add a cloud provider for a Snapshot Manager	14
	Associate media servers with a Snapshot Manager	18
	Discover assets on Snapshot Manager	18
	Edit a Snapshot Manager	20
	Enable or disable a Snapshot Manager	20
	(Optional) Add the Snapshot Manager extension	21
	Managing intelligent cloud groups	21
	Create an intelligent cloud group	22
	Delete an intelligent cloud group	25
	Protecting cloud assets or intelligent cloud groups	26
	Customize or edit protection for cloud assets or intelligent groups	
	-	28
	Remove protection from cloud assets or intelligent groups	29
	Cloud asset cleanup	29
	Cloud asset filtering	30
	AWS and Azure government cloud support	33
	About protecting Microsoft Azure resources using resource groups	33
	Before vou beain	34
	Limitations and considerations	34
	About resource group configurations and outcome	35
	Troubleshoot resource group permissions	38
	About the NetBackup Accelerator for cloud workloads	38
	How the NetBackup Accelerator works with virtual machines	39
	Accelerator forced rescan for virtual machines (schedule attribute)	
		40
	Accelerator backups and the NetBackup catalog	40
	Accelerator messages in the backup job details log	40
	Configuring backup schedule for cloud workloads	41
	Backup options for cloud workloads	44

	Snapshot replication	47
	Configure AWS snapshot replication	47
	Using AWS snapshot replication	50
	Support matrix for account replication	52
	Protect applications in-cloud with application consistent snapshots	
		54
	Protecting PaaS assets	55
	Prerequisites for protecting PaaS assets	56
	Installing the native client utilities	58
	Configuring the storage server for instant access	61
	About incremental backup for PaaS workloads	62
	Limitations and considerations	62
	Discovering PaaS assets	65
	Viewing PaaS assets	67
	Managing PaaS credentials	67
	View the credential name that is applied to a database	67
	Add credentials to a database	67
	Add protection to PaaS assets	72
	Perform backup now	72
Chapter 2	Recovering cloud assets	74
	Recovering cloud assets	74
	Perform rollback recovery of cloud assets	80
	Recovering PaaS assets	81
	Recovering non-RDS PaaS assets	81
	Recovering RDS-based PaaS asset	82
	Recovering Azure protected assets	84
	Recovering duplicate images from AdvancedDisk	86
Chapter 3	Performing granular restore	87
-		97
	Supported environment list	، ۵۵ ۵۵
	List of supported file systems	00
	Before you begin	09
	Limitations and considerations	00
	Restoring files and folders from cloud virtual machines	92 05
	Restoring volumes on cloud virtual machines	טפ ממ
	Troubleshooting	۵۵ مە

Chapter 4	Troubleshooting protection and recovery of cloud	
	assets	104
	Troubleshoot cloud workload protection issues	104
	Troubleshoot PaaS workload protection and recovery issues	108

Chapter

Managing and protecting cloud assets

This chapter includes the following topics:

- About protecting cloud assets
- Limitations and considerations
- Configure Snapshot Manager's in NetBackup
- Managing intelligent cloud groups
- Protecting cloud assets or intelligent cloud groups
- Cloud asset cleanup
- Cloud asset filtering
- AWS and Azure government cloud support
- About protecting Microsoft Azure resources using resource groups
- About the NetBackup Accelerator for cloud workloads
- Configuring backup schedule for cloud workloads
- Backup options for cloud workloads
- Snapshot replication
- Configure AWS snapshot replication
- Using AWS snapshot replication
- Support matrix for account replication

- Protect applications in-cloud with application consistent snapshots
- Protecting PaaS assets

About protecting cloud assets

Using NetBackup, you can now protect your in-cloud workloads. The cloud data protection framework leverages the Snapshot Manager infrastructure to drive faster proliferation of cloud providers. In NetBackup 8.3 and later, Snapshot Manager can protect assets in AWS, Azure, Azure Stack hub and GCP clouds.

The following table describes the tasks.

Task	Description	
Before you begin ensure that you have the appropriate permissions.	To manage and protect cloud assets in the web UI you must have the workload administrator role or similar permissions. The NetBackup security administrator can manage your role permissions at an individual asset level or at the account or subscription level, or at a cloud provider level.	
	See the NetBackup Web UI Administrator's Guide.	
	Note: For managing hosted applications, you need Manage Assets and Manage Protection Plans permissions.	
Deploy Snapshot Manager	Install Snapshot Manager in your environment.	
	See "Add a Snapshot Manager" on page 13.	
	Review Snapshot Manager and NetBackup limitations.	
	See "Limitations and considerations" on page 10.	
Configure the Snapshot Manager	Register the Snapshot Manager in NetBackup. See the NetBackup Snapshot Client Administrator's Guide.	

 Table 1-1
 Configuring protection for cloud assets

Task	Description	
Add a configuration	All the supported cloud providers are displayed in the web UI.	
	You need to add the cloud account (configure the cloud plug-in) for the cloud provider you need. You can create multiple configurations for each provider.	
	See "Add a cloud provider for a Snapshot Manager" on page 14.	
	For Amazon, you can choose to use IAM role.	
	See "IAM Role for AWS Configuration" on page 17.	
Asset discovery	NetBackup retrieves the cloud assets pertaining to the cloud accounts that are configured in NetBackup. Assets are populated in NetBackup asset DB.	
	By default, asset discovery happens every 2 hours and is configurable.	
	In case of applications, you can set discovery interval between 15 minutes to 45 minutes.	
	See "Discover assets on Snapshot Manager" on page 18.	
Create a protection plan	Create a protection plan. A protection plan is used to schedule backup start windows.	
	See the NetBackup Web UI Administrator's Guide.	
	You can also configure the protection plan for snapshot replication. See "Configure AWS snapshot replication" on page 47.	
Choose to protect a virtual machine, application, or volume	For each cloud provider, a list of discovered assets is displayed. Add the assets to a protection plan.	
	See the NetBackup Web UI Administrator's Guide.	
	You can also choose to protect application using application consistent snapshots. See "Protect applications in-cloud with application consistent snapshots" on page 54.	

Table 1-1	Configuring protection for cloud assets (continued)

Task	Description	
Recover cloud assets	 You can recover the assets using the recovery points. See "Recovering cloud assets" on page 74. See "Recovering cloud assets" on page 74. See "Perform rollback recovery of cloud assets " on page 80. You can also restore the assets using the nbcloudrestore CLI utility. Note: Do not use the bprestore CLI for restores 	
	See the NetBackup Commands Reference Guide.	
Troubleshooting	See "Troubleshoot cloud workload protection issues" on page 104.	

 Table 1-1
 Configuring protection for cloud assets (continued)

Limitations and considerations

Consider the following when protecting cloud workloads

 Deletion of Snapshot Manager host entry and its associated plug-ins is not supported in NetBackup.

If you delete plug-ins that are configured in NetBackup, you cannot recover any Snapshot Manager images that are associated with that plug-in.

- Review the NetBackup Snapshot Manager Install and Upgrade Guide for information on the capabilities of Snapshot Manager.
- If you have a previous installation of Snapshot Manager, Veritas recommends that you upgrade the Snapshot Manager and not reinstall it.
 If you do reinstall the Snapshot Manager server, you need to reconfigure the Snapshot Manager and perform all the protection-related steps.
- By default, Snapshot Manager is configured with port 443.
- After Snapshot Manager server is added, the host machine tries to use the IPv6 address to discover assets on cloud. If the IPV6 address is found on the host, the application is configured to use it. If an IPv6 address is not found, the IPv4 address is used.
- For Snapshot Manager, enhanced auditing is not supported. Thus, when you
 add or update a Snapshot Manager, with non-root but NetBackup Admin rights,
 during auditing the user is shown as root.

If you deploy Snapshot Manager using the CloudFormation template, when you
register the on-host agent with the Snapshot Manager node using the command,
the IP address used must be private IP and not public IP.

Note: Veritas recommends having swap space enabled on NetBackup primary servers that would be used to run backup from snapshot jobs for cloud asset groups. The recommended size for swap space must be greater than or equal to 1.5 times of the system memory. In scenarios where swap space enablement is not available, it is recommend to have systems with higher memory configuration.

Configure Snapshot Manager's in NetBackup

You can add a Snapshot Manager using the NetBackup Web UI. Starting with 8.3, the Snapshot Manager can discover cloud assets on Amazon Web Services and Microsoft Azure US Government cloud.

Consider the following important points:

- You can associate multiple Snapshot Manager's to a NetBackup primary server. But you can associate only one Snapshot Manager to one NetBackup master server.
- You can associate multiple media servers to a Snapshot Manager. Only the media servers that are linked to your NetBackup primary server can be linked to a Snapshot Manager.
- You can now manage Snapshot Manager and control discovery of assets from the NetBackup WebUI, REST API, and CLI without interacting with the Snapshot Manager interfaces.
- For backup from snapshot jobs, the NetBackup media storage associated servers are used instead of Snapshot Manager associated media servers. The NetBackup media storage associated servers must be connected to the Snapshot Manager to facilitate all the Snapshot Manager related operations.

The following table describes the underlying tasks.

Task	Description
Add a Snapshot Manager	To add a Snapshot Manager in NetBackup, you must add the credentials and validate the certificate of the Snapshot Manager. See "Add a Snapshot Manager" on page 13.

Table 1-2Configuring Snapshot Manager's

Task	Description
Add cloud providers	To discover assets on the Snapshot Manager, you must add the cloud providers. See "Add a cloud provider for a Snapshot Manager" on page 14.
Discover assets on Snapshot Manager	You can discover assets on the Snapshot Manager.See "Discover assets on Snapshot Manager" on page 18.
Associate media servers	To offload snapshots and restore workflows to a media server, you must associate the media server to the Snapshot Manager.See "Associate media servers with a Snapshot Manager" on page 18.

 Table 1-2
 Configuring Snapshot Manager's (continued)

Configure a third-party CA certificate

You can use a self-signed or a third-party certificate to validate your Snapshot Manager.

Consider the following points:

- For Windows, you can give a certificate as a file path or install the third party certificate in the Trusted Root Certificates authorities.
- To switch from a self-signed certificate to a third-party certificate for an already added Snapshot Manager, you can update the tpconfig command or edit the Snapshot Manager API or from NetBackup WebUI.

To configure a third-party CA certificate

- 1 Generate the third party certificate and private key for your Snapshot Manager.
- 2 Run the /cloudpoint/scripts/cp_certificate_management.sh script to upload the certificate, key and trust store to the Snapshot Manager.
- **3** In NetBackup, create a certificate file and append the certificate of root and all intermediate CAs in the pem file.
- 4 In the bp.conf file, at /cloudpoint/openv/netbackup/, create the following entries:
 - ECA_TRUST_STORE_PATH = /cloudpoint/eca/trusted/cacerts.pem
 - (Optional) VIRTUALIZATION_CRL_CHECK = CHAIN
 - Optional) ECA_CRL_PATH =/cloudpoint/eca/crl/

Note: The CA certificates and CRLs should be present under /cloudpoint/eca/trusted/cacerts.pem for trust-store, and /cloudpoint/eca/crl for CRL.

- The ECA_CRL_PATH option specifies the path to the directory where the Certificate Revocation Lists (CRL) of the external certificate authority (CA) are located. All files in ECA_CRL_PATH must be in DER, PEM, and P7B formats.
- VIRTUALIZATION_CRL_CHECK option is only required if you want to check the revocation status of the certificate. By default, the VIRTUALIZATION_CRL_CHECK option is disabled.
- You can disable, LEAF, or CHAIN the value of the VIRTUALIZATION_CRL_CHECK option. For LEAF, revocation status of the leaf certificate is validated against the CRL. For CHAIN, revocation status of all certificates from the certificate chain are validated against the CRL.

Note: Following should be the order in which the certificates are uploaded: Leaf > Intermediate > Root. If the certificates are not uploaded in the correct order, Snapshot Manager might not work.

5 Add the Snapshot Manager to NetBackup or run the tpconfig command to update the certificate for a Snapshot Manager already added to NetBackup.

Add a Snapshot Manager

You can add a Snapshot Manager using NetBackup WebUI. You must provide the Snapshot Manager credentials and validate the certificate.

Note: To allow backups from snapshots, bi-directional connectivity is required between Snapshot Manager and NetBackup servers

To add a Snapshot Manager

- 1 On the left, click **Cloud**.
- 2 Click on the Snapshot Manager tab.
- 3 Click Add.
- 4 In the Snapshot Manager field, enter one of the following:
 - The host name or IP address of the Snapshot Manager.

The host name or IP address must be the same as the one you have provided at the time of Snapshot Manager configuration during Snapshot Manager installation.

- If the DNS server is configured, enter the FDQN of the Snapshot Manager.
- 5 In **Port** field, enter the port number for the Snapshot Manager.

The default port value is 443.

- 6 Click Validate.
- 7 In the Validate certificate dialog box, click Accept.
- 8 Enter the Snapshot Manager credentials that have provided at the time of Snapshot Manager installation.
- 9 Click Save.

Note: If NetBackup security level is set to VERY HIGH, an additional field **Token** is shown where you can provide a Standard Host Token. This is required for NetBackup certificates generation on Snapshot Manager. You may need to contact the security administrator or a backup administrator for requesting the additional security permissions required for generating the token.

Add a cloud provider for a Snapshot Manager

You can protect the assets on the Amazon Web Services (AWS), Google Cloud Platform (GCP), Microsoft Azure, and Microsoft Azure Stack Hub cloud providers. Starting with 9.0, the Snapshot Manager can discover Amazon Web Services and Microsoft Azure US Government cloud workloads.

To add a cloud provider for Snapshot Manager

- 1 On the left, click **Cloud**.
- 2 Click the **Providers** tab or click **Add** under the cloud provider for which you want to add a configuration.
- 3 Enter a value in the **Configuration Name** field, in the **Add configuration** pane.
- 4 Select the preferred Snapshot Manager.

5 Enter the required details.

Cloud provider	Parameter	Description	
Microsoft Azure	Credential type: Application service principal		
	Tenant ID	The ID of the AAD directory in which you created the application.	
	Client ID	The application ID.	
	Secret key	The secret key of the application.	
	Credential type: System managed identity	Enable system managed identity on Snapshot Manager host in Azure.	
		Note: Assign a role to the system managed identity.	
	Credential type: User managed identit	ty .	
	Client ID	The ID of the user managed identity connected to the Snapshot Manager host.	
	Following parameters are applicable for	r all the above credential type's	
	Regions	One or more regions in which to discover cloud assets.	
		Note: If you configure a government cloud, select US Gov Arizona, US Gov Texas US, or Gov Virginia.	
	Resource Group prefix	The string with which you want to append all the resources in a resource group.	
	Protect assets even if prefixed Resource Groups are not found	The check box determines whether the assets are protected if they are not associated to any resource groups.	

Cloud provider	Parameter	Description
Microsoft Azure Stack Hub	Using AAD: Azure Stack Hub Resource Manager	The endpoint URL in the following format, that allows Snapshot Manager to connect with your Azure resources.
		https://management. <location>.<fqdn></fqdn></location>
	Tenant ID	The ID of the AAD directory in which you created the application.
	Client ID	The application ID.
	Secret Key	The secret key of the application.
	Authentication Resource URL (optional)	The URL where the authentication token is sent to.
	Using ADFS: Azure Stack Hub Resource Manager endpoint URI	The endpoint URL in the following format, that allows Snapshot Manager to connect with your Azure resources.
		https://management. <location>.<fqdn></fqdn></location>
	Tenant ID	The ID of the AAD directory in which you created the application.
	Client ID	The application ID.
	Secret Key	The secret key of the application.
	Authentication Resource URL (optional)	The URL where the authentication token is sent to.
Amazon AWS Note: If the Snapshot Manager is configured with IAM Config, the Access Key and Secret Key options	Access Key	The access key ID, when specified with the secret access key, authorizes Snapshot Manager to interact with the AWS APIs.
are not available.	Secret Key	The secret key of the application.
	Regions	One or more AWS regions in which to discover cloud assets.
		Note: If you configure a government cloud, select us-gov-east-1 or us-gov-west-1.

Cloud provider	Parameter	Description
Google Cloud Platform	Project ID	The ID of the project from which the resources are managed. Listed as in the project_id JSON file.
	Client Email	The email address of the Client ID. Listed as client_email in the JSON file.
	Private Key	The private key. Listed as private_key in the JSON file.
		Note: You must enter this key without quotes. Do not enter any spaces or return characters at the beginning or end of the key.
	Regions	A list of regions in which the provider operates.

- 6 Enter the connection and authentication details in the Add Configuration pane.
- 7 Click Save.

The assets on the cloud providers are automatically discovered.

IAM Role for AWS Configuration

If the Snapshot Manager is deployed in cloud, AWS configuration can be configured to use IAM role for authentication.

See "Add a cloud provider for a Snapshot Manager" on page 14.

Before proceeding, ensure the following:

- IAM role is configured within AWS. See the NetBackup Snapshot Manager Install and Upgrade Guide for details.
- After you upgrade NetBackup and Snapshot Manager to the latest version, you need to update the credentials. Run the following command:

tpconfig -update -snapshot_manager <snapshot manager host>
-snapshot_manager_user_id <snapshot manager user ID>
-manage workload <workload type> -security token <security token>

Note: Post upgrade, credentials are updated to support only IAM role.

The following implementations of IAM role are supported:

- Source account: In this case, the cloud assets that need to be protected are in the same AWS account as Snapshot Manager. Thus, AWS cloud is aware of the AWS account ID and role name, you need to only select the region.
- Cross account: In this case, the cloud assets that need to be protected are in a different AWS account than Snapshot Manager. Thus, you need to enter the target account and the target role name details along with the region so that Snapshot Manager can access those assets.

You need to establish a trust relationship between the source and the target account. For example, if this is the role ARN for the role you want to use to configure the plugin:

arn:aws:iam::935923755:role/TEST_IAM_ROLE So, to configure the plugin, provide the last part of the ARN, the name:TEST_IAM_ROLE For more details, refer to the Access AWS Accounts Using IAM Roles related

information in the Amazon Web Services documentation.

Associate media servers with a Snapshot Manager

You can use a media server to offload the snapshots and restores jobs of your cloud. To enable that you must associate one or more media servers to a Snapshot Manager. The media servers must be in an active state to run the snapshot or restore jobs. The media server that you associate with the Snapshot Manager must be associate to your NetBackup master server also. However, the discovery jobs run on the NetBackup master server only.

To associate media servers with a Snapshot Manager

- 1 On the left, click **Cloud**.
- 2 Click on the **Snapshot Manager** tab.
- 3 From the menu next to the Snapshot Manager, click Advanced settings.
- 4 In the **Media server** tab, select one or more media servers that you want associate with the Snapshot Manager.
- 5 Click Save.

Discover assets on Snapshot Manager

After you configure your cloud providers with a Snapshot Manager, automatic discovery is triggered to discover assets from the cloud. During periodic discovery, NetBackup pulls the assets data from Snapshot Manager every two hours whereas Snapshot Manager pulls the asset data from cloud provider configurations every

one hour. If you disable a Snapshot Manager, all the assets associated with that server are no longer protected or synced with NetBackup.

You can also manually trigger the cloud asset discovery if required, using the *Discover* option for individual cloud provider configurations, or you can trigger a discovery on a Snapshot Manager to fetch the assets data available on the Snapshot Manager.

After the first full discovery, NetBackup subsequently performs periodic incremental discovery of assets for the configured Snapshot Manager. It only detects the changes, such as addition, removal, or modification of assets, that occurred between the last and current discovery.

Note: For the accurate incremental discovery, ensure that the time is set correctly on the NetBackup master server and the Snapshot Manager, according to the time-zones they are located in, to avoid any issues with the discovery.

The following procedure describes how to perform discovery at the Snapshot Manager level, which does not actually discover the assets from the Cloud, but only fetches the point-in-time data from Snapshot Manager.

To discover assets on Snapshot Manager

- 1 On the left, click **Cloud**.
- 2 Click on the Snapshot Manager tab
- **3** From the menu next to the Snapshot Manager, click **Discover**.

The following procedure describes how to perform discovery at the configuration level, which triggers a deep discovery of assets and fetches the point-in-time state of the assets detecting any additions, modifications, or deletion of assets in the Cloud.

To discover assets for a cloud provider configuration

- 1 On the left, click **Cloud**.
- 2 Click on the Snapshot Manager tab
- **3** Click the Snapshot Manager IP or hostname for which to view the cloud providers.
- 4 Click on the provider tab for which to view the configurations.
- 5 From the menu next to the configuration name, click **Discover**.

Note: If the discovery on cloud provider configurations takes more than 30 minutes, the discovery operation times out. But the subsequent operation continues which syncs the NetBackup assets with the Snapshot Manager assets.

Change the autodiscovery frequency for Snapshot Manager

Use nbgetconfig and the nbsetconfig commands to view, add, or change the autodiscovery option. For example:

CLOUD AUTODISCOVERY INTERVAL = number of seconds

See the NetBackup Administrator's Guide, Volume I for more details.

Edit a Snapshot Manager

You can update the Snapshot Manager credentials. However, you cannot edit the Host name, IP address or Port of a Snapshot Manager.

To edit a Snapshot Manager

- 1 On the left, click, **Cloud**.
- 2 Click on the Snapshot Manager tab.
- 3 From the menu next to the Snapshot Manager, click Edit.

You can only edit the credentials for Snapshot Manager. You must validate the certificate before you can update the credentials.

- 4 Update the credentials.
- 5 In the Token field, enter a Reissue token for Snapshot Manager
- 6 Click Save.

Enable or disable a Snapshot Manager

Based on your preference, you can enable or disable a Snapshot Manager. If you disable a Snapshot Manager, you cannot discover assets or assign protection plans.

To enable or disable a Snapshot Manager

- 1 On the left, click **Cloud**.
- 2 Click on the **Snapshot Manager** tab.
- **3** Based on the Snapshot Managerstatus, select **Enable** or **Disable**.

Note: After disabling a Snapshot Manager protection for the associated assets will start failing for that server. In that case, unsubscribe the assets from the protection plans or cancel any pending SLP operations to avoid seeing job failures during the time it is disabled.

(Optional) Add the Snapshot Manager extension

The Snapshot Manager extension serves the purpose of scaling the capacity of the Snapshot Manager host to service a large number of requests concurrently running on the Snapshot Manager server at its peak performance capacity. You can install one or more Snapshot Manager extensions on-premise or in cloud, depending on your requirements to run the jobs without putting the host under additional stress. An extension can increase the processing capacity of the Snapshot Manager host.

The Snapshot Manager extension can have the configuration same or higher as the Snapshot Manager host.

Supported Snapshot Manager extension environments:

- VM based extension for on-premise
- Cloud based extension with managed Kubernetes cluster

Refer to *Deploying Snapshot Manager extensions* chapter in the latest version of NetBackup Snapshot Manager Install and Upgrade Guide.

Managing intelligent cloud groups

You can create and protect a dynamic group of assets by defining the intelligent cloud asset groups based on a set of filters called queries. NetBackup selects the cloud virtual machines, applications, or volumes based on the queries, and adds them to the group. An intelligent group automatically reflects changes in the asset environment and eliminates the need to manually revise the list of assets in the group when the assets are added or removed from the environment.

Then when you apply protection plan to an intelligent cloud asset group, all the assets satisfying the query conditions will automatically be protected if the asset environment changes in future.

Note: You can create, update, or delete the intelligent groups only if your role has the necessary RBAC permissions for the cloud assets that you require to manage. The NetBackup security administrator can grant you access for an asset type (VM, PaaS, application, volume, network) associated with a specific account or subscription, or at a cloud provider level. Refer to the *NetBackup Web UI Administrator's Guide*.

Create an intelligent cloud group

To create an intelligent cloud group

- 1 On the left, click **Cloud**.
- 2 Click the Intelligent groups tab and then click + Add.
- **3** Enter a name and description for the group.
- 4 Select the cloud provider, account ID, and region.

Note: If region is not specified, then the cloud intelligent group protects assets across region.

- 5 Select the Asset type.
- 6 Then do one of the following:
 - Select Include all assets of the selected type.
 This option uses a default query to select all assets for backup when the protection plan runs.
 - To select only the assets that meet specific conditions, create your own query: Click Add condition.

7 To add a condition, use the drop-downs to select a keyword and operator and then enter a value.

See the section called "Query options for creating intelligent cloud groups" on page 24.

To change the effect of the query, click **+ Condition** and click **AND** or **OR**, then select the keyword, operator, and value for the condition. For example:

Asset type					
Include all assets of th	e selected type				Preview
AND OR					+ Condition + Sub-query
displayName	~	Contains	~	CP	÷
taginame	~	Starts with	~	eng	÷
AND OR					♦ Condition ♦ Sub-query
state	~		~	running	
					Cancel Add and Protect Add

This example uses **AND** to narrow the scope of the query: It selects only the VMs that have cp in their display name and that also have a tag name as eng, and are in running state.

Note: Special character '<' is not supported in a tag name. If present, asset group creation will fail.

Note: Known limitation in NetBackup - if you create a query that has the asset tag names (referenced from your cloud provider) containing spaces or special characters such as (,), &, \, /, ", [,], {, }, you cannot later edit the query for editing any parameters. This does not prevent you from successfully creating the intelligent group and applying the protection plan to it. Only the Edit query functionality is affected with this limitation.

To avoid this issue, ensure that the tag names do not contain the specified special characters and create a new query with the new tag names.

You can also add sub-queries to a condition. Click **+ Sub-query** and click **AND** or **OR**, then select the keyword, operator, and value for the sub-query condition.

8 To test the query, click **Preview**.

The query-based selection process is dynamic. Changes in the virtual environment can affect which assets the query selects when the protection plan runs. As a result, the assets that the query selects later when the protection plan runs may not be identical to those currently listed in the preview.

Note: When using queries in **Intelligent groups**, the NetBackup web UI might not display an accurate list of assets that match the query if the query condition has non-English characters.

Using the not equals filter condition on any attribute returns assets including those that have no value (null) present for the attribute. For multi-value attributes such as tag, the assets that do not match at least one of the values of the attribute are not returned

Note: When you click **Preview** or you save the group, the query options are treated as case-sensitive when the assets are selected for the group. Under **Virtual machines**, if you click on a VM that was not selected for the group, the **Intelligent groups** field reads none.

9 To save the group without adding it to a protection plan, click **Add**.

To save the group and apply a protection plan to it, click **Add and protect**. Select the plan, and click **Protect**.

Query options for creating intelligent cloud groups

Note: The attribute values may not match exactly with values shown on the cloud provider's portal. You can refer to the asset details page or the cloud provider's API response of an individual asset.

Keyword	Description	
	(all values are case-sensitive)	
displayName	Asset's display name.	
state	For example, running, stopped etc.	
tag	A label assigned to the asset for categorization.	

Table 1-3 Query keywords

Keyword	Description	
	(all values are case-sensitive)	
instanceType/machineType/vmSize	Asset's instance/machine type or VM size, depending on the cloud provider selection.	
	For example, t2.large, t3.large, or b2ms, d2sv3	

 Table 1-3
 Query keywords (continued)

Table 1-4Query operators

Operator	Description
Starts with	Matches the value when it occurs at the start of a string.
Ends with	Matches the value when it occurs at the end of a string.
Contains	Matches the value you enter wherever that value occurs in the string.
=	Matches only the value that you enter.
!=	Matches any value that is not equal to the value that you enter.

Note: Once you create an intelligent group, you cannot edit the cloud provider selection for it, but you can edit the name and description, and modify the query as required.

Delete an intelligent cloud group

To delete an intelligent cloud group

- 1 On the left, click **Cloud**.
- 2 Locate the group under the Intelligent groups tab.
- 3 If the group is not protected, select it and then click **Delete**.
- 4 If the group is protected, click on the group, scroll down and click **Remove protection**.
- 5 Then select that group under the **Intelligent groups** tab and click **Delete**.

Protecting cloud assets or intelligent cloud groups

You can create the cloud provider-specific protection plans for your cloud workloads. Then you can subscribe the assets that are associated with the cloud provider to a provider-specific protection plan.

Note: If you previously had a protection plan that was applied to assets from different cloud providers, it is automatically converted to the new provider-specific format. This conversion happens after an upgrade to NetBackup 9.1. For example, if you had the assets from Google Cloud and AWS Cloud that are subscribed to one protection plan, then the protection plan is split. The protection plan is split into two separate protection plans for each provider.

See the section called "Conversion of protection plans after an upgrade to NetBackup 9.1" on page 27. section.

Use the following procedure to subscribe a cloud VM, application, volume, or an intelligent group to a protection plan. When you subscribe an asset to a protection plan, you assign predefined backup settings to the asset.

Note: The RBAC role that is assigned to you must give you access to the assets that you want to manage and to the protection plans that you want to use.

To protect a cloud asset or an intelligent group

- 1 On the left, click **Cloud**.
- 2 On the Virtual machines tab, or Applications tab, or Volumes tab or Intelligent groups tab, click the box for the asset or the asset group and click Add protection.
- 3 Select a protection plan and click Next.
- 4 You can adjust the following settings:
 - Schedules and retention
 - Storage options

For more information about storage options in the web UI, review the *Configuring storage* section in the NetBackup Web UI Administrator's Guide.

- Backup options
- 5 Click Protect.

Backup now option for immediate protection

Apart from the scheduled protection plans, you can also use the **Backup now** option to backup an asset immediately, to safeguard against any unplanned circumstances.

- 1. Select a cloud asset or an intelligent group and click **Backup now**.
- 2. Then select a protection plan to apply. Only the protection plans relevant to a specific cloud provider of the asset are displayed as options.
- 3. Click Start backup.

A backup job is triggered, which can be tracked on the **Activity monitor** page.

For more information, see NetBackup Web UI Administrator's Guide.

Conversion of protection plans after an upgrade to NetBackup 9.1

Note the following points with respect to the automatic conversion of older protection plans to the new format.

- Protection plan conversion starts when the asset migration is completed after the upgrade of NetBackup to 9.1.
- Old protection plans with no assets subscribed are not converted to the new format. You can manually delete them.
- Before or during conversion
 - All the assets are unsubscribed from the old protection plan and subscribed to the converted protection plan.
 - No new assets can be subscribed to the old protection plan.
 - The **Backup now** operation fails for the old plan.
 - Customizing or editing the old protection plan is prevented.

After successful conversion

- If the old protection plan was used to protect the assets from only one cloud provider, then the new plan retains the same name and asset subscription upon conversion.
- If the old protection plan was used to protect the assets from multiple cloud providers, then the name of the old protection plan is retained as before. The protection plan name is updated to retain the asset subscription for any one cloud provider upon conversion.

For the other cloud providers which were part of the old plan, new protection plans are created upon conversion, and only the assets of respective

providers are subscribed to them. New plans are named in the following format <old plan name> <cloud provider>.

- Hence you may see more number of plans in your *Protection Plans* menu on the web UI than before.
- Success messages are shown in the notifications as follows: The protection plan <protectionPlanName> created during conversion to new format.

Successfully converted the protection plan <protectionPlanName> to the new format.

Then you can start managing and applying the converted protection plans as normal.

Failure scenarios

Refer to the following to know how the failure scenarios are handled during or after the conversion of protection plans. Also check the notifications for any failure alerts and take the necessary action.

- Some of the assets might fail to get unsubscribed from the old protection plan. In that case, the conversion still continues with the assets that are successfully unsubscribed. The conversion process for the assets that failed, is retried every 4 hours.
- After the conversion, some of the assets might fail to get automatically re-subscribed to the new plan. In that case, you need to manually subscribe those assets to the converted protection plan.
- Failure might be encountered when the required access permissions are assigned to the new, converted protection plan. In that case, you need to manually assign the access permissions.

Customize or edit protection for cloud assets or intelligent groups

You can edit certain settings for a protection plan, including schedule backup windows and other options.

To customize or edit the protection plan for a cloud asset

- 1 On the left, click **Workloads > Cloud**.
- 2 On the Virtual machines tab, or Applications tab, or Volumes tab or Intelligent groups tab, click on the asset that you want to customize the protection for.
- 3 Click Customize protection > Continue.
- 4 You can adjust one or more of the following settings:

Schedules and retention

Change the backup start window.

Backup options

Enable/disable regional snapshots for Google Cloud assets, or specify/change snapshot destination resource group for Azure and Azure Stack Hub assets.

Remove protection from cloud assets or intelligent groups

You can unsubscribe a cloud asset from a protection plan. When the asset is unsubscribed, backups are no longer performed.

To remove protection from a cloud asset

- 1 On the left, click **Cloud**.
- 2 On the Virtual machines tab, or Applications tab, or Volumes tab or Intelligent groups tab, click on the asset that you want to remove the protection for.
- 3 Click Remove protection > Yes.

Cloud asset cleanup

Cloud assets are cleaned up automatically during cleanup cycle or manually based on the following criteria:

- No active protection plan to cloud asset.
- Asset is not discovered in last 30 days (cleanup age).
- No recovery points exist.
- Asset is marked for deletion (asset is deleted on Snapshot Manager).

User can enhance this cloud asset cleanup criteria by updating cleanup-age and providing specific filter criteria for assets through bp.conf file. Following parameters must be configured in bp.conf file:

- CLOUD.CLEANUP_AGE_MINUTES
- CLOUD.CLEANUP_FILTER

For example,

```
/usr/openv/netbackup/bin/nbsetconfig
nbsetconfig> CLOUD.CLEANUP_AGE_MINUTES = 180
nbsetconfig> CLOUD.CLEANUP_FILTER = "provider eq 'aws'"
```

nbsetconfig>

User can also manually run the POST query using the cleanup-assets named query with the following request body and then run GET with query ID obtained from the POST response, as described in the following example:

```
{
   "data":{
    "type":"query",
   "attributes":{
        "queryName":"cleanup-assets",
        "workloads":["cloud"],
        "parameters": {
            "cleanup_age_minutes": 180
        },
        "filter": "provider eq 'aws'"
      }
}
```

Cloud asset filtering

User can define custom filter based on attributes, which would be used to list assets into Virtual machines, Applications, PaaS, and Volumes tab.

To create a filter

- 1 On the left, click **Cloud**.
- 2 Under the Virtual machines, Applications, PaaS, or Volumes tab, click on the **Filter** icon on the right top of the screen.

The Create filter option is displayed.

- **3** Click the **Create filter** option to define custom filter based on attributes to list assets into Virtual machines, Applications, PaaS, or Volumes tab.
- **4** To create a filter, enter the details for the following parameters:

Parameter	Description
Name	Name of the filter.
Description	Provide the description for the filter.
Query	To select only the assets that meet specific conditions, create your own query.

- **5** To select only the assets that meet specific conditions, create your own query: Click **+ condition**.
- **6** To add a condition, use the drop-downs to select a keyword and operator and then enter a value.

See the section called "Query options for creating intelligent cloud groups" on page 24.

To change the effect of the query, click **+ Condition** and click **AND** or **OR**, then select the keyword, operator, and value for the condition. For example:

Create filter						×
Name * ams-cloud-assets			Description Enter description			
AND OR					+ Condition	+ Sub-query
- Provider V	Contains	×	aws			
Name ~	Contains	v	cloudpoint			8
				Cancel Save Save and ad	d another	Save and apply

This example uses **AND** to narrow the scope of the query: It selects only the assets that have aws in their display name and that also have a **Name** as cloudpoint, and are in running state.

You can also add sub-queries to a condition. Click **+ Sub-query** and click **AND** or **OR**, then select the keyword, operator, and value for the sub-query condition.

Query options for creating filter

Note: The attribute values may not match exactly with values shown on the cloud provider's portal. You can refer to the asset details page or the cloud provider's API response of an individual asset.

Table 1-5Query keywords

Keyword	Description
	(all values are case-sensitive)
Server type	Type of the server.

Keyword	Description		
	(all values are case-sensitive)		
Instance ID	Asset's instance ID, depending on the cloud provider selection.		
Instance name	Asset's instance name, depending on the cloud provider selection.		
Name	Asset's display name.		
Provider	Asset's cloud provider name.		
Region	Asset's cloud provider region name.		
Config ID	Asset's config ID.		
Database service	Asset's database service.		
Deleted	Deleted asset.		
Entity type	Asset's entity type.		
Service domain	Asset's service domain.		
Snapshot Manager	The instance of Snapshot Manager with which the asset is registered.		

 Table 1-5
 Query keywords (continued)

Table 1-6Query operators

Operator	Description
Starts with	Matches the value when it occurs at the start of a string.
Ends with	Matches the value when it occurs at the end of a string.
Contains	Matches the value you enter wherever that value occurs in the string.
=	Matches only the value that you enter.
!=	Matches any value that is not equal to the value that you enter.

AWS and Azure government cloud support

Starting with 8.3, the Snapshot Manager can discover Amazon Web Services and Microsoft Azure US Government cloud workloads. After the Snapshot Manager is added to NetBackup, you can protect the workloads by NetBackup. NetBackup is compliant with the regulatory requirements including IPv6 support to deploy Snapshot Managert on the AWS and Azure US government cloud workloads.

After you configure AWS or Azure US Government cloud, the AWS and Azure agent service is created which discovers the cloud assets based on provided region. The discovered assets are displayed in NetBackup. Currently, only workloads from selected regions and mapped endpoint are discovered and protected. For the same Snapshot Manager host, you cannot use a combination of public and government clouds.

An error might occur if you update a cloud plug-in when the plug-in assets operations are in-progress.

Snapshot Manager supports the following GovCloud (US) regions:

Amazon Web Services

GovCloud (US) regions

- us-gov-east-1
- us-gov-west-1

Microsoft Azure

- US Gov Arizona
- US Gov Texas
- US Gov Virginia

Note: PaaS assets does not support government cloud.

For information about configuring AWS and Microsoft Azure, See "Add a cloud provider for a Snapshot Manager" on page 14.

About protecting Microsoft Azure resources using resource groups

NetBackup lets you define a peer Resource Groups snapshot destination for every resource group that contains protected virtual machines and volumes.

All resources in Microsoft Azure are associated to a resource group. After a snapshot is created, it is associated to a resource group. Also, each resource group is associated to a region. See the following:

https://docs.microsoft.com/en-us/azure/azure-resource-manager/ management/manage-resource-groups-portal

Snapshot Manager creates a snapshot and places the snapshot in resource group to which the resource belongs even under the following conditions:

- If you don't provide a prefix for a resource group
- Peer resource groups are not created
- You allow the snapshots to get created

You can configure the settings to place the snapshots in different resource group than the resource group that is associated with the resource. However, note the following important points:

- The peer resource group must be in the same region as the region of the resource group of the resource.
- If a peer resource group is not found, the configurations determine whether the snapshots creation succeeds or fails.

To enable this feature, you must create peer resource groups. Snapshot Manager then appends the prefix of the resource group that is associated with the resource. When a snapshot is created, the peer resource group name is derived based on the prefix and the resource group to which the resource is associated.

Note: You can now directly associate a snapshot to an existing peer resource group, at the time of creating a protection plan. However the functionality of defining a peer resource group by specifying a prefix which is described in this section, still exists.

Refer to information on creating protection plans in the *NetBackup Web UI Administrator's Guide* for the complete procedure.

Before you begin

- The peer resource groups must be available for resources that are being protected using the resource group.
- Regions of a plugin configuration must not overlap with another configuration if a prefix is specified.

Limitations and considerations

- Only alphanumeric characters, periods, underscores, hyphen, or parenthesis are allowed in the resource group names.
- The prefix length must be less than 89 characters.

 You cannot use characters that Azure configuration does not allow for resource group naming conventions.

About resource group configurations and outcome

The following table lists scenarios for virtual machines and resource group setup, resource configuration, and outcome.

Resource group prefix	Protect assets even if prefixed Resource Groups are not found check box	Outcome		
Not specified	Not selected	NetBackup associates the newly created snapshots in resource group of the resource.		
Specified Not selected		 NetBackup creates new the snapshots and associates the snapshots to the peer resource group if the following conditions are met: The peer resource group is created. The peer resource group is in the same region as the resource group. If the conditions are not met 		
		snapshot jobs fail.		
Specified	Selected	 NetBackup creates new snapshots and associates the snapshots to the peer resource group if the following conditions are met: The peer resource group is created. The peer resource group is in the same region as the resource group. If a peer resource group is not created or is in a different region then the newly created snapshot is associated to the resource group of the resource group of 		

 Table 1-7
 Configurations and outcome

Examples of resource group configurations

The following table lists the examples for resource group configurations.

Conditions	Configurations	Result	
 OS and all disks are in the same resource group. Peer resource group is named correctly. Peer resource is located in the same region as resource group of resource. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is selected. 	Snapshots are created in the peer resource group.	
 OS and all disks are in separate resource groups. Peer resource groups are named correctly. Peer resources are located in the same region as resource groups of resources. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is selected. 	Snapshots are created in the peer resource group.	
 OS and all disks are in the same resource group. Peer resource group is created in a different region from the resource group of the resource. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is selected. 	The snapshots are created in original resource group not the peer resource group.	
 OS and all disks are in the same resource group. Peer resource group is not created. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is selected. 	The snapshots are created in original resource group not the peer resource group.	

Table 1-8Example configurations
Conditions	Configurations	Result
 OS and all disks are in separate resource groups, RG1 and RG2. Peer resource groups RG1 is named correctly and located in the same region as the resources. Peer resources group RG2 is not created. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is selected. 	Snapshots are created in the peer resource group of RG1 and original resource group RG2.
 OS and all disks are in same resource group. Peer resource groups are named correctly. Peer resources group is located different region than the resource group of resources. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is not selected. 	Snapshots are not created and the job fails.
 OS and all disks are in the same resource group. Peer resource group is not created. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is not selected. 	Snapshots are not created and the job fails.
 OS and all disks are in separate resource groups, RG1 and RG2. Peer resource groups of RG1 and RG2 that is, snapRG1 and snapRG2 are in different regions. Peer resource group snapRG1 is located in the same region as the resource group RG1. The peer resource group snapRG2 is located in a different region than resource group RG2. 	 Resource Group Prefix value is provided. The Protect assets even if prefixed Resource Groups are not found check box is not selected. 	Snapshots are not created and the job fails.

 Table 1-8
 Example configurations (continued)

Troubleshoot resource group permissions

If appropriate permissions are not assigned to the resource group, the snapshot creation fails for Azure resources that are associated to resource groups.

Workaround:

To resolve this issue, perform the following steps:

- 1. Navigate to https://portal.azure.com/#blade/HubsExtension/BrowseResourceGroups.
- 2. Click on the resource group, that is to be used in the snapshot.
- 3. Click on Access control (IAM).
- 4. Click on Add Role Assignment.
- 5. Select Role as Owner, Assign Access to as User, and select the Application (created for Snapshot Manager, to make API calls).
- 6. Save and try to backup again.

About the NetBackup Accelerator for cloud workloads

NetBackup Accelerator reduces the backup time for cloud backups. NetBackup uses reference snapshots to identify the changes that were made within a virtual machine. Only the changed data blocks are sent to the NetBackup media server, to significantly reduce the I/O and backup time. The media server combines the new data with previous backup data and produces a traditional full NetBackup image that includes the complete virtual machine files.

NetBackup supports Accelerator backup for AWS, Azure and Azure Stack workloads.

Note: Accelerator is most appropriate for virtual machine data that does not experience a high rate of change.

Accelerator has the following benefits:

- Performs the full backups faster than traditional backup. Creates a compact backup stream that uses less network bandwidth between the backup host and the server. Accelerator sends only changed data blocks for the backup. NetBackup then creates a full traditional NetBackup image that includes the changed block data.
- Accelerator backups support Granular Recovery Technology (GRT).

- Reduces the I/O on the Snapshot Manager.
- Reduces the CPU load on the Snapshot Manager.

How the NetBackup Accelerator works with virtual machines

For Azure and Azure Stack backups, Accelerator is activated when you select a Accelerator supported storage type, like MSDP, OpenStorage, CloudStorage, and MSDP-C (Azure and AWS).

The NetBackup Accelerator creates the backup stream and backup image for each virtual machine as follows:

- If the virtual machine has no previous backup, NetBackup performs a full backup.
- At the next backup, NetBackup identifies data that has changed since the previous backup. Only changed blocks and the header information are included in the backup, to create a full VM backup. The changed blocks are identified by comparing the previous reference snapshot and the current snapshot. If you select Keep backup only or Initiate backup when snapshot is about to expire option in the protection plan, the snapshot is retained for accelerator purpose till the next backup is completed.
- The backup host sends to the media server a tar backup stream that consists of the following: The virtual machine's changed blocks, and the previous backup ID and data extents (block offset and size) of the unchanged blocks.
- The media server reads the virtual machine's changed blocks, the backup ID, and information about the data extents of the unchanged blocks. From the backup ID and data extents, the media server locates the rest of the virtual machine's data in existing backups.
- The media server directs the storage server to create a new full image that consists of the following: The newly changed blocks, and the existing unchanged blocks that reside on the storage server. The storage server may not write the existing blocks but rather link them to the image.
- Microsoft Azure does not allow more than 200 subsequent incremental snapshots. If you select the Keep snapshot along with backup option in the protection plan and specify a such a retention period for the snapshot, so that it leads to more than 200 incremental snapshots. Then, full backups take place instead of accelerator. It is recommended to keep a reasonable snapshot retention period to utilize the accelerator benefits.
- If the configuration of a VM changes, for example, if a new disk is added to a VM between two accelerator backups, a full backup is taken for that disk, and accelerator backup is taken for the existing disks.

Accelerator forced rescan for virtual machines (schedule attribute)

Accelerator forced rescan helps to prevent corrupt backup image issues by manually executing the ForcedRescan command. When Accelerator forced rescan is used, all the data on the virtual machine is backed up. This backup is similar to the first Accelerator backup for a policy. For the forced rescan job, the optimization percentage for Accelerator is 0. The duration of the backup is similar to a non-Accelerator full backup.

Force rescan enhances safety, and establishes a baseline for the next Accelerator backup. This feature protects against any potential damage like failure of checksum verification on the data in the staging area.

Recommendations for using forced rescan:

- Do not trigger force rescan for the VMs which are turned off.
- If the storage location memory is full, you can see a notification in the UI. Initiate the force rescan only when sufficient memory is available at the storage location.

NetBackup creates a schedule named 'ForcedRescan' for every protected VM. To manually trigger the backup with force rescan execute the following command in the command prompt or the Linux terminal:

bpbackup -i -p <policy_name> -s ForcedRescan
For example, bpbackup -i -p
msdp 10mins FRS+5d990ab5-f791-474f-885a-ae0c30f31c98 -s ForcedRescan

You can obtain the policy name from web UI from the relevant protection plan.

Accelerator backups and the NetBackup catalog

Use of Accelerator does not affect the size of the NetBackup catalog. A full backup with Accelerator generates the same catalog size as a full backup of the same data without Accelerator. The same is true of incremental backups: use of Accelerator does not require more catalog space than the same backup without Accelerator.

Accelerator messages in the backup job details log

When a virtual machine is first backed up, Accelerator is not used for that backup. The following messages appear in the job details log:

Jul 21, 2021 1:55:52 PM - Info bpbrm (pid=78332) accelerator enabled Jul 21, 2021 1:55:53 PM - Info bpbrm (pid=78332) There is no complete backup image match with track journal, a regular full backup will be performed. ••

Jul 21, 2021 1:56:11 PM - Info bpbkar (pid=1301) accelerator sent 402666496 bytes out of 402664960 bytes to server, optimization 0.0%

When subsequent backups of the virtual machine use Accelerator, the following messages appear in the job details log:

Jul 21, 2021 2:01:33 PM - Info bpbrm (pid=79788) accelerator enabled
...
Jul 21, 2021 2:02:00 PM - Info bpbkar (pid=1350) accelerator

sent 1196032 bytes out of 402664960 bytes to server, optimization 99.7%

This message is a key trace for Accelerator. In this example Accelerator was successful at reducing the backup data by 99.7%.

Configuring backup schedule for cloud workloads

You can add backup schedule in the Attributes tab of the Add backup schedule dialog, while creating a protection plan for the Azure, Azure Stack, AWS and GCP cloud workloads.

See the *Managing protection plans* section of the *NetBackup Web UI Administrator's Guide*, for details of how to create a protection plan.

To add backup schedule to a cloud workload

- 1 On the left, click **Protection > Protection plans** and then click **Add**.
- 2 In Basic properties, enter a Name, Description, and select Cloud, from the Workload drop-down list.
- 3 Select a Cloud Provider from the drop-down list, click Next. In Schedules, click Add schedule.

In the **Add backup schedule** tab, you can configure the options for retaining the backup and the snapshot.

4 (For Azure SQL PaaS assets only.) If you have selected Protect PaaS assets only for the protection plan, select Backup type as Incremental backup or Full. For incremental backup type, NetBackup taken an initial full backup, and all subsequent backups capture only incremental changes in the database. This feature increases backup performance to a great extent. In case of a schema change, goes back to full backup from incremental backup, and notifies this activity in the activity monitor.

Assign a longer retention period to full backups than to incremental backups within a policy. A complete restore requires the previous full backup plus all subsequent incremental backups. It may not be possible to restore all the files if the full backup expires before the incremental backups. See "About incremental backup for PaaS workloads" on page 62.

- 5 From the **Recurrence** drop-down, specify the frequency of the backup.
- 6 In the Snapshot and backup options, do any of the following:
 - Select Keep snapshot along with backup option to retain both the snapshot and the backup. Specify retention period for both the snapshot and the backup, using the Keep snapshot for and the Keep backup for drop-downs. Select Full from the Backup type drop-down. Select Initiate backup only when the snapshot is about to expire option, to start the backup job just before the retained snapshot expires.
 - Select Keep snapshot only option, to retain only the snapshot. Specify retention period for the snapshot using the Keep snapshot for drop-down.
 - (Optional) If you have selected provider as Amazon AWS, and selected to retain the snapshot by selecting any of the above two options, you can configure snapshot replication at this point. For more information about cloud snapshot replication, See "Configure AWS snapshot replication" on page 47.
 - Select Enable Snapshot replication.
 - In the table, select Region, AWS Account, and Retention period for the replicated snapshots.

Note: The number of replication copies that you configure is displayed in the **Snapshot replicas** column in the **Schedules and retention** table in the **Schedules** tab.

 Select Keep backup only option, to retain only the backup. The snapshot expires immediately after the backup. Specify retention period for the backup using the Keep backup for drop-down. Select Full from the Backup type drop-down. **Note:** As NetBackup supports granular restore only from the snapshot, if you select **Keep Backup Only** the granular recovery options do not work. Similarly, AWS snapshot replication feature does not work if you select **Keep Backup Only**.

7 Continue creating the schedule in the **Start window** tab, as described in the *Managing protection plans* section of the *NetBackup Web UI Administrator's Guide*.

Availability of granular recovery for different backup options

Availability of the granular recovery for files or folders option, depends on the different backup options that you select for the workload.

- When you select the Keep snapshot along with backup option, granular recovery is available.
- When you select the Keep snapshot only option, granular recovery is available.
- When you select the **Keep backup only** option, granular recovery is not available.

Indexing during backup and snapshot jobs

- NetBackup performs VxMS (Veritas Mapping Service) based indexing from snapshot, and inline indexing during the backup from snapshot Jobs. It can index files irrespective of the region and location of the Snapshot Manager.
 VxMS based indexing is currently supported for GCP, AWS, Azure, and Azure Stack Hub clouds.
- Indexing is performed during the actual backup or snapshot jobs, but you can perform the recovery of individual files or folders only from the snapshot copy using Enable granular recovery for files and folders option.
- Once the snapshot of the VM assets is created, the 'Index from Snapshot' job for each of the assets is triggered. You can check the indexing job details in the Activity Monitor.
- The VxMS debug logs and the cloud connector debug logs are available in the /cloudpoint/openv/dm/datamover.<datamover-id>/netbackup/logs folder of the Snapshot Manager.

Note: If the VM is not in connected state, then the VM backup continues and the backup job is marked as partially successful. In this case, you cannot restore individual files or folders as the indexing is not available when the VM is not connected.

Backup options for cloud workloads

Note: For a connected VM, a file system consistent snapshot is attempted. In case a connected VM is stopped later, then the application enters into an error state and a crash consistent snapshot is taken instead of file system consistent snapshot. You can refer to the Job monitor and refer the logs if the snapshot taken was crash consistent or file system consistent snapshot.

Regional snapshots for Google cloud

You can choose to enable regional snapshots for the Google cloud workloads while creating a protection plan.

If the regional snapshot option is enabled, the snapshot will be created in the same region in which the asset exists. Otherwise, the snapshot will be created in a multi-regional location.



Snapshot destination resource group for Azure and Azure Stack Hub

You can choose to specify a snapshot destination peer resource group while creating a protection plan for Azure or Azure Stack Hub. While the previous functionality of defining a peer resource group by specifying a prefix still exists, you can now directly associate a snapshot to an existing peer resource group at the time of creating a protection plan.

If you have selected the cloud provider as Microsoft Azure or Azure Stack Hub while creating a protection plan, you can select **Specify snapshot destination resource group** to associate snapshots to a particular peer resource group within the same region in which the asset exists. Then select a configuration, subscription, and a resource group for a snapshot destination.

The snapshot is stored in one of the destination resource groups, in the following preference:

- A destination resource group specified in the protection plan
- A pre-fixed resource group specified in the plugin configuration (for Azure only)
- A resource group in which the asset exists, if no destination or pre-fixed resource group is specified in NetBackup.

eate protection plan		
Basic properties 🚽 🕑 Schedules	- 🕑 Storage options - 🕚 Backup e	options - (5) Permissions - (6) Re
Backup options		
Enable granular recovery for files or Specify snapshot destination resour	folders rce group	
Configuration name *		
azurecloudplugin	~	
Subscription name or ID * XXXXXXX (a332d749- XXXXXX-XXXXXX-X	00000000) ~	
Resource group	Region	
azure-scale-rhei83- mongo-dnd	eastus2	Select

Excluding selected disks from backup

You can configure a protection plan to exclude some disks from the backup and snapshot which are applicable to all supported cloud vendors including GCP. This enables you to avoid redundant images of the disks that do not need to be backed up, and speed up the backups by reducing the volume of data to be processed.

If you are creating a protection plan for AWS, Azure, Azure Stack Hub, or GCP clouds, you can select **Exclude selected disks from backups** option and specify the disks that should not be included in the backup image. You can choose to

exclude either all the non-boot disks, or the disks that have specific tags associated with them in the corresponding cloud provider account.

Create protection plan				×
Basic properties	Schedules	Backup options	Permissions	(i) Review
Backup options Chubic granular recovery for files or foldes Enable regional snapchot Chubic selected datas from backups @ All non boord datas Datas with a specific top @ Xey Lampler Nit, Differ, Checubit	0	Yalue Example true		

Note: A protection plan that has disk exclusion option enabled can be applied only to the cloud VM type assets and VM intelligent groups.

Then while restoring the VMs from the Recovery Points tab, refer to the **Includes disks** column to view the list of disks that are included or excluded in the backup image.

Refer to the information on creating a protection plan in the *NetBackup Web UI Administrator's Guide* for the complete procedure.

Notes:

- In case of LVM, if disks are excluded partially then system might not boot up properly.
- In case there is a non supported file system configured on a disk and user wants to exclude that disk from snapshot, the snapshot would continue to be crash consistent snapshot as the disk containing non supported file system is excluded.
- If the user wants to exclude the disk, he/she should have the nofail flag attached to the data disk prior to taking a snapshot in the /etc/fstab file. This is required if the user reboot the instance without this volume attached (for example, after moving the volume to another instance), the nofail mount option enables the instance to boot even if there are errors mounting the volume. For more information, refer to the following example entry in the /etc/fstab file:
 For example,UUID=aebf131c-6957-451e-8d34-ec978d9581ae /data xfs defaults,nofail 0 2
- The user should ensure that assets are properly discovered once there has been any change in their tags from the cloud provider. Once the policy run is scheduled for an asset, the disks are excluded as per the discovered data only.

If, the user attaches a tag while the snapshot is in progress, that **tag** would not be considered as a part of exclusion. Once discovery is completed, it will be considered during next protection cycle.

 In case of OS with non-English locale, if user opts tag based exclusion in protection plan and disk tag has non-English character, even then disk exclusion works as expected. But in some cases tag with non-English character is not correctly captured in job(try) logs and audit logs although there is no functionality impact as disk exclusion is considered correctly.

Snapshot replication

Replicating a snapshot means saving a copy of the snapshot to another location. In AWS, another location can be one of the following:

- different region within the same account.
- same region in a different account.
- different region within different account.

For example, an AWS cloud administrator have their assets in the region X. The snapshots of those assets will also be stored in X region. However, you can also replicate the snapshots to the Y region within same account or X/Y region in a different account, for an added level of protection. In NBU Snapshot Manager terminology, the original location (X) is the replication source, and the location where snapshots are replicated (Y) is the replication destination.

Replication is performed in three steps. This mechanism is handled internally and the entire process is completely transparent to the user.

- Share the snapshot, only if replicating to a cross account. For more information, see the Share a snapshot section of the AWS documentation.
- Copy the snapshot. For more information, see the CopySnapshot section of the AWS documentation.
- Unshare the snapshot, only if replicating to a cross account.

Configure AWS snapshot replication

Requirements for replicating snapshots

Replicating unencrypted snapshots

Ensure that the source and target accounts/regions are configured using the AWS cloud provider from NetBackup Snapshot Manager. There are no additional requirements for replicating unencrypted snapshots.

Replicating encrypted snapshots using AWS KMS

Ensure that the source and target accounts/regions are configured using the AWS cloud provider from NetBackup Snapshot Manager. Additionally, to replicate encrypted snapshots to a cross account, the encryption CMK key from the original location needs to be shared to the target account. (This shared KMS key is implicitly used while copying the snapshot in the target account, and the copied snapshot can be replicated by a different key). Both the source and target locations should have encryption key (KMS key) with same name; that is, they should have the same key alias (in terms of AWS). If encryption key with the same name is not present at the target, then the replicated snapshot is encrypted using the default KMS key in the target location.

Permissions for cross account replication

For cross-account replication, the AWS IAM user or role associated with the snapshot source region's AWS account (source AWS account) must have the following permissions:

- ModifySnapshotAttribute and CopySnapshot on the EC2 instance.
- DescribeKey and ReEncrypt on the KMS key that is used to encrypt the original snapshot.

For cross-account replication, the AWS IAM user or role associated with the snapshot replication target region's AWS account (target AWS account) must have the following permissions:

- CreateGrant, DescribeKey, and Decrypt on the KMS key that is used to encrypt the original snapshot.
- CreateGrant, Encrypt, Decrypt, DescribeKey, and GenerateDataKeyWithoutPlainText on the KMS encryption key used while performing the CopySnapshot operation on the original snapshot.

You can choose to replicate snapshots for AWS cloud assets from the primary location to a remote or a secondary location. The Snapshot Manager's support cross-region and cross account replication. With snapshot replication you can achieve the following:

- Maintain a copy of cloud assets at a different destination for long-term retention and auditing requirements.
- Recover cloud assets from the replicated copies from another region in case there is a region outage.
- Recover cloud assets from the replicated copies from another account in case the user account is compromised.

Configuration

Review the following information to configure snapshot replication:

- You can configure snapshot replication when you create a protection plan. See the NetBackup[™] Web UI Administrator's Guide.
- For cross account replication, you need to establish a trust relationship between the source and the target account. For more details, refer to the Across AWS Accounts Using IAM Roles related information in the Amazon Web Services documentation.

Considerations

Consider the following when you configure cloud snapshot replication:

- Even if multiple schedules are configured, the replication destination region that is configured is applied to all the schedules.
- Cloud snapshot replication is supported only for Amazon cloud providers.

Asset protection criteria

Consider the following before adding cloud assets to a protection plan that is configured for cloud snapshot replication:

 Assets must be added to a protection plan that replicates snapshots to a different region.

For example, assets residing in region 'aws_account_1-us-east-1' cannot be subscribed to a protection plan replicating to the same region 'aws_account_1-us-east-1'.

Assets can be replicated to a different account in the same region.

For example, assets residing in region 'aws_account_1-us-east-1' can be subscribed to a protection plan replicating to the same region but different account 'aws_account_2-us-east-1'.

- Assets that are discovered by a Snapshot Manager must be replicated to the region that is discovered by the same Snapshot Manager.
 For example, assets that are discovered by Snapshot Manager 'CP1' cannot be subscribed to a protection plan replicating to a region that is discovered by Snapshot Manager 'CP2'.
- Only Amazon assets can be subscribed to a protection plan that is configured for cloud snapshot replication.

Manage concurrent snapshots replications

For better performance, you can tune the number of concurrent snapshot replications. Amazon has different limits for each asset type to do concurrent

snapshot replications to a single destination region. For example, RDS has a limit for 5, EBS has a limit for 5, and EC2 has a limit for 50. For more details refer to *Copy Snapshot* related information in the *Amazon Web Services* documentation.

In NetBackup this limit is defined using the following parameter in the ${\tt bp.conf}$ file:

MAX_CLOUD_SNAPSHOT_REPLICATION_JOBS_PER_DESTINATION

The default value is 5.

Using AWS snapshot replication

This section elaborates how to create snapshot replicas using the AWS snapshot replication feature, and restore the replicated snapshots whenever required. Refer to the *NetBackup*[™] *Snapshot Manager Install and Upgrade Guide* and the *NetBackup Web UI Administrator's Guide* for details about these steps, otherwise indicated.

Creating snapshot replications

This section describes how to configure the Source region to create snapshot replicas in the Target region.

To create replicas

- 1 Add Snapshot Manager (CP1) in webUI. See "Add a Snapshot Manager" on page 13.
- 2 Add AWS plug-in for Source and Target region for replication.
- 3 Create protection plan and select **Region** and **Account**. See "Configuring backup schedule for cloud workloads" on page 41.
- **4** Connect and configure an application consistent guest VM using the OnHost agent.
- **5** Trigger snapshot-based backup and replicate the snapshots using the protection plan.
- 6 Verify the recovery points for snapshot and replica copy.

Restoring from the snapshot replicas in the target region

If the Source region fails, you can restore the VMs belonging to this region, from the Target region, where you have taken the snapshot replicas. As the Source region is down, you will initially need to restore the VMs in the Target region.

Note: You cannot restore single files or folders from a replica that was discovered by an alternate Snapshot Manager in a failed over region.

Restoring in the target region

- 1 Disable server CP1 in the Source region from webUI. See "Enable or disable a Snapshot Manager" on page 20.
- 2 Register a new Snapshot Manager (CP2) in the target region, from webUI.
- **3** Add AWS plug-in for only the Target region and account. Let the discovery complete.
- 4 To restore VMs:
 - Log on to the NetBackup web UI.
 - On the left, click Cloud, under Workloads. On the Virtual machines tab, click the machine that you want to recover.
 - Click the Recovery points tab. In the list of images, click Restore in front of the required Replica image, and click Restore virtual machine.
 - To change the Display name for the VM, enter a new name.
 - Select a subnet (subnet path having VPC).
 See "Recovering cloud assets" on page 74.
- 5 Add appropriate security group to the restored VMs to enable remote access.
- **6** Uninstall and reinstall the Snapshot Manager agent from the restored VMs, and then register the Snapshot Manager agents with the new CP2 server.
- 7 Run a deep discovery from the AWS provider console.
- **8** Create new protection plan to protect the restored VMs. Trigger a snapshot-based backup.

Restoring back to the source region from the target region

You can restore the VMs from the Target region to the Source region, once the source region is back online.

Restoring to the source region

- 1 Edit the AWS plug-in for CP2 and add the Source region.
- 2 Create a new protection plan to create a snapshot replica in the Source region.
- 3 Trigger snapshot-based backup and replicate.
- 4 Disable the CP2 server in webUI. See "Enable or disable a Snapshot Manager" on page 20.
- 5 Enable the CP1 server and trigger deep discovery from AWS provider console.
- 6 Perform full restore of the VMs from the Target region.
- 7 Add appropriate security group to enable remote access to restored VMs.

- **8** Uninstall and reinstall the Snapshot Manager agents from the restored VMs, and then register Snapshot Manager agents with the CP1 server.
- **9** Run a deep discovery from the AWS console.
- **10** Use the existing protection plan to protect newly restored VMs.

Support matrix for account replication

Asset types	Source asset (Region X)	Source snapshot (Region X)	Replicated snapshot (Region Y)
EBS Volume, EC2 Instance and RDS/Aurora	Unencrypted	Unencrypted	Unencrypted
	Attached disks encrypted using default AWS KMS key.	Attached disks encrypted using default AWS KMS key.	Attached disks encrypted using default AWS KMS key.
	Encrypted using AWS KMS CMK key (with Alias ABC).	Encrypted using AWS KMS CMK key (Alias ABC).	Encrypted using AWS KMS CMK key with name if present (Alias ABC), else encrypted using default AWS KMS key.

 Table 1-9
 Support matrix for same account replication

Asset types	Source asset (Account A Region X)	Source snapshot (Account A Region X)	Replicated snapshot (Account B Region Y)
EBS Volume, EC2	Unencrypted	Unencrypted	Unencrypted
Instance and RDS/Aurora	Encrypted using default AWS KMS key.	Encrypted using default AWS KMS key.	Not supported
	Encrypted using AWS KMS CMK key (with Alias ABC).	Encrypted using AWS KMS CMK key (with Alias ABC).	Encrypted using AWS KMS CMK key with name if present (with Alias ABC), else encrypted using default AWS KMS key.

 Table 1-10
 Support matrix for different account same region replication

Support matrix for different account different region replication

Asset types	Source asset (Account A Region X)	Source snapshot (Account A Region X)	Replicated snapshot (Account B Region Y)
EBS Volume and	Unencrypted	Unencrypted	Unencrypted
EC2 Instance	Encrypted using default AWS KMS key.	Encrypted using default AWS KMS key.	Not supported
	Encrypted using AWS KMS CMK key (with Alias ABC).	Encrypted using AWS KMS CMK key (with Alias ABC).	Encrypted using AWS KMS CMK key with name if present (with Alias ABC), else encrypted using default AWS KMS key.

(0	continued)		
Asset types	Source asset (Account A Region X)	Source snapshot (Account A Region X)	Replicated snapshot (Account B Region Y)
RDS	Unencrypted	Unencrypted	Unencrypted
	Encrypted using default AWS KMS key.	Encrypted using default AWS KMS key.	Not supported
	Encrypted using default AWS KMS key.	Encrypted using default AWS KMS key.	Not supported
Aurora	Unencrypted	Unencrypted	Not supported
	Encrypted using default AWS KMS key.	Encrypted using default AWS KMS key.	Not supported
	Encrypted using default AWS KMS key.	Encrypted using default AWS KMS key.	Not supported

Table 1-11 Support matrix for different account different region replication (continued)

Protect applications in-cloud with application consistent snapshots

You can take application consistent (point-in-time) snapshots of the applications that are deployed on virtual machines in cloud. This lets you perform a point-in-time recovery of applications.

You can perform original location and alternate location restores for these workloads.

For alternate location restore, consider the following:

- For alternate location restore of MS SQL workloads, the target host must be discovered but the application status should not be in connected or configured state.
- For alternate location restore of Oracle workloads, the target host must be discovered but the application status should not be in connected or configured state.

Before you begin

Ensure that the database is prepared for snapshots. For details review the plug-in configuration notes in the Veritas Snapshot Manager documentation.

To configure applications for point-in-time recovery

- 1 Connect to the virtual machine that hosts the applications.
 - After the cloud assets are discovered, go the Virtual Machines tab.
 - Select the virtual machine where the application is hosted. On the top right, click **Manage credentials**.
 - Enter the credentials. If the credentials for the VM are not configured, you
 must configure the credentials. See the *Managing credentials* chapter of
 the *WebUI Administrator Guide*.
 - After the virtual machines are connected, the virtual machines state is updated to Connected.
- 2 Select the virtual machine where the application is hosted. On the top right, click **Configure application**.
- **3** After the process is complete, the application status is updated to configured.
- **4** The applications are displayed under the **Applications** tab after the next discovery.
- 5 Apply the protection plan. See the *NetBackup Web UI Administrator's Guide*.

To edit or update virtual machine credentials

- 1 Go to the Virtual Machines tab.
- 2 Select the virtual machines for which you want to update credentials. On the top right, click **Manage credentials**.
- **3** Update the credentials.

To edit or update application configuration

- 1 Go to the **Applications** tab.
- 2 Select the application for which you want to update. On the top right, click Edit configuration
- **3** Update the credentials and click **Configure**.

Protecting PaaS assets

You can manage the PaaS assets after discovered by NetBackup. The assets are displayed in the **PaaS** and **Applications** tabs, under cloud workload. The

Applications tab displays the RDS assets, whereas the **PaaS** tab displays the non-RDS assets. You can view, protect, and recover PaaS assets from these two tabs.

Prerequisites for protecting PaaS assets

NetBackup lets you discover, protect, and restore PaaS assets across different cloud platforms for a variety of assets. This section details the supported platforms and databases.

Supported cloud providers

NetBackup enables you to protect PaaS assets with the following cloud providers:

- Microsoft Azure
- AWS
- GCP

Supported databases for different providers

The following table lists the supported databases for each cloud provider.

Providers	Supported databases
Microsoft Azure	PostgreSQL, SQL Managed Instance, SQL, MariaDB, and MySQL.
	The following components are not supported:
	Azure SQL - Elastic pool
	Azure SQL Managed Instance - Azure Arc
	Azure PostgreSQL - Hyperscale (Citus) server group and Azure Arc enabled PostgreSQL Hyperscale
AWS	RDS SQL, RDS PostgreSQL, RDS MySQL, RDS MariaDB, RDS Aurora MySQL, RDS Aurora PostgreSQL, and DynamoDB.
GCP	Cloud SQL for PostgreSQL and Cloud SQL for MySQL

 Table 1-12
 Supported databases by PaaS

Supported platforms

This section details the supported platforms for primary and media servers.

NetBackup server	Supported platform
Primary	RHEL, SUSE, and Windows
Media	RHEL
Storage server	Universal share on underlying MSDP block storage or MSDP-Cloud storage STU

Table 1-13Supported platforms for PaaS

Required cloud provider permissions

The credential that you use to add the cloud providers must have all the required permissions and privileges assigned as mentioned in the *NetBackup Snapshot Manager Installation and Upgrade Guide*.

Supported ports

Here are the supported ports for different PaaS databases.

Database PaaS workload	Supported ports
Azure SQL Server	1433
Azure SQL Managed Instance	1433
Azure MySQL	3306
Azure PostgreSQL	5432
Azure MariaDB	3306
GCP PostgreSQL	5432
GCP MySQL	3306
AWS DynamoDB	NA
AWS RDS PostgreSQL	5432
AWS RDS MySQL	3306
AWS MariaDB	3306
AWS RDS AuroraDB Postgres	5432

Table 1-14Supported ports for PaaS

Database PaaS workload	Supported ports
AWS RDS AuroraDB MySQL	3306
AWS RDS SQL server	1433

 Table 1-14
 Supported ports for PaaS (continued)

Enabling binary logging for MySQL databases

- For AWS, see https://aws.amazon.com/premiumsupport/knowledge-center/rds-mysql-functions/
- For Azure, set the value of the parameter log_bin_trust_function_creators as 1, as described in the link: https://leam.microsoft.com/en-us/azure/mysql/single-server/how-to-server-parameters
- For GCP, do the following:
 - Open the instance and click Edit.
 - Scroll down to Flags section.
 - To set a flag, click **Add item**, select **log_bin_trust_function_creators** flag from the drop-down menu, and set its value to on.
 - Click Save to save your changes. You can confirm your changes under Flags in the Overview page.

Installing the native client utilities

If you use a build-your-own (BYO) setup, you must install the native client utilities in your NetBackup environment for your PaaS workload to work.

For NetBackup deployments in Azure Kubernetes Services (AKS) or Elastic Kubernetes Services (EKS), the native client utilities are packaged as part of NetBackup media server and primary server no manual installation is required for them.

Ensure that the network settings like firewall, security group, and DNS configuration are configured appropriately to access databases within the cloud provider.

Note: If any of these packages are already installed in the media server(s), remove the packages to avoid conflict with the newer versions of the packages that you install.

Installing the MySQL client utility

Note: MySQL client utility recommended version is 8.0.31.

RPM Download https://downloads.mysql.com/archives/community/ location

To install, run the following commands in the terminal:

- 1 rpm -ivh mysql-community-common-<version no>.x86 64.rpm
- 2 rpm -ivh mysql-community-client-plugins- <version_no>.x86_64.rpm
- 3 rpm -ivh mysql-community-libs- <version_no>.x86_64.rpm
- 4 rpm -ivh mysql-community-client- <version_no>.x86_64.rpm

Note: Avoid using MySQL client utility 8.0.32 version as there is bug reported by MySQL.

Installing sqlpackage client utility

Note: sqlpackage client utility recommended version is 19.2(Build: 16.0.6296.0).

Download locations	https://docs.microsoft.com/en-us/sql/tools/ /sqlpackage-download?view=sql-server-ver15
	https://packages.microsoft.com/rhel/7/prod/msodbcsql17-17.10.2.1-1.x86_64.rpm
	https://packages.microsoft.com/rhel/7/ prod/unixODBC-2.3.7-1.rh.x86_64.rpm

To install, run the following commands in the terminal:

6 source ~/.bashrc

Note: Ensure that sqlpackage is added as a default path variable.

- 7 sqlpackage
- 8 rpm -ivh unixODBC-2.3.7-1.rh.x86_64.rpm
- 9 rpm -ivh msodbcsql17-17.10.2.1-1.x86 64.rpm

RHEL 9 users perform the following additional steps:

1 Download the Microsoft.NETCore.App.Runtime.linux-x64 from the link:

https://www.nuget.org/api/v2/package/Microsoft.NETCore.App.Runtime.linux-x64/6.0.10

Locate the file: microsoft.netcore.app.runtime.linux-x64.6.0.10.nupkg.

- **2** Extract the file using a decompression tool like, 7zip.
- 3 Navigate to:

microsoft.netcore.app.runtime.linux-x64.6.0.10.nupkg\runtimes\linux-x64\lib\net6.0\

4 Copy the file System.Security.Cryptography.X509Certificates.dll from there to/sqlpackage folder created in step 2 of installing sqlpackage client utility task.

If you are attaching the 10.1 media server as an external media server with 10.1.1 NetBackup setup, perform the following steps on the 10.1 media server.

For a BYO NetBackup setup:

Run the command:

mkdir -p <backup and restore ushare export path>

- Check the Defaultvers value of NFS in the /etc/nfsmount.conf file.
 - If the Defaultvers value is nfs3, then mount the backup and restore ushare path with the option nolock. For example: mount <ushare mount path> <ushare export path> -o nolock
 - If the Defaultvers is nfs4, mount the backup and restore ushare path without the nolock option.

For NetBackup deployed in AKS and EKS environments:

• Run the command:

mkdir -p <backup and restore ushare export path>

• Check the Defaultvers value of NFS from the /etc/nfsmount.conf file.

- If the Defaultvers value is nfs3, then mount the backup and restore ushare path with the option nolock For example: mount <ushare mount path> <ushare export path> -o nolock
- If the Defaultvers value is nfs4, then mount the v4 version of backup and restore ushare path without the nolock option.

Installing Postgres client utility

Note: Postgres client utility recommended version is 14.6.

Download locations	RHEL 7	https://download.postgresql.org/pub/repos/yum/14/redhat/rhel-7-x86_64/
	RHEL 8	https://download.postgresql.org/pub/repos/yum/14/redhat/rhel-8-x86_64/
	RHEL 9	https://download.postgresql.org/pub/repos/yum/14/redhat/rhel-9-x86_64/

To install, run the following commands in the terminal:

- 1 rpm -ivh postgresql14-libs-14.6-1PGDG.rhel7.x86_64.rpm
- 2 rpm -ivh postgresql14-14.6-1PGDG.rhel7.x86_64.rpm

Note: 1z4 compression package and libicu are required by postgresql14-14.6-1PGDG.rhel8.x86_64.rpm on RHEL 8 and 9.

Configuring the storage server for instant access

Here is the required configuration for your storage server to support instance access.

- **1** Ensure that NFS and NGINX are installed.
- 2 The NGINX version must be the same as the one in the corresponding official RHEL version release. Install it from the corresponding RHEL yum source (EPEL).
- **3** Ensure that the policycoreutils and policycoreutils-python packages are installed from the same RHEL yum source (RHEL server). Run the following commands:
 - semanage port -a -t http_port_t -p tcp 10087
 - setsebool -P httpd_can_network_connect 1

- 4 Ensure that any mount points does not directly mount the /mnt folder on the storage server. Mount the mount points to its subfolders only.
- **5** Enable the logrotate permission in selinux using the following command:

semanage permissive -a logrotate_t

About incremental backup for PaaS workloads

NetBackup supports differential incremental backup for Azure SQL server workload. Incremental backups reduce the backup window significantly in NetBackup. In this method, NetBackup, backs up only the data that has been changed since the subsequent full backup.

Differential incremental backup is only supported for those workloads, where the Change Data Capture feature on the Azure SQL server is enabled.

Guidelines for working with incremental backups for PaaS workloads:

- Assign a longer retention period to full backups than to incremental backups within a policy. A complete restore requires the previous full backup plus all subsequent incremental backups. It may not be possible to restore all the files if the full backup expires before the incremental backups.
- Use one storage for full and incremental backups.
- Do not create long-term copy for incremental backups.
- Do not expire random incremental backup images. Expiring them may cause application inconsistency due to data loss. NetBackup relies on previous full backup and all the subsequent incremental backups.
- While duplicating, ensure that the full and the incremental backup copies are duplicated to the target storage. Any of the previous full or incremental images missing may result in data loss.
- While importing, ensure that the full and all the incremental backup copies are imported together. Any of the previous dependent full or incremental images missing may result in failure.

Limitations and considerations

Consider the following when protecting cloud workloads.

For all databases

 NetBackup deployments in Flex Appliance and Flex Scale do not support PaaS workloads.

- Supports only default the ports for all the databases across providers. Workload
 instances configured with the custom ports are not supported.
- Database names containing the characters '#' and '/' are not supported for backup and restore operations. Also, the database name should adhere to naming conventions suggested by the cloud vendors.
- Backup and restore of a database with multi-byte or non-English characters are not supported for a primary server running Windows and having back-level media server with a version less than 10.1.1.
- You can duplicate the PaaS backup image to a supported storage server. But before you start a restore, you need to duplicate the image, back to an MSDP server with universal share enabled. See "Recovering duplicate images from AdvancedDisk" on page 86.
- With NetBackup 10.2, you can perform backup and restore of supported Azure PaaS databases with Managed Identity based database authentication. This is not supported for Azure Database for MariaDB server. This feature requires at least one media server of version 10.2 or higher.
- For authentication of Azure database, It is recommended to use User Assigned managed identity to work across all media servers. Using a database user created with a system-assigned managed identity, associated with the media server or vm-scale-set (AKS/EKS), does not work with any other media server or media in any other vm-scale set (AKS/EKS).

For PostgreSQL

- Restore of security privileges is not supported.
- During restore you can use <u>-no-owner</u> and <u>-no-privileges</u> option. After restore, the metadata captured at the time of backup, are shown as owner/ACL in the progress log restore activity on web UI.
- Restore does not fail, if the owner/role does not exist on the destination.
- Post restore, the database has the role associated according to the credentials provided in NetBackup against the destination instance.
- Users need to modify the ownership of databases post restore.
- Backup and restore are not supported if the only SSL (Secure Sockets Layer) connection is enforced at the server level for GCP PostgreSQL workload.
- Azure Postgres database restore from single to flexible server or vice versa is not supported because of the cloud provider limitations.
- Following characters are not supported in database name in restore workflow:
 &, (,), <, >, \, |, /, ;, `, ', and ".

Uppercase username is not supported for new users added after PostgreSQL server creation.

For AWS DynamoDB

- Alternates restore for region and account is not supported.
- Restore from imported images from a different primary server is only supported using NetBackup REST API.

For AWS RDS SQL

- Only Express and Web editions for AWS RDS SQL are supported.
- For credential validation, IAM is not supported for AWS RDS SQL. You can use the username and password method.
- Only Amazon RDS data management type is supported. The data management type RDS Custom is not supported for AWS RDS SQL instance editions.

For MySQL

- Restore operation require superuser privileges if the dump file contains CREATE DEFINER statement for backups taken on version lower than 10.2.
- Backup taken on version 10.2 or higher cannot be restored using version lower than 10.2.
- Backup and restore are not supported if the only SSL connection is enforced at the server level for GCP MySQL workload.
- You can restore MySQL database to an alternate instance with another MySQL version than the backup instance, depending on MySQL's version compatibility.

For Azure SQL and SQL Managed Instance

- The Azure VM which is used as a media server, should be in the same Vnet as that of an Azure-managed instance. Alternatively, if the media server and SQL managed instance are in different Vnet, then both the Vnets must be peered to access the database instance.
- Backup fails when Readlock is placed on the database or resource group.
- Backup is partially successful when Deletelock is placed on the database or resource group. The tempdb stale entry does not get deleted from the Azure cloud portal. You need to manually delete it.
- To restore a database on an Azure SQL server or Azure Managed Instance, you must assign AAD admin privilege on the target server, before beginning the restore, to the following, as required:
 - The system or the user-managed identity of the media servers.

 The vm-scale-set in which NetBackup media is deployed (in case of AKS or EKS deployment).

For Azure SQL incremental backup

- You can enable Change Data Capture (CDC) only on databases tiers S3 and above. Sub-core (Basic, S0, S1, S2) Azure SQL Databases are not supported for CDC.
- You may encounter backup or restore issues for databases having encrypted columns in table. As a workaround, Microsoft suggests using Publish/Extract commands to tackle this issue.
- Restore may fail for database having blob data in table.
- To duplicate incremental backups on different storage servers; NetBackup generates different copy numbers for the same recovery point. If you try to restore an incremental copy where no earlier reference of full and other incremental backup is present, the restore fails.
- Note that incremental backup can run only on NetBackup version 10.2 and above media server.
- The user ID used for the cloud service must have permission to enable and disable CDC. Without this permission, you can see errors like: 3842: "Failed to enable CDC" and 3844: "Failed to disable CDC".
- Any attempt to enable CDC fails if a custom schema or user named cdc exists in the database. The term cdc is reserved for system use.
- If you restore to any edition other than Standard or Enterprise, the operation is blocked because CDC requires SQL Server Standard or Enterprise editions. Error message 932 is displayed.
- Avoid backing up databases with BLOB data tables. If a table contains BLOB data, then the backup might be successful, but the restore fails.

Discovering PaaS assets

NetBackup lets you discover, protect, and restore PaaS database assets. You can also discover and restore Azure SQL database and Azure SQL managed database assets backed up by Microsoft Azure. The supported backup modes are Point in time backup and Long-term retention backup.

Note: If you have upgraded the NetBackup Snapshot Manager (previously CloudPoint) from version 10.0 to 10.1. For all users with custom roles, the PaaS assets are marked as deleted in the **PaaS** tab. The assets do not show any recovery-point on them, instead new assets with same name are visible. The old assets get removed from the **PaaS** tab after the subsequent scheduled asset cleanup (default duration is 30 days). As a work-around for this problem, re-assign permissions of all the new asset to the existing RBAC role or create a new custom role. For more information, see *NetBackup WebUI Administrator's Guide*.

Note: If you change the Snapshot Manager cloud plug-in configuration from Azure service principal to Azure managed identity, the status of the previously discovered PaaS assets are displayed deleted. NetBackup Snapshot Manager removes the deleted assets every 24 hours, if you want to perform backup or recovery before the scheduled cleanup, contact Veritas Technical Support.

To discover PaaS assets:

- 1 Add a Snapshot Manager. See "Add a Snapshot Manager" on page 13.
- 2 Add Microsoft Azure, GCP, or AWS as a provider. See "Add a cloud provider for a Snapshot Manager" on page 14.
- **3** Run a discovery. See "Discover assets on Snapshot Manager" on page 18.

After the discovery is complete, you can find all the discovered Azure PostgreSQL, MariaDB, SQL Managed Instance, SQL, MySQL and GCP Cloud SQL for PostgreSQL, Cloud SQL for MySQL, or AWS Dynamo DB assets in the **PaaS** tab, in the **Cloud** workload.

All discovered AWS RDS PostgreSQL, RDS MySQL, RDS MariaDB, RDS SQL, and AuroraDB assets appear in the **Applications** tab. The RDS instances support provider snapshot-based backups as well as NetBackup managed backups.

NetBackup can manage and protect all the assets listed under the **PaaS** tab. Additionally, Azure SQL database and Azure SQL Managed database assets can also be backed up by Microsoft Azure.

Note: When you create and delete a PaaS asset with same name in intervals, and if the PaaS asset is deleted after discovery, web UI shows old data until the next periodic discovery runs.

Viewing PaaS assets

To view PaaS assets:

- 1 On the left, click **Cloud** under **Workloads**.
- 2 In the **PaaS** tab, the assets that are available to you are displayed. The RDS assets are displayed in the **Applications** tab.

You can perform **Add protection**, **Backup now**, **Manage credential** operations in the displayed assets.

For DynamoDB assets the Manage credentials option is not available.

For the deleted assets, you can only manage credentials.

Managing PaaS credentials

You can add credentials for a database listed in the **PaaS** and **Applications** tab under **Cloud** workload. You can add, edit, or delete PaaS credentials from the central **Credential management** console in NetBackup.

View the credential name that is applied to a database

You can view the named credential that is configured for the databases in the **Credential name** column of the **PaaS** tab. If the credentials are not configured for a particular asset, this field is blank.

To view the credentials for PaaS databases:

- 1 On the left, select Workloads > Cloud> PaaS tab.
- 2 Click Show or hide columns above the database list table.
- 3 Select Credential name to display the credential name column.

Add credentials to a database

You can add or modify credentials for a database listed in the PaaS tab.

To add or change credentials

1 On the left, click **Workloads** > **Cloud**.

In the **PaaS** tab, the assets that are available to you are displayed. The RDS assets are displayed in the **Applications** tab.

- 2 Select the database in the table, then click Manage credentials.
- **3** Select a **Validation host**. The validation host must be the RHEL media server which has connectivity to the PaaS workload.

You can add existing credentials or create new credentials for the database:

- To select an exiting credential for the account, select the Select from existing credentials option, select the required credential from the table below, and click Next.
- To add a new credential for the account, select Add credentials, and click Next. Enter a Credential name, Tag, and Description for the new credential. Under Service credentials:
 - Select Role based database authentication (Applicable for supported database service) to use AWS IAM, Azure System Managed and User Managed authentication.
 - Select IAM database authentication (Applicable for Amazon RDS only) for Amazon RDS assets only, and specify a Database user name.

See "Creating an IAM database username" on page 69.

Note: If the Snapshot manager is deployed in-cloud with an attached IAM role having the required permission. You must also deploy the media server in same cloud environment and attach the same IAM role. Otherwise, the backup jobs for the AWS assets fail.

 Select Azure System Managed Identity authentication or Azure User Managed Identity authentication as required. Enter the username of the database, and click Next.
 To perform backup and restore operations utilizing managed identity authentication, you must configure AAD admin to the source and target database servers.

Note: If the snapshot manager deployed in cloud with an attached Managed Identity having the required permissions, attach the same identity to the media server. For AKS and EKS deployments attach the same Managed identity to the VM scale set.

- Select Password authentication and specify the username and the password for the database server. Click Next.
- Add a role that you want to have access to the credential. To add new permissions to a role:
 - Click Add.
 - Select a role.

- Select the credential permissions that you want the role to have.
- Click Save.
- 4 Click **Next** to finish creating the credential.

For more information about credentials and how to edit or delete a credential, see *NetBackup Web UI Administrator's Guide.*

Creating an IAM database username

To create an IAM username:

- 1 Enable IAM DB authentication on the RDS DB instance.
- 2 Create Database user using master login (rds_iam
 - For MySQL create the username using master login (rds_iam):
 - mysql --protocol=tcp --host=instance_fqdn --user=admin -p --port=3306
 - CREATE USER iamuser IDENTIFIED WITH AWSAuthenticationPlugin as 'RDS';
 - GRANT SELECT, INSERT, UPDATE, DELETE, CREATE, DROP, RELOAD, PROCESS, REFERENCES, INDEX, ALTER, SHOW DATABASES, LOCK TABLES, CREATE VIEW, SHOW VIEW, CREATE ROUTINE, ALTER ROUTINE, EVENT, TRIGGER ON *.* TO `iamuser`@'%' WITH GRANT OPTION;
 - For PostgreSQL create the user under server.
 - psql -h instance_fqdn -U postgres
 - CREATE USER iamuser WITH LOGIN;
 - GRANT rds_iam TO iamuser;
 - ALTER ROLE iamuser WITH LOGIN CREATEDB;
 - GRANT postgres TO iamuser;
- 3 Attach the RDS policy to the IAM role attached to the NetBackup media server.

Creating a system or user managed identity username

For Azure SQL Server and Managed Instance

Do any of the following configurations:

Configure managed identity user as AAD admin:

Set AAD admin on the SQL server or the Managed instance.

 Go to Settings > Azure Active Directory > Set admin. Search and set system-assigned or user-assigned managed identity, and save.

Note: Only those media servers configured as system-assigned managed identity as AAD admin can perform backup and restore.

Create managed identity user on the database using SSMS client:

- To set AAD admin for SQL server to create user, go to Settings > Active Directory admin > Set admin. Pick active directory the user, and save.
- Login to the SQL database or Managed database to create user under that database.

CREATE USER [<managed_identity>] FROM EXTERNAL PROVIDER; ALTER ROLE db_owner ADD MEMBER [<managed_identity>];

- Provide login permission for that user on the SQL Server, run
 - # CREATE USER [<managed_identity>] FROM EXTERNAL PROVIDER;
 - # ALTER ROLE loginmanager ADD MEMBER [<managed identity>];

Note: You must create users for all media servers communicating with the database using the system-assigned managed identity.

Note: To restore database, you must configure the managed identity user as AAD admin on the target server.

For MySQL

- To configure the AAD admin for MySQL server to create user, go to Settings > Active Directory admin > Set admin. Pick the active directory user, and save.
- Get the client ID for managed identity using Azure CLI, run

```
# az ad sp list --display-name <managed_identity> --query [*].appId
--out tsv
```

Generate access token to login, using Azure CLI, run:

```
# az account get-access-token --resource-type oss-rdbms
```

Login using the AAD admin user and access token, run:

```
# mysql -h <server name> --user <user name>
--enable-cleartext-plugin --password=<token>
```

Create the manage identity user and grant the permissions, run:

```
# SET aad_auth_validate_oids_in_tenant = OFF;
    # CREATE AADUSER '<db_user>' IDENTIFIED BY
'<Generated_client_id>';
    # GRANT USAGE, DROP, SELECT, CREATE, SHOW VIEW, EVENT, LOCK
TABLES , ALTER, CREATE VIEW, INSERT, REFERENCES, ALTER ROUTINE,
PROCESS ON *.* TO '<db_user>'@'%'
```

For PostgreSQL

- To configure the AAD admin for PostgreSQL server to create user, go to Settings
 Active Directory admin > Set admin. Pick the active directory user, and save.
- Get client ID for the managed identity:

```
# az ad sp list --display-name <managed_identity> --query
[*].appId --out tsv
```

Generate the access token required to login, run:

az account get-access-token --resource-type oss-rdbms

Export the password for the generated token, run:

export PGPASSWORD=<token>

Login using the AAD admin user and the access token, run:

```
# psql "host=<host name> port=5432 dbname=<dbname> user=<user
name> sslmode=require"
```

- Create user and grant permission, run:
 - # SET aad auth validate oids in tenant = OFF;
 - # CREATE ROLE <db user> WITH LOGIN PASSWORD '<client id>' IN ROLE azure
 - # GRANT azure pg admin TO <db user>;
 - # ALTER USER smipguser CREATEDB;
 - # ALTER USER smipguser Replication;

Note: Only user managed identity is supported for MySQL Flexible Server. Managed Identity support is not available for PostgreSQL Flexible Server.

Add protection to PaaS assets

After you discover the PaaS assets, you can add protection to them in the **Applications** or **PaaS** tab in **Cloud** workload.

To add protection to PaaS assets

- 1 On the left, click **Workloads > Cloud**.
- 2 To protect AWS RDS supported database assets, click the **Applications** tab. For other PaaS assets, click the **PaaS** tab.
- 3 Check if the asset that you want to protect has a credential.

See "View the credential name that is applied to a database" on page 67..

If the **Credential name** column is empty, you need to assign a credential to the asset.

See "Add credentials to a database " on page 67.

4 To add protection to an asset, select the asset and click Add protection.

An asset must have assigned credentials to be eligible for most operations. For example, if you want to assign the asset to a protection plan or perform backup now.

- 5 Select a protection plan and click Next.
- 6 Review the configuration settings and click **Protect**.

Perform backup now

Using this option you can create a one-time backup of the selected asset. This backup does not affect any future, or scheduled backups.
To perform backup now

1 On the left, click **Workloads** > **Cloud**.

To backup AWS RDS supported database assets, click the **Applications** tab. For other PaaS assets, click the **PaaS** tab.

Note: You can see and protect the user-created databases. The system databases are not shown and protected, as these databases need the cloud provider's superuser privilege to perform backup and restore.

- 2 Select the asset, then click Add protection.
- **3** Select the required protection plan, then click **Start backup**.

You can view the status of the backup job in the Activity monitor.

The database agents access the database from within the media server (container, in case of NetBackup deployed in AKS and EKS environments), and perform NFS mount of the Universal share path on the media server (backup host).

Note: For incremental backup of Azure SQL databases, NetBackup performs a full backup even if the asset is protected by a protection plan with backup type a differential incremental.

Chapter

Recovering cloud assets

This chapter includes the following topics:

- Recovering cloud assets
- Perform rollback recovery of cloud assets
- Recovering PaaS assets

Recovering cloud assets

You can restore AWS, Azure, Azure Stack and GCP VM assets from snapshot copy, replica copy, backup copy, or duplicate copy.

While restoring VMs, NetBackup gives you the option to change certain parameters of the original backup or snapshot copy. Including options like changing the VM display name, changing power options of the VM, removing tag associations during restore, and restoring to an alternate network. You can also restore VMs to an alternate configuration, to a different zone, to a different subscription, and restore VMs or disks to a different resource group.

- For GCP: Select Firewall rule
- For Azure: Select Network security group
- For AWS: Select Security group

About the pre-recovery check for VMs

Pre-recovery check indicates how a restore may fail, before the restore is initiated. The pre-recovery check verifies the following:

- Usage of supported characters and the length in the display name.
- Existence of destination network
- Existence of selected Resource group for VMs and disks

- Existence of source VM snapshot (applicable for restore from snapshot)
- Existence of the staging location added in the file /cloudpoint/azurestack.conf (applicable for restore from backup for Azure stack)
- Existence of a VM with the same display name.
- Connectivity with the Snapshot Manager and cloud credential validation.

Supported parameters for restoring cloud assets

The following table summarizes the different parameters that you can change while restoring assets for different cloud providers.

Table 2-1	Supported parameters for Azure, Azure Stack, GCP, and AWS
	snapshot and backup copies

Parameters	Snapshot copy		ру	Backup copy		
	Azure	Azure Stack	GCP and AWS	Azure	Azure Stack	GCP and AWS
Change VM display name	Y	Y	Y	Y	Y	Y
Change power state of the VM	Y	Y	Y	Y	Y	Y
Remove tag associations	Y	Y	Y	Y	Y	Y
Restore to a different network	Y	Y	Y	Y	Y	Y
Subscription ID				Y	Y	Y
Change resource group	Y	Y		Y	Y	
Change region of the VM				Y	Y	Y
Change provider configuration				Y	Y	

 Table 2-1
 Supported parameters for Azure, Azure Stack, GCP, and AWS snapshot and backup copies (continued)

Change resource group for disks	Y	Y		Y	Y	
Zone	Y		Y	Y		Y
Security group/Firewall rule/Network security group	Y	Y	Y	Y	Y	Y

Recovering virtual machines

To recover a VM

- 1 On the left, click **Cloud**.
- 2 Click the Virtual Machines tab.

All the discovered cloud assets for the respective category are displayed.

- **3** Double-click the protected asset that you want recover.
- 4 Click the **Recovery points** tab.

The available images are listed in rows with the backup timestamp for each image. For AWS workloads you can see replica as well as backup images, if available.

5 In the Copies column, click the copy that you want to recover. You can see the backup, snapshot, and replica copy, if available. Click Recover. If you don't select a copy to restore, the primary copy is selected.

6 Click Restore Virtual Machine.

7 In the Recovery target page, do the following:

If you restore a backup copy, modify the values of these parameters as required:

- Configuration: To restore to an alternate configuration, select one from the drop-down.
- **Region**: To restore to an alternate region, select one from the drop-down.
- **Subscription**: To restore to an alternate subscription, select one from the drop-down. For Azure and Azure Stack only.

- Resource group: To restore to an alternate resource group, click the search icon, in the Select resource group dialog, select the required resource group. For Azure and Azure Stack only.
- Display name: To change the display name, enter the new one in the field. The specified display name is validated during the pre-recovery check.

Note: Except in AWS workloads, the following special characters are not allowed in the display name: ` ~ ! @ # \$ % ^ & * () = + _ [] { } \\ | ; : ' \" , < > / ?."

If you restore a snapshot copy, specify only the **Resource group** and the **Display name**.

- 8 Click Next.
- **9** In the Recovery options page:
 - If you restore a backup copy, to restore to a different zone, select a Zone. To select a network available in that zone, click the search icon near Network configuration, and select a target network for recovery. User can also select Security group / Network security group / Firewall rule for AWS, Azure, and GCP cloud providers respectively.
 - (Only for GCP) If you restore a snapshot copy, to restore to a different region, select a **Region**. To select a network available in that zone, click the search icon in **Network configuration**, and select a target network for recovery. The list shows networks available in that zone.
 - If you restore a snapshot copy, to restore to a different zone, select a Zone. To select a network available in that zone, click the search icon in Network configuration, and select a target network for recovery. The list shows networks available in that zone.

User can also select **Security group / Network security group / Firewall rule** for AWS, Azure, and GCP cloud providers respectively.

In the Advanced section:

- To keep the VM powered on after recovery, select **Power on after recovery**.
- To remove the tags associated with the asset at the time of backup or creating snapshot, select **Remove tag associations**.

Note: If you do not select the **Remove tag associations** option, any tag value for assets should not have spaces, before and after a comma. After the restoration of an asset, the spaces before and after any comma in the tag values are removed. For example, the value for the tag name:**created_on**: *Fri*, 02-Apr-2021 07:54:59 PM, EDT, is converted to: *Fri*,02-Apr-2021 07:54:59 PM,EDT. You can manually edit the tag values to reinstate the spaces.

Note: Selection of **None** for zone means VM will not be placed in any zone and selection of **None** for **Network security group/Security group/Firewall rule** means that no security rules are applied to the restored VM.

- **10** Click **Next**. The pre-recovery check begins. This stage validates all the recovery parameters and displays errors, if any. You can fix the errors before starting the recovery.
- 11 Click Start recovery.

The Restore activity tab shows the job progress.

For information on the recovery status codes, see the NetBackup administrator or the *NetBackup Status Codes Reference Guide*, available here:

http://www.veritas.com/docs/000003214

Recovering applications and volumes to its original location

For GCP, when you restore a snapshot that was created before the upgrade, if the source disk is not present, a default restored disk, pd-standard is created.

To recover applications and volumes to the original location

- 1 On the left, click **Cloud**.
- 2 Click the Applications or Volumes tab.

All the discovered cloud assets for the respective category are displayed.

- **3** Double-click on the protected asset that you want recover.
- 4 Click the **Recovery points** tab. In the calendar view, click the date on which the backup occurred.

The available images are listed in rows with the backup timestamp for each image.

5 On the top right for the preferred recovery point, select **Original location**.

- 6 Click Start recovery.
- 7 On the left, click **Activity monitor** to view the job status.

Recovering applications and volumes to an alternate location

Considerations

 For encrypted VM restore in AWS to an alternate location, the key-pair names must be same on the source and destination region. If not, create a new key-pair in the destination region that is consistent with the key-pair in the source region.

To recover applications and volumes to alternate location

- 1 On the left, click **Cloud**.
- 2 Click the Applications or Volumes tab.

All the discovered cloud assets for the respective category are displayed.

- **3** Double-click on the protected asset that you want recover.
- 4 Click the **Recovery points** tab. In the calendar view, click the date on which the backup occurred.

The available images are listed in rows with the backup timestamp for each image.

- 5 On the top right for the preferred recovery point, select **Alternate location**.
- 6 Select the location where you want to restore the cloud asset.
- 7 Click Start recovery.
- 8 On the left, click **Activity monitor** to view the job status.

Recovery scenarios for GCP VMs with read-only volumes

The following table describes how NetBackup handles the restore/recovery of GCP VMs that have read-only volumes.

 Table 2-2
 Recovery scenarios for read-only GCP VMs

Scenario	Handling
Restoring a volume from the snapshot of an attached read-only disk, from the Volumes tab under Cloud workload.	During restore, the disk is attached in the read/write mode to the original or alternate location.

Scenario	Handling
Restoring a VM, with a read-only disk, from a crash-consistent snapshot, from the Virtual machines tab under Cloud workloads.	During restore of such a VM to its original or alternate location, a read-only disk is restored in a read/write mode.
Restoring a VM with a read-only disk, from an app-consistent	You can attach a read-only disk to multiple VMs, but NetBackup discovers it under only one VM.
snapshot, from the Virtual machine tab under Cloud workload.	For a Windows VM, the snapshot fails with a VSS error, similar to the following:
	Failure: flexsnap.GenericError: Failed to take snapshot (error: Failed to create VSS snapshot of the selected volumes.)"
	For a Linux VM, the snapshot may or may not be successful for the VM under which the disk is discovered, but fails for the rest of the VMs due to the missing dependencies. Error example:
	linear_flow.Flow: create snapshot (test-win) of host linux-1(len=4)' requires ['snap_google- gcepd-us-west 2-b-7534340043 132122994'] but no other entity produces said requirements\n MissingDependencies
	In the above case, if a snapshot is successful for a Linux VM, a read-only disk is restored in a read/write mode.

 Table 2-2
 Recovery scenarios for read-only GCP VMs (continued)

Perform rollback recovery of cloud assets

The rollback recovery of a cloud asset overwrites the existing data on the original asset. Unlike virtual machine restore, rollback restore does not create a new copy of the restored image, but replaces the existing data on the source.

Note: Snapshot replicas do not support rollback. Also, Azure Stack and GCP workloads does not support rollback restore.

To perform rollback recovery of the cloud asset

- 1 On the left, click **Cloud**.
- 2 Click the Virtual Machines.

All the discovered cloud assets for the respective category are displayed.

- **3** Double-click on the protected asset you want to recover.
- 4 Click the **Recovery points** tab. The available images are listed in rows with the backup timestamp for each image. In the **Copies** column, click the snapshot that you want to recover. Click **Recover> Rollback restore**.
- 5 Click Start recovery. The existing data is overwritten.
- 6 On the left, click **Activity monitor > Jobs** to view the job status.

Recovering PaaS assets

PaaS assets are listed under the **Cloud** workload. You can restore AWS RDS PostgreSQL, RDS MySQL, RDS MariaDB, RDS AuroraDB, and RDS SQL Server assets from the **Applications** tab, and all other PaaS assets, from the **PaaS** tab. Recovery flows for Azure assets are different based on whether they are NetBackup protected or Azure protected.

From NetBackup 10.2, you can separately restore the data/schema and metadata for MySQL database. You need superuser privileges for metadata restore and at least one media server with a version 10.2 or later.

Note: For MySQL restore, if you do not have admin or root user privileges, then you must have view permission, along with the restore permissions.

Before performing Instant access recovery ensure to add the key: MEDIA_SERVER_POD_CIDR in the bp.conf file of the primary server. For NetBackup deployed in AKS or EKS environment, set its value to the subnets of the media server pod, as comma-separated values. For example: MEDIA_SERVER_POD_CIDR=10.0.0.0/8, 10.0.0.0/16

Recovering non-RDS PaaS assets

You can restore the non-RDS PaaS assets from the **PaaS** tab, under Cloud workload.

To restore non-RDS PaaS assets:

- 1 On the left, click **Cloud**, under **Workloads**, and click the **PaaS** tab. Click the name of the asset that you want to recover.
- 2 Click the **Recovery points** tab, for Azure assets, additionally select **NetBackup** managed.

The available recovery points are displayed in the table.

- 3 Click **Recover** in the row of the image that you want to recover.
- 4 In the **Name** field, the original name of the asset appears by default. You can change the name in the field. You may not be able to change this name later.
- 5 (Optional) In the Target instance field, the source instance of the asset is selected by default. To restore to an alternate instance, select the required instance. Target instance is not available for DynamoDB assets.
- 6 (Optional, for MySQL databases only.) Select **Restore metadata** to restore metadata such as views, triggers, store procedures, and so on.
- 7 (Optional, for MySQL databases only.) For the target instance credentials for restore:
 - Select Use already associated credentials to use the credentials that are already associated with the instance, and click Start recovery.
 - Select Use different credentials to use a different set of credentials, either existing credentials or create a new one.

See "Add credentials to a database " on page 67.

The validation host for validating these credentials must be the same as the one used during backup. If the host used during backup is not available during credential validation during restore, then validation fails.

(Optional) Select **Make default credentials** to set these credentials as default credentials for the asset.

8 Click Start recovery.

The **Restore activity** tab shows you the status.

Recovering RDS-based PaaS asset

You can restore the RDS-based PaaS assets from the **Applications** tab, under the **Cloud** workload.

To restore RDS-based PaaS assets:

- 1 On the left, click **Cloud**, under **Workloads**, and click the **Applications** tab. Click the name of the asset that you want to recover.
- 2 Click the **Recovery points** tab, in the calendar, select the date for which you want to see the recovery points.

The available recovery points are displayed on the right.

- 3 Click **Recover** in the row of the image that you want to recover.
- 4 Under Source databases, select the databases that you want to restore. Click Add database, in the Add database dialog, select the required databases, and click Select.
- **5** Enter a prefix to add to the restored databases, or use the default. This field must have a value.
- **6** (Optional) In the **Target instance** field, the source instance of the asset is selected by default. To restore to an alternate instance, select the required instance.
- 7 (Optional, for MySQL databases only.) Select **Restore metadata** to restore metadata such as views, triggers, store procedures, and so on.
- 8 (Optional, for MySQL databases only.) For the target instance credentials for restore:
 - Select Use already associated credentials to use the credentials that are already associated with the instance, and click Start recovery.
 - Select Use different credentials to use a different set of credentials, either existing credentials or create a new one.
 See "Add credentials to a database " on page 67.
 (Optional) Select Make default credentials to set these credentials as default credentials for the asset.
 - Select a validation host to validate the provided credentials.

9 Click Start recovery.

The **Restore activity** tab shows you the status.

These two restore workflows implicitly create an instant access mount share against the recovery point.

Recovering Azure protected assets

NetBackup lets you restore Azure SQL database and Azure SQL managed database assets that are backed up by Microsoft Azure. The supported backup modes are Point in time backup and Long-term retention backup.

Note: Restoration in Elastic pool in Instance pool is not supported.

Before proceeding make sure that you have the required permissions to restore PaaS assets.

To recover point in time backup assets:

- 1 On the left, click **Cloud**.
- 2 Click the PaaS tab.

All the discovered PaaS assets are displayed.

- 3 Under Recovery points type, select Provider protected.
- 4 Click **Restore** in the row of the protected Azure SQL database and Azure SQL managed database asset that you want to recover.
- 5 In the Recovery points tab, under Point in time backup, click Restore.
- 6 Select a date and time under **Restore point (UTC)**. You can select any restore point, between the earliest restore point, and the:
 - Latest backup time for online databases.
 - Database deletion time for deleted databases.

Microsoft Azure may round off the selected time to the nearest available recovery point, using UTC time.

The default restore date and time displayed in web UI may differ based on the selected PaaS asset. For example, for Azure SQL databases, the default restore time is the current time, and for Azure SQL managed database, the default restore time is 6 minutes earlier than the current time.

7 Optionally, for Azure SQL databases, enter a name for the restored database in the Database name field. Database names cannot have special characters like < > * % & : \ / and ? or control characters. Do not end the name with a period or space. For more information about Azure resource naming rules, see https://docs.microsoft.com/en-us/azure/azure-resource-manager /management/resource-name-rules#microsoftsql

If you do not enter a name, NetBackup automatically assigns a name in the <*dbName>_*<*Restored time in UTC>* format.

8 Optionally, for Azure SQL managed databases, enter the instance name in the **Managed instance** field. By default, the instance name of the recovery point is displayed. You can also search for the managed instance name using the search option. You can restore to the same region to which your subscription belongs.

If you cannot see the desired managed instance in the search results, perform a manual discovery. Also, ensure that you have RBAC access to the managed instance.

9 Click Next. Once the Pre-recovery check is complete, click Start recovery.

You can check the status of the job in the activity monitor.

To recover long-term retention backup assets:

- 1 On the left, click **Cloud**.
- 2 Click the PaaS tab.

All the discovered PaaS assets are displayed.

- 3 Click **Restore** in the row of the protected asset that you want recover.
- 4 In the **Recovery points** tab, under **Long term retention backup**, click **Restore** against the image that you want to restore.
- 5 Optionally, for Azure SQL databases, enter a name for the restored database in the Database name field. Database names cannot have special characters like <> * %& :\/ and ? or control characters. Do not end the name with a period or space. For more information about Azure resource naming rules, see https://docs.microsoft.com/en-us/azure/azure-resource-manager /management/resource-name-rules#microsoftsql

If you do not enter a name, NetBackup automatically assigns a name in the *restore_<dbName>* format.

- 6 Optionally, for Azure SQL managed databases, enter the instance name in the **Managed instance** field. By default, the instance name of the recovery point is displayed. You can also search for the managed instance name using the search option. You can restore to the same region to which your subscription belongs.
- 7 Click Next. Once the Pre-recovery check is complete, click Start recovery.

You can check the status of the job in the activity monitor.

Note: Tags from portal as well as Snapshot Manager are not restored. However, the "createdby: cloudpoint" tag is created while restoring through NetBackup.

Note: For provider protected recovery jobs, any intermittent failures keep the recovery job running until the next schedule job cleanup runs.

Recovering duplicate images from AdvancedDisk

A 10.1 media server cannot initiate PaaS restores from a duplicated image, if the image resides on an AdvancedDisk storage or an MSDP cloud storage. As a workaround, you can perform the following steps:

Pre-requisite:

- 1. For AdvancedDisk the media server version associated with the MSDP server must be 10.1 or above.
- 2. For MSDP cloud storage, media server version used for recovery must be 10.1.1.
- 3. Ensure that ushare is set up and configured on the MSDP server.
- 4. Create a universal share on this MSDP storage server. Ensure that you add the corresponding media server hostname/IP in the export list of ushare.

To recover from AdvancedDisk, do the following:

1 Using the Catalog in web UI, manually duplicate the image to an MSDP storage. See *NetBackup WebUI Administrator's Guide* for details.

Note: To duplicate from a second copy, click search again after selecting duplicate option in catalog view.

2 Once the duplication job completes, ensure that the new recovery point is visible for the given asset in web UI.

To start a restore job, See "Recovering PaaS assets" on page 81.

To restore using REST API, see section:

```
recovery/workloads/cloud/scenarios/asset/recover. Refer to NetBackup API
documentation.
```

Note: For RDS instance recovery, NetBackup does not display any error or warning messages, if you initiate the restore from a backup image residing on AdvancedDisk storage.

Chapter

Performing granular restore

This chapter includes the following topics:

- About granular restore
- Supported environment list
- List of supported file systems
- Before you begin
- Limitations and considerations
- Restoring files and folders from cloud virtual machines
- Restoring volumes on cloud virtual machines
- Troubleshooting

About granular restore

NetBackup enables you to perform a granular restore of files and folders on cloud virtual machines. You can create snapshots, backup of snapshot and restore, at the same time you can also locate and restore individual files and folders. You can also restore volumes from virtual machines.

This process is known as granular restore in which each single file in the snapshot or backup is considered as a granule or more commonly referred to as single file restore. NetBackup makes an inventory of all the files within a snapshot or backup using an indexing process. You can restore specific files from a snapshot only if that snapshot has been indexed by NetBackup. You can also restore specific files from a backup only if that backup has been indexed by NetBackup. The following table helps you understand the flow of enabling granular restore of volumes, files, and folders:

Description
Connect the virtual machines that you want to use to perform granular restore.
Use the Discover option. Navigate to Cloud > Snapshot Managers > <i>Snapshot Manager</i> > Actions > Discover.
Create a protection plan. Ensure that the Enable granular recovery for files or folders check box is selected in the Backup options of the protection plan.
Add the assets on the VMs connected in the previous step to the protection plan that has the indexable attribute enabled granular restore.
Schedule backup job and indexing or use the Backup now option. The backup job starts immediately.
Perform granular restore of a file, folder, or volume.

Table 3-1Granular restore tasks

Supported environment list

The following table lists the supported versions.

Table 3-2 Supported versi

Application	Version
NetBackup	10.2
NetBackup backup host OS	RHEL 7.x and 8.x

Application	Version
Snapshot Manager host OS	 RHEL 7.x and later, RHEL 8.6 Ubuntu 18.04 LTS and 20.04 LTS Note: The version of the OS (Ubuntu 20.04 LTS) listed on the UI is the version of the container.
Cloud providers	 Amazon Web Services Microsoft Azure Microsoft Azure Stack Hub Google Cloud Platform
Snapshot Manager or agent instance type	 Amazon AWS: t2.large/t3.large Microsoft Azure: D2s_V3Standard Microsoft Azure Stack Hub: DS2_v2 Standard, DS3_v2 Standard Google Cloud Platform: n1.Standard2 and larger
Snapshot Manager agent host to be protected	 Linux OS: RHEL 7.x and RHEL 8.2, 8.4 and 8.5 Windows OS Version: 2012 R2, 2016, 2019 and 2022

Table 3-2 Supported versions (continued)

List of supported file systems

The following table provides details about supported files systems.

 ext4 xfs

Platform

RHEL (With consistent

snapshot property)

Note: For Google cloud platform, if agent host is on operating system version RHEL 8.x, then Snapshot Manager must be installed on host having operating system version RHEL 8.x.

- ext3
- GPT
- MBR
- No layout (direct FS)

Discovered file system Partition layouts

Platform	Discovered file system	Partition layouts
Windows (With consistent snapshot property)	NTFS	GPTMBR

Note: Application consistent snapshot is not supported for ext2 file system version.

Note: GRT is allowed irrespective of destination file-system/partition type (FAT, ReFS, LDM or LVM).

Before you begin

Ensure the following points are addressed before you perform granular restore. Configured Snapshot Manager and VM to be protected with granular restore enabled have the following requirements:

- (Applicable only for snapshots)
 - (Microsoft Azure and Azure Stack Hub) Even if Snapshot Manager is not deployed in the same subscription and region as the connected VM, but if a backup schedule is configured as part of the protection plan, then granular restore can be performed. For snapshot-only protection plan schedule, for both Azure and Azure Stack Hub, you need to deploy the Snapshot Manager host in the same subscription and region as the VMs.
 - Amazon AWS: The Snapshot Manager host and the connected VM must be in the same account and region.
 - Google Cloud Platform: The Snapshot Manager host and the connected VM must be in the same project.
 - The cloud plug-in must be configured to protect the assets in the region in which the Snapshot Manager host is deployed.
 - If you want to restore volume to the same virtual machine and location, you
 must detach existing volume and free the slot and then try to restore.
- The host must be in a connected state and must have required supported configuration.
- The host must have the fsConsistent and indexable flags enabled when connected. The indexable flag is applicable for a snapshot-only protection plan schedule.
- Protection plan must have the Enable Granular restore for files and folders check box enabled.

- Apart from the boot disk and disk that is mounted on "/cloudpoint", no extra disk should be attached to Snapshot Manager instance explicitly.
- File systems on the host must be supported.
 See "List of supported file systems" on page 89.
- Configure port 5671 and 443 for open Snapshot Manager host.
- For agentless restore, in Linux systems, configure the port 22 on the indexable virtual machines. For Windows platform, configure the ports 135, 445 and the dynamic/fixed WMI-IN port on the indexable virtual machines.
- Ensure that the following points are addressed before you perform the single file restore from backup of snapshot:
 - Supported NetBackup and Snapshot Manager version 10.2 onwards.
 - Granular restore will work only if backup image is restored from MSDP storage server (version must be 10.2 onwards) with instant access enabled.
 - Target host agent must be upgraded to the latest version.
 - On Windows target host, administrator must have attach and detach policy enabled for disks. For more information, refer to AttachVirtualDisk function.
 - (For Windows) To restore symlink, agent must be configured using the required access.
 - Backup must be taken with Granular File and Restore option selected.
 - Target virtual machine must have access to MSDP storage server over the access to NFS/SMB.
 - Windows target must have the following:
 - (For restoring window image content with Restoring Access Control list) Samba user credentials must be stored in windows credential manager for a MSDP storage server (which is exporting the Instant access share): On MSDP server, run the smbpasswd -a <username> command to generate the Samba credentials.

Add DNS name or IP of MSDP server, with above username and generated password to windows credential manager.

The smbpasswd command will fail if user is not present on MSDP server. Hence first add user using the useradd <username> command and then use the smbpasswd command.

■ (For restoring Linux image content) NFS client must be installed. For more information on how to enable SMB/IA on MSDP, refer to the *NetBackup*[™] *Deduplication Guide*. Verify the SMB configuration on MSDP server with the

/usr/openv/pdde/vpfs/bin/ia_byo_precheck.sh precheck script.

Limitations and considerations

Consider the following important points for granular restore.

- After a restore job is completed, you cannot expand the directories in the File List section of the restore job.
- If adequate space is not available on the target location, the restore operation fails before the copy operation begins.
- In the activity monitor summary, when the restore job starts it shows the current file which is the first entry in the restore items. After the job is complete, the summary goes blank.
- Bytes transferred and estimated bytes in activity monitor are not updated and shown as 0.
- The ephemeral storage devices are ignored when a snapshot is performed. (For example, Amazon AWS instance store volumes and Microsoft Azure temporary disks.) These devices are also ignored for indexing as well.
- The file systems that are created on LDM disks are ignored when host consistent snapshots are created and indexed.
- Until old agent (pre-installed) service is not restarted, alternate host restore (GRT and application) of LVM asset might fail. To support the recovery of LVM assets, you need to restart the older agents.
- Granular restore (GRT) or single file restore (SFR) can be performed with the help of VxMS indexing. VxMS indexing is applicable for all Snapshot Manager supported file systems. VxMS indexing can be performed for Azure, Azure Stack, AWS cloud and GCP is performed on an existing mount-based indexing.
- Host consistent snapshot is supported for EXT2 file system only if it is mounted as read-only.
- If any unsupported file systems are present on the host, the host can be added to the protection plan that is created for granular restore. The protection plans for granular restore have the Enable granular recovery for files or folders check box value set to true.
- Snapshot Manager communicates the number of index jobs that can be run to NetBackup. NetBackup then throttles the requests. By default, the number of index jobs is initialized to 2. Post discovery of Snapshot Manager host capabilities, it is increased to number of disk slots available. However, you can

update the value for indexing max_jobs=<value> in flexsnap.conf file to override this limit.

- Snapshot Manager host limits the number of disk slots that the cloud providers enforce. NetBackup throttles the indexing requests to Snapshot Manager. To achieve this request, during Cloud Asset discovery process, NetBackup fetches Snapshot Manager host capabilities. These capabilities include the Max no of index jobs parameter. This parameter is used to limit the requests that are sent to Snapshot Manager and index job queue in NetBackup. By default, the maximum number of parallel indexing jobs is 2. But once the cloud plug-in is configured which discovers the Snapshot Manager host, the capability API fetches the number of max jobs based on attachment points and available resources. You can set the limit by adding the indexing max_jobs=x entry in the config file of the Snapshot Manager host. If the Snapshot Manager host receives number of indexing requests more than its capability, the requests are queued.
- During indexing, OS errors can occur while crawling files, directories, or other entries. These errors are ignored and the indexing operation continues. To restore the missing files, you must initiate the granular restore operations on the parent folder.
- When you create or mount a disk from the Windows VM, add the drive letter. This action ensures that the indexing operation can capture the correct drive letter.
- In some cases a mount point is not visible when you browse for add files or folders in the recovery point. Consider the following reasons:
 - The "/" (root file system) is on an LVM, and
 - The mount point is not directly related to "/" (root file system).

In this scenario, search for the mount point from the right panel and then restore the files or folders successfully.

For example, if a disk is mounted on /mnt1/mnt2 where /mnt1 is any directory on the "/" (root FS which is on LVM setup) and mnt2 is a mount point inside mnt1, the "mnt2" is not visible in the tree on the left panel. However, you can search and restore files or folders inside mount point.

- To restore files and folders from VM snapshot recovery points, the /etc/fstab file on the Linux servers, must have entries based on the file system UUID, instead of device paths. The device paths can change depending on the order in which Linux discovers the devices during system boot.
- While restoring application or file systems from one OS version to another OS version, refer to the OS and application vendor's compatibility matrix. Restore of file system from higher version to lower version is not recommended.

- A user group cannot restore a drive as source to an alternate folder as the destination. A user group does not have the writer permission to create a new folder.
- The agentless connection cannot restore the encrypted file by Windows (or EFS) through Granular File Level Restore (Restore files and folder option).
 However you can restore the file through volume level restore and then decrypt the file.
- Files stored on volume mounted on folder (junction point) can be restored only if underlying disk has GPT partition layout. If volume is mounted using drive letter, then files can be restored irrespective of partition layout of the underlying disk.
- Consider the following limitations for single file restore from backup of snapshot:
 - If restoring files/folders when source host is Linux and target host is Windows, then
 - File attributes cannot be restored on windows host and only the content of the file is restored.
 - If there is any symlink in selected files/folders for restoration, then the symlink will not be restored.
 - In case of Original Location Restore, available size check before copy is skipped.
 - If restoring files/folders when source host is Linux and target host is Linux, then socket and block files would not be restored.
 - Restoration of files and folders is not supported when they reside on LDM disks/dynamic disks/storage spaces.
 - Live mount retained during partial restore success would be removed/expired before retention period expiry, if media server or PureDisk Deduplication Engine and Veritas Provisioning file system daemon service restarts.
 - If Media servers are not upgraded to 10.2, then master server on 10.2 will be used to connect to NetBackup Snapshot Manager.
 - Junction point on windows after indexing is seen as format like Volume {4e3f8396-490a-400a-8abf-5579cafd4c0f} in Add files. If junction point is selected in Add files for single file restore from backup operation then select Restore everything to a different location and enable the Require to restore access control list in Advanced option.

Restoring files and folders from cloud virtual machines

You can restore a single file or folder from a cloud virtual machine.

Note: For Microsoft Azure, Google Cloud Platform, and Amazon AWS NetBackup supports snapshot and recovery of cloud assets that are encrypted using the keys that the manager provides.

To restore a file or folder

- 1 On the left, click **Cloud**.
- 2 Click on the Virtual machines tab.
- **3** Select the virtual machine where the application is hosted. On the top right, click **Connect**.
- 4 After the VM is connected, on the top right, click Add protection.
- 5 Select a protection plan that is created for granular recovery of files and folders and click Next.
- 6 Click Protect.
- 7 To execute the protection plan, click **Backup now**.
- 8 After a snapshot and the two indexing job or two backup from snapshot job for the assets are complete, click the **Recovery points** tab.
- **9** For the preferred recovery point, select **Restore files and folders** from the Action menu.

You can also restore files and folders for **Snapshot** and **Backup** type of copies by clicking on **Recover** and then selecting **Restore files and folders** for specific type of copy.

- **10** In the Add file step, click **Add**.
- 11 In the Add files and folders dialog box, select the files you want to restore and click Add.

You can click the folders or drives on the left to expand and view the files in a particular folder. You can search files based on their names or extensions.

- 12 Click Next.
- **13** In the Recovery target step, perform the following:

Dialog box	Snapshot copy	Backup copy
Restore to	Target VM - Select a VM. A list with all connected VMs having same operating systems as original target host is displayed. If you do not select a VM, the files are restored to the original VM.	 Cloud provider - Select cloud provider to where single file restore is to be performed. Configuration - To restore to an alternate configuration, select one from the drop-down. Region - To restore to an alternate region, select one from the drop-down. (For Azure and Azure Stack only) Subscription - To restore to an alternate subscription, select one from the drop-down. Target VM - Select a VM. A list with all connected/disconnected and Linux/Windows VMs are displayed for cross platform restore.

Restore target options Restore everything to original location

 Restore everything to a different location
 You must then provide a directory location. You can also enter a UNC path to the location.

Cross platform restore is supported for the following scenarios:

- NetBackup and Snapshot Manager on one cloud, target host on another cloud.
- NetBackup and Snapshot Manager on one cloud, another Snapshot Manager and target host on another cloud.
- NetBackup and Snapshot Manager on one cloud, AIR (Auto Image Replication) restore on another domain.
- **14** If **Restore everything to original location** option is selected, then click **Next** and select the following preferred option in the Recovery options step:

Dialog box	Snapshot copy	Backup copy
Options	 Append string to In the String field 	o file names d, enter the string that you want use to
	append. The strir of a file.	ng is appended before the last extension
	 Allow overwrite 	of existing files

You must have appropriate permissions.

Dialog box	Snapshot copy	Backup copy
Advanced options	N/A	 (Applicable only for Windows to Windows restore) Require to restore access control list - Select the checkbox to restore access control list which requires additional operations. Target host NAT gateway IP address - Enter network address translation gateway IP address, in case the target VM is behind a network gateway and is not directly accessible.
		Note: Only private IP or hostname allowed.

15 If **Restore everything to a different location** option is selected, then provide the **Directory for restore** and click **Next**.

16 In the Review step, view the selected options and click **Start Recovery**.

The restore job for the selected files is triggered. You can view the job details on the Activity monitor. After the job is successful, you can see summary of restored files in the job details.

Note: Permission on files are assigned based on uid/guid, during restore to non-similar environments (where user/groups does not match). Restored files/folders must have permission to non-intended users/groups on target host. Hence after successful restore of required files, user must modify the access as per requirement.

Note the following:

When restoring hardlinks for single file restore from Snapshot or Backup (source Linux VM to target Linux VM), ensure that you follow the following guidelines:

- When selecting folders and files in Add files and folders dialog box, do not select redundant entries. For example, selecting a folder and a file that exists in the same folder, since the folder already has that file.
- Even if redundant entries are selected, ensure that you do not select the Allow overwrite of existing files option in Recovery option step. This will result in failure of copying the hardlink file.

Restoring volumes on cloud virtual machines

You can restore one or more volumes on a virtual machine.

To restore a volume

- 1 On the left, click **Cloud**.
- 2 Click on the Virtual machines tab.
- **3** Select the virtual machine where the application is hosted.
- 4 After the VM is connected, on the top right, click **Add protection**.
- 5 Select a protection plan and click **Next**.
- 6 Click Protect.
- 7 To execute the protection plan, click **Backup now**.
- 8 To view the recovery points, click the **Recovery points** tab.
- **9** On the top right for the preferred recovery point, select **Restore volumes**.

You can also apply date filters to search across the recovery points.

- **10** In the **Restore volumes** dialog box, select one or more volumes.
- **11** From the **Target VM** list, select the VM on which you want to restore the volumes.

In case of restore from a replicated (non-primary) VM, the restore to original location is not supported. If you do not select a VM, the files are restored to the original VM.

12 Click Restore.

The restore job for the selected volumes is triggered. You can view the job details on the Activity monitor.

Troubleshooting

Troubleshooting snapshot restore process for Microsoft Azure cloud

When you trigger a subsequent (twice) restore operation on the same VM, an error occurs during restore operation. This error causes the following issues:

- The tags from original OS disk are not copied to newly created restored OS disk.
- User login might fail after the VM restore due to ssh failure.

Workaround:

Check if the ssh daemon is running on the system. If not, then perform the steps that are mentioned in the the following document provided by Microsoft:

learn.microsoft.com/en-us/troubleshoot/azure/virtual-machines/troubleshoot-ssh-connection

Filtering unsupported files and folders

If you try to restore files or folders from partition or file system that are not supported by Snapshot Manager, then you get the following error in the restore job.

Error nbcs (pid=<processs id>) Failed to restore file(s) and folder(s)
from snapshot for asset <asset name>

Workaround:

If you want to avoid listing files or folder while browsing for single file restore, which are not supported by Snapshot Manager, then enable CP DISKMAP check by setting below flag in bp.conf file of NetBackup master server.

CP_DISKMAP_CHECK = true/yes

Backup from restore operation is partially successful

Backup from restore operation is partially successful when disk is full on the selected target directory. Following messages are displayed:

```
Dec 29, 2022 2:57:51 PM - Info nbcs (pid=2244) Granular restore(SFR) is completed
    Dec 29, 2022 2:57:51 PM - Info nbcs (pid=2244) Summary of SFR Operation - Success
files/folders count: 0 ,
    Failed files/folders count: 1 , Warning files/folders
    count: 0, Skipped files/folders count: 0
    Dec 29, 2022 2:57:51 PM - Info nbcs (pid=2244)
    Detailed restore summary report is available on recovery target host at location:
    /var/log/flexsnap/restore/granular-restore-09b4d44d
```

Dec 29, 2022 2:57:51 PM - Warning bprd (pid=1977) Granular Restore from backup completed with error.

Copy the files manually from live access mount:

ip-10-239-185-241:/mnt/vpfs shares/vmfiles/8fcc/8fcc132b-a202-49a8-b654-81ff242a718a/livemount

Dec 29, 2022 2:57:51 PM - end Restore; elapsed time 0:01:51 the requested operation was partially successful(1)

For backup from restore if live mount is created successfully then even though there is other error reported apart from ASSET_NOT_FOUND, its considered as partial

success. If there is no network devices/filesystem mounted on target location and disk is full then below messages can be seen in job details:

```
Jan 02, 2023 12:11:16 AM - Error nbcs (pid=13934)
187776K space required for file/folder restore while 20K is total available space on
/disk1
```

In this case other network devices/file system must have been mounted on the target path, hence Snapshot Manager agent considers the free space on device/file system. But once it tries to copy the file it fails with space error logged into summary report. For example,

/var/log/flexsnap/restore/granular-restore-09b4d44d in above Job details log

Workaround:

Check the summary report on target host location. For example,

```
/var/log/flexsnap/restore/granular-restore-09b4d44d
[root@ip-10-239-187-148 granular-restore-09b4d44d]# cat root-error.log
Dec 29 09:27:44: ERROR - FILE: /disk1/dl380g9-149-vm15_package.zip
[Error 28] IOError: No space left on device
```

 If the file copy operation failed due to disk space, then create some space and copy the file from live mount.

The live mount path details can be found in the job details as follows:

```
Dec 29, 2022 2:57:51 PM - Warning bprd (pid=1977) Granular Restore from backup completed
with error.
Copy the files manually from live access mount:
```

ip-10-239-185-241:/mnt/vpfs_shares/vmfiles/8fcc/8fcc132b-a202-49a8-b654-81ff242a718a/livemount

Partial recovery is observed when user selects a disconnected target virtual machine

Partial recovery could be due to the following reasons:

- If the target virtual machine is disconnected (no connectivity through agent).
- If any failure is seen while copying files/folders on target virtual machine.
- When a window virtual machine content is restored on Linux target virtual machine.

In such partial recovery cases, the created instance access will not be deleted and will be available for next 24 hours.

The instance access retention interval is configurable by setting

CLOUD_VM_IA_RETENTION_INTERVAL_IN_HOURS key in bp.conf file. (Default value is 24hrs).

Workaround:

User can perform manual steps to access the Instant access share on target host and then manfully copy the required files/folders.

(Copy files over NFS) To restore Linux image content on Linux host:

 To mount an NFS share on a Linux system, install the NFS client package using the following command:

\$ sudo yum install nfs-utils

 Using the following mount command, mount the Instant access on target Linux host:

```
# Create a directory say /mnt/restore
$ mkdir -p /mnt/restore
# Mount the instant access
$ mount -t nfs <InstantAccessServer:InstantAccessPath> /mnt/restore
```

 Instant access path can be retrieved from activity manager logs which is in the following format:

<InstantAccessServer>:/mnt/vpfs_shares/vmfiles/<id>/<InstantAccessId>/livemount

(SMB access) To restore Windows image contents (with ACL) on Windows target host:

- SMB credentials of MSDP storage server of source virtual machine image must be added to the Windows credential manager.
- Use the given live mount to access virtual hard disks by navigating to Activity Monitor > Job details.

The virtual hard disks are listed under the folder with vhd_ as the prefix.

- On the Disk Management dialog box under the Action tab, attach the required virtual hard disk and click on OK.
- On the Add Drive Letter or Path dialog box, select Assign the following drive letter option to assign the letter to Virtual Disk to browse data and click on OK.
- Navigate to the assigned drive in the above step and copy the data manually.

(Live mount) To restore windows image contents on Linux target host:

- Linux must have the cifs package. Obtain the packages using the # yum install cifs-utils command.
- Create the mount directory using the # mkdir <my_mount_dir> command.
- Mount exported path using Samba username and password as follows: mount -t cifs -o username=<sambauser> //<InstantAccessServer>/<InstantAccessPath> <my_mount_dir>
- Copy the files using the following command:
 - # cp <my_mount_dir>/<file_path> <target_dir_path>

Issues with single file restore from backup of snapshot

Issue/Error	Description	Workaround
Log path to check	<pre>For information related to restore details on target host, check the following logs: path/file: /tmp/flexsnap-agentless-onhost.log /var/log/flexsnap/restore/granular-restore-*</pre>	To resolve the failures or exceptions occurred during single file restore on Snapshot Manager, refer to the following logs on Snapshot Manager host: /cloudpoint/logs/flexsnap.log
Pre-recovery check fails	When restoring files and folders to disconnected target virtual machine, the pre-recovery check fails with the following error:	Ensure that the target virtual machine is in connected state with agent configured for successful restore.
	Target VM state: Target VM <vm_name> has no agent configured</vm_name>	
	If recovery is started, restore operation would be partially successful.	
Partial recovery for source Linux VM to target Windows VM (no NFS client)	When restoring files and folders from source Linux VM to target Windows VM without installing NFS client on Windows target machine, then the recovery is partially successful with the following error displayed:	Install NFS client on window target machine before you perform restore from Linux VM to Windows VM.
	Error nbcs (pid=42513) Invalid operation for asset: <asset_id> Warning bprd (pid=42045) Granular Restore from backup completed with error. Copy the files manually from live access mount: <livemount_path>. Note that live access mount is available only for 24 brs.</livemount_path></asset_id>	

Issue/Error	Description	Workaround
Restore job fails for deleted target VM	Restore job fails with the following error when restoring files and folders on target VM which is deleted from cloud environment:	Select a different target VM.
	<pre>Error nbcs (pid=44859) Target VM not found, asset_id <asset_id></asset_id></pre>	
Create Instant access fails	Creation of Instant access fails during restore job if Instant access is not enabled on MSDP storage server.	Verify if Instant access is supported on MSDP media server by using the following pre-check script:
		/usr/openv/pdde/vpfs/bin/ia_byo_precheck.sh
Target VM does not have free drives to attach Virtual Disk	If the number of volumes containing the selected files are more than the number of free available drives on target host then the operation fails.	Restore files and folders from less number of volumes.
Not enough space: **\\driverMapping.json	If media server where MSDP is configured has FIPS enabled.	Disable FIPS on the media server where MSDP is installed or add domain user samba credentials to target VM.

Issue with Azure cloud provider VM's

If one of VM's disks is not initialized, downloading or restoring VM files using Instant access fails with the following error:

```
Jan 24, 2023 11:58:47 AM - Error NBWMC (pid=3716) Internal Error:
('failed to find operation system information, please check the source
VM', ('Failed to expose
VMDK', 1006), None)
Failed to create the instant access mount.
(4001)
```

Libguestfs is a third party tool used by Instant access to retrieve files from VM backup. If a disk is not initialized, libguestfs will not be able to handle it.

Workaround:

Initialize the disk, backup the VM and try to download or restore VM files using Instant access again.



Troubleshooting protection and recovery of cloud assets

This chapter includes the following topics:

- Troubleshoot cloud workload protection issues
- Troubleshoot PaaS workload protection and recovery issues

Troubleshoot cloud workload protection issues

Review the following log files to troubleshoot any issues with protection of cloud assets:

- Log files for configuration
- Log files for snapshot creation
- Log files for restore operations
- Log files for snapshot deletion

During troubleshooting, ensure that you have also reviewed the limitations. See "Limitations and considerations" on page 10.

For troubleshooting issues, see the NetBackup Status Codes Reference Guide.

To view the Snapshot Manager log files, see the Snapshot Manager logs topic in the *NetBackup Snapshot Manager Install and Upgrade Guide*.

Log files for configuration

Use the following logs to troubleshoot cloud configuration issues.

Process	Logs
tpconfig	Windows
tpconfig command is one way for registering	NetBackup install path/volmgr/debug/tpcommand
Snapshot Manager in NetBackup.	UNIX
	/usr/openv/volmgr/debug/tpcommand
nbwebservice	Windows
Plug-ins are configured using NetBackup REST	NetBackup install path/webserver/logs
API.	UNIX
	/usr/openv/wmc/webserver/logs
	/usr/openv/logs/nbwebservices
nbemm	Windows
nbemm stores the Snapshot Manager and plug-in	NetBackup install path/path/logs/nbemm
information in EMM database.	UNIX
	/usr/openv/logs/nbemm

Table 4-1Log files for configuration

Log files for asset discovery

Use the following logs to troubleshoot asset discovery issues.

Table 4-2

Log files for asset discovery

Process	Logs
ncfnbcs	Windows
Verifies if discovery was completed or not.	NetBackup install path/bin/vxlogview -o 366
	UNIX
	/usr/openv/netbackup/bin/vxlogview -o 366
Picloud	Windows
Provides the details of discovery operation.	NetBackup install path/bin/vxlogview -i 497
	UNIX
	/usr/openv/netbackup/bin/vxlogview -i 497

Table	4-2
-------	-----

Log files for asset discovery (continued)

Process	Logs
nbwebservice	Windows
To get details about the asset database workflows that are part of the discovery operation.	NetBackup install path/webserver/logs
Note: Refer to the same log files for details of assets that are added to protection plan.	/usr/openv/wmc/webserver/logs
	/usr/openv/logs/nbwebservices

Log files for snapshot creation

Use the following logs to troubleshoot snapshot creation issues.

Table 4-3Log files for snapshot creation		
Process	Logs	
nbpem	Windows	
nbpem PID for given job is available in the	NetBackup install path/bin/vxlogview -o 116	
NetBackup activity monitor.	UNIX	
	/usr/openv/netbackup/bin/vxlogview -o 116	
nbjm	Windows	
nbjm PID for given job is available in the	NetBackup install path/bin/vxlogview -o 117	
NetBackup activity monitor.	UNIX	
	/usr/openv/netbackup/bin/vxlogview -o 117	
nbcs	Windows	
nbcs PID for given job is available in the NetBackup activity monitor.	NetBackup install path/bin/vxlogview -i 366 -P nbcs_process_id	
	UNIX	
	/usr/openv/netbackup/bin/vxlogview -i 366 -P nbcs_process_id	
	The nbcs logs are available at the following location:	
	Windows	
	NetBackup install path/logs/ncfnbcs	
	UNIX	
	/usr/openv/logs/ncfnbcs	

Process	Logs
nbrb	Windows
nbrb is requested to provide a media server for a given job. For Cloud, a particular media server is picked up from the associated list of media	<i>NetBackup install path/</i> bin/vxlogview –o 118 UNIX
servers for a Snapshot Manager.	/usr/openv/netbackup/bin/vxlogview -i 118

Table 4-3Log files for snapshot creation (continued)

Log files for restore operations

Use the following logs to troubleshoot restore issues.

Table 4-4	Table 4-4	
Process	Logs	
nbwebservice	Windows	
The snapshot restore operation is triggered by	NetBackup install path/webserver/logs	
NetBackup REST API.	UNIX	
	/usr/openv/wmc/webserver/logs	
	/usr/openv/logs/nbwebservices	
bprd	Windows	
The NetBackup REST API communicates with bprd to initiate restore.	NetBackup install path/netbackup/logs	
	UNIX	
	/usr/openv/netbackup/logs/bprd	
ncfnbcs	Windows	
nbcs PID for given job is available in the	NetBackup install path/bin/vxlogview -i 366 -P	
NetBackup activity monitor.	nbcs_process_id	
	UNIX	
	/usr/openv/netbackup/bin/vxlogview -i 366 -P nbcs_process_id	

Log files for snapshot deletion

Use the following logs to troubleshoot snapshot deletion issues.

Process	Logs
bpdm	Windows
The snapshot delete or clean-up operation is triggered by bpdm.	NetBackup install path/netbackup/logs
	UNIX
	/usr/openv/netbackup/logs/bpdm
ncfnbcs	Windows
nbcs PID for given job is available in the	NetBackup install path/bin/vxlogview -i 366 -P
NetBackup activity monitor.	nbcs_process_id
	UNIX
	/usr/openv/netbackup/bin/vxlogview -i 366 -P nbcs_process_id

Table 4-5 Log files for snapshot deletion

Pre-recovery check fails with access denied error during alternate location restore

When attempting to perform recovery of a VM from a backup image copy, if you do not have the required privileges assigned to your role to perform alternate location restore, you encounter the error during the pre-recovery check operation.

This may happen when you have privilege to perform only original location recovery, and you are trying to do alternate location recovery.

Workaround

- While doing original location restore, do not change any pre-populated fields in the pre-recovery page.
- If you want to perform alternate location recovery, ensure that you have the required privileges.

Troubleshoot PaaS workload protection and recovery issues

Backup fails with error: 3808 Cannot check if the database exists.

You can see the following message in the Activity Monitor:

AuthorizationFailed -Message: The client '<clientId> '<objetId>' does not have authorization to perform action 'Microsoft.Sql/servers/databases/read' over scope
'<resoourceld>' or the scope is invalid. If access was recently granted, please refresh your credentials.

Explanation: This error occurs, when the Snapshot Manager and NetBackup are deployed in AKS, and:

- The media server pod node pool is a different node pool from the Snapshot Manager node pool
- Managed Identity is enabled in the Snapshot Manager Virtual Machine Scale set

Workaround: Do any of the following:

- In the media server that you are using for backup and restore, enable Managed Identity on the Scale set. Also, assign required permission in the role attached to this managed identity.
- Create a storage unit on the MSDP server, and use only those media servers that has Managed Identity enabled on Scale configuration.

Backup fails when the database or the resource group has Read-only lock applied, and partially successful when Delete lock is applied.

Explanation: This issue occurs if the Read-only lock or Delete lock attribute is applied to the database or the resource group.

Workaround: Before performing any backup or restore, remove any existing Read-only lock and Delete lock attributes from the database or the resource group.

Status Code 150: Termination requested by administrator

Explanation: This appears when you manually cancel a backup or a restore job from the activity monitor and a database is created on the portal during the partial restore operation.

Workaround:Manually clean up the database on the provider portal, and temporary staging location at the universal share mount location under specific directory created by database name.

Stale status messages in Activity monitor

Explanation: If the Snapshot Manager container service restarts abruptly; the provider protected restore jobs may remain in the active state and you may not see the updated status on the activity monitor details page.

Workaround: Restart the workflow containers using the following command in the Snapshot Manager:

```
docker restart flexsnap-workflow-system-0-min
flexsnap-workflow-general-0-min
```

After restarting the containers, the restore jobs are updated with the latest status in the activity monitor.

Status Code 233: Premature eof encountered

Explanation: Appears if the client name used for backup exceeds the length of 255 characters.

The bpdbm logs confirms the same by displaying the following error message:

db_error_add_to_file: Length of client is too long. Got 278, but limit is 255. read_next_image: db_IMAGEreceive() failed: text exceeded allowed length (225)

Note: This is observed when the primary server is RHEL.

Workaround:Rename the database such that the client name fits within the length of 255 characters.

Error: Broken pipe (32), premature end of file encountered EXITING with status 42, network read failed

Explanation:Occurs during backup if the client name used is big in length, due to this the file path length of catalog image exceeds 256 chars and fails with the above error message in activity monitor.

The bpdbm logs confirms the same by displaying the following error message:

<16> db_error_add_to_file: cannot stat(\\?\C:\Program Files\Veritas \NetBackup\db\images \azure-midb-1afb87487dc04ddc8fafe453dccb7ca3+ nbux-qa-bidi-rg+eastus+az-sql-mi-bidinet01+ testdb_bidinet02\1656000000\tmp\catstore\ BACKUPNOW+141a73e7-cdc4-4371-823a-f170447dba2d_ 1656349831_FULL.f_imgUserGroupNames0): No such file or directory (2) <16> ImageReadFilesFile::get_file_size: cannot stat(\\?\C:\Program Files\Veritas\NetBackup\db \images\azure-midb-1afb87487dc04ddc8fafe453d ccb7ca3+nbux-qa-bidi-rg+eastus+az-sql-mi-bidinet01+testdb_ bidinet02\165600000\tmp\catstore\BACKUPNOW+141a73e7-cdc4-4371 -823a-f170447dba2d_1656349831_FULL.f_imgUserGroupNames0): No such file or directory (2) <16> ImageReadFilesFile::executeQuery: Cannot copy \\?\C:\Program Files\Veritas\NetBackup\db\images\azure-midb-1afb87487dc04ddc8fafe453dccb7

```
ca3+nbux-qa-bidi-rg+eastus+az-sql-mi-bidinet01+testdb_bidinet02\1
656000000\tmp\catstore\BACKUPNOW+141a73e7-cdc4-4371-823a-f170447d
ba2d_1656349831_FULL.f_imgUserGroupNames0
```

Note: This is observed when the primary server is Windows.

Workaround: Rename the database such that the file path length fits within the length of 256 characters.

Status Code 3801: Cannot complete the requested operation.

Explanation: NetBackup is not able to successfully carry out the requested operation.

Recommended action: Please refer to the activity monitor details for possible reason of failure.

Status Code 3817: Cannot complete the pre-backup operation

Explanation: The error message seen in dbagentsutil logs as,pg_dump: error: query failed: ERROR: permission denied for table test;pg_dump: error: query was: LOCK TABLE public.test IN ACCESS SHARE MODE; Invoked operation: PRE BACKUP failed

Occurs when you try to backup a database which has multiple tables with different roles. If tables have at least one different owner, other than the database owner, and it is not a member the database owner role, then the backup may fail.

Recommended action: You must have a role that has access to all tables inside the database which you want to backup or restore.

For example, say that we wanted to backup the school database which has two tables.

- student, Owner is postgres
- teacher, Owner is schooladmin

Create a new role. Say, NBUbackupadmin

Run the following command to create the role:

```
postgres=> CREATE USER NBUbackupadmin WITH PASSWORD '********';
```

CREATE ROLE

To make this new role a member of postgres and schooladmin role, run:

postgres=> GRANT postgres TO NBUbackupadmin;

```
GRANT ROLE
postgres=> GRANT schooladmin TO NBUbackupadmin;
GRANT ROLE
```

Note: You must have a role who is either owner or member of the owner of the table, for all tables inside database.

Backup fails with Status 40 (Network connection broken)

Explanation: Backups fail due to loss of connectivity to the media server.

Recommended action: You can restart the backup job if the policy has checkpoints enabled. Once the network issue is resolved, select the incomplete backup job in web UI and click **Resume**. The job resumes from the point it was stopped. If checkpoint is not enabled in the policy, the job shows up as a failed job in the web UI.

Backup job fails with the error: "Failed to backup database"

Explanation: The Job details contain additional details: ManagedIdentityCredential authentication unavailable. The requested identity is not assigned to this resource. The allocated media server doesn't have any Managed Identity attached to it.

Recommended action: If you use system or user managed identity for the PaaS Azure SQL and Managed Instances, apply the same set of permissions/rules to the media server(s) and the snapshot manager. If you use user managed identity, attach the same user managed identity to the media server(s) and the snapshot manager.

Error code 3842 - The requested backup type for the corresponding PaaS asset is unsupported.

Differential incremental backup is supported for only for Azure SQL server. When you select an unsupported backup type, this error appears.

Error code 3843 or 3844 - Failed to disable CDC.

Appears when you do not have permissions to enable or disable CDC.

Explanation: Give NetBackup the necessary permissions to enable or disable CDC in your Azure environment.

Note: Do not enable CDC manually. Provide the permissions to NetBackup for enable or disable CDC.

Error: Client restore EXIT STATUS 5: the restore failed to recover the requested files Cloud policy restore error (2824)

Error: ERR - Failed to restore database [<db_name>] with name [<db_name>]. ERR - Failed to open file ". Errno = 12: client restore EXIT STATUS 5: the restore failed to recover the requested files

Explanation: Occurs during restore if the backup image is generated on 10.2 media and restore goes to an older (< 10.2) media server.

Workaround: Change the restore media to 10.2 and remove the older media from storage.