

Veritas™ File System Programmer's Reference Guide

Linux

5.1 Service Pack 1

Veritas File System Programmer's Reference Guide

The software described in this book is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Product version: 5.1SP1

Document version: 5.1SP1.1

Legal Notice

Copyright © 2010 Symantec Corporation. All rights reserved.

Symantec, the Symantec logo, Veritas, Veritas Storage Foundation, CommandCentral, NetBackup, Enterprise Vault, and LiveUpdate are trademarks or registered trademarks of Symantec corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation
350 Ellis Street
Mountain View, CA 94043
<http://www.symantec.com>

Technical Support

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our Web site at the following URL:

www.symantec.com/business/support/index.jsp

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

Contacting Technical Support

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/contact_techsupp_static.jsp

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

- Product release level

- Hardware information
- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
 - Error messages and log files
 - Troubleshooting that was performed before contacting Symantec
 - Recent software configuration changes and network changes

Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs or manuals

Support agreement resources

If you want to contact Symantec regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan	customercare_apac@symantec.com
Europe, Middle-East, and Africa	semea@symantec.com
North America and Latin America	supportsolutions@symantec.com

Documentation

Your feedback on product documentation is important to us. Send suggestions for improvements and reports on errors or omissions. Include the title and document version (located on the second page), and chapter and section titles of the text on which you are reporting. Send feedback to:

docs@symantec.com

About Symantec Connect

Symantec Connect is the peer-to-peer technical community site for Symantec's enterprise customers. Participants can connect and share information with other product users, including creating forum posts, articles, videos, downloads, blogs and suggesting ideas, as well as interact with Symantec product teams and Technical Support. Content is rated by the community, and members receive reward points for their contributions.

<http://www.symantec.com/connect/storage-management>

Contents

Technical Support	4
Chapter 1	Veritas File System software developer's kit 11
	About the software developer's kit 11
	File System software developer's kit features 11
	API library interfaces 12
	File Change Log 12
	Multi-volume support 13
	Veritas File System I/O 13
	Software developer's kit packages 13
	Required libraries and header files 14
	Compiling environment 14
	Recompiling with a different compiler 14
Chapter 2	File Change Log 17
	About the File Change Log file 17
	Recorded changes 17
	Using the File Change Log file 18
	File Change Log logging activation 19
	File Change Log file layout 20
	Record types 22
	Special records 24
	Typical record sequences 24
	File Change Log tunables 25
	How tunables handle File Change Log growth size 26
	Application programming interface for File Change Log 27
	Ease of use 27
	Backward compatibility 28
	API functions 28
	File Change Log record 36
	Copying File Change Log records 43
	Veritas File System and File Change Log upgrade and downgrade 47
	Reverse path name lookup 48
	Inodes 48

	<code>vxfs_inotopath_gen</code>	49
Chapter 3	Multi-volume support	51
	About multi-volume support	51
	Uses for multi-volume support	52
	Volume application programming interfaces	52
	Administering volume sets	53
	Querying the volume set for a file system	53
	Modifying a volume within a file system	54
	Encapsulating and de-encapsulating a volume	54
	Allocation policy application programming interfaces	54
	Directing file allocations	55
	Creating and assigning policies	56
	Querying the defined policies	57
	Enforcing a policy	58
	Data structures	58
	Using policies and application programming interfaces	59
	Defining and assigning allocation policies	59
	Using volume application programming interfaces	60
Chapter 4	Named data streams	63
	About named data streams	63
	Uses for named data streams	64
	Named data streams application programming interface	64
	Listing named data streams	66
	Namespace for named data streams	67
	Behavior changes in other system calls	67
	Querying named data streams	68
	Application programming interface	69
	Command reference	69
Chapter 5	Veritas File System I/O	71
	About Veritas File System I/O	71
	Freeze and thaw	71
	Caching advisories	74
	Direct I/O	74
	Concurrent I/O	75
	Unbuffered I/O	76
	Other advisories	76
	Extents	77
	Extent attributes	78

	Reservation: preallocating space to a file	79
	Fixed extent size	79
	Application programming interface for extent attributes	80
	Allocation flags	81
	Allocation flags with fixed extent size	83
	How to use extent attribute APIs	84
	Setting fixed extent size	84
Chapter 6	Thin Reclamation	87
	About Thin Storage	87
	About Thin Reclamation	87
	Thin Reclamation application programming interface	87
	vxfs_ts_reclaim return values	90
Index		91

Veritas File System software developer's kit

This chapter includes the following topics:

- [About the software developer's kit](#)
- [File System software developer's kit features](#)
- [Software developer's kit packages](#)
- [Required libraries and header files](#)
- [Compiling environment](#)

About the software developer's kit

Veritas File System (VxFS) Software Developer's Kit (SDK) provides developers with the information necessary to use the application programming interfaces (APIs) to modify and tune various features and components of the Veritas File System. These APIs are provided with the VxFS Software Developer's Kit.

Most of the APIs covered in this document are available in the VxFS 4.0 release and subsequent releases.

File System software developer's kit features

This section provides an overview of the VxFS features that are accessible with the SDK.

API library interfaces

The API library interfaces highlighted in this SDK are the `vxfsutil` library and VxFS IOCTL directives. The library contains a collection of API calls that applications can use to take advantage of the features of the VxFS file system. Manual pages are available for all of the API interfaces.

[Table 1-1](#) describes the API calls and features available in the VxFS API library.

Table 1-1 Library APIs and features

APIs	Feature
inotopath	Inode-to-path lookup
nattr	Named Data Stream
FCL	File Change Log
MVS	Multi-volume support
Caching Advisories	IOCTL directives
Extents	IOCTL directives
Freeze/Thaw	IOCTL directives

The VxFS API library, `vxfsutil`, can be installed independent of the Veritas File System product. This library is implemented using a stubs library and dynamic library combination. Applications are compiled with the stubs library `libvxfsutil.a`, making the application portable to any VxFS target environment. The application can then be run on a VxFS target, and the stubs library finds the dynamic library that is provided with the VxFS target.

The stubs library uses a default path for the location of the `vxfsutil.so` dynamic library. In most cases, the default path should be used. However, the default path can be overridden by setting the environment variable, `LIBVXFSUTIL_DLL_PATH`, to the path of the `vxfsutil.so` library. This structure allows an application to be deployed with minimal issues related to compatibility with other releases of VxFS.

File Change Log

The VxFS File Change Log (FCL) tracks changes to files and directories in a file system. Applications such as backup products, Web crawlers, search and indexing engines, and replication software that typically scan an entire file system searching for modifications since a previous scan can use the File Change Log.

See [“About the File Change Log file”](#) on page 17.

Multi-volume support

The multi-volume support (MVS) feature allows a VxFS file system to use multiple Veritas™ Volume Manager (VxVM) volumes as underlying storage. Administrators and applications can control where files go to maximize effective performance, while minimizing cost. This feature can be used only with Veritas Volume Manager. In addition, some of the functionality requires additional license keys.

See [“About multi-volume support”](#) on page 51.

Veritas File System I/O

VxFS conforms to the System V Interface Definition (SVID) requirements and supports user access through the Network File System (NFS). Applications that require performance features not available with other file systems, can take advantage of VxFS enhancements.

Software developer's kit packages

The `VRTSfssdk` package comprises the SDK. The `VRTSfssdk` package contains libraries, header files, and sample programs in source and binary formats that demonstrate usage of the VxFS API interfaces to develop and compile applications. The `VRTSfssdk` package also contains this guide and the API manual pages.

The directory structure in the `VRTSfssdk` package is as follows:

<code>src</code>	Contains several subdirectories with sample programs and GNU-based <code>Makefile</code> files on each topic of interest.
<code>bin</code>	Contains symlinks to all the sample programs in the sources directory for easy access to binaries.
<code>include</code>	Contains the header files for API library and <code>ioctl</code> interfaces.
<code>lib</code>	Contains the pre-compiled <code>vxfsutil</code> API interface stubs library.
<code>libsrc</code>	Contains the source code for the <code>vxfsutil</code> API interface stubs library.

The `VRTSfssdk` package can be obtained separately from the VxFS package. To run the applications or sample programs, a licensed VxFS target is required. In addition, the VxFS license of the required features should be installed on the target system.

Required libraries and header files

The `VRTSfssdk` package is installed in the `/opt` directory. The associated libraries and header files are installed in the following locations:

- `/opt/VRTSfssdk/5.0/lib/libvxfsutil.a`
- `/opt/VRTSfssdk/5.0/include/vxfsutil.h`
- `/opt/VRTSfssdk/5.0/include/sys/fs/fcl.h`
- `/opt/VRTSfssdk/5.0/include/sys/fs/vx_ioctl.h`

There are also symlinks to these files from the standard Veritas paths: `/opt/VRTS/lib` and `/opt/VRTS/include`. The standard paths are the default paths in the latest releases of VxFS and the VxFS SDK.

Compiling environment

The SDK package installs sample programs with compiled binaries.

The requirements for running the sample programs are as follows:

- A target system with the appropriate version of `VRTSvxfs` installed
- Root permission, which some programs require
- A mounted VxFS 4.1 or later file system. Some may require a file system that is mounted on a Veritas Volume Set.

Note: Some programs may require special volume configurations (volume sets). In addition, some programs require a file system to be mounted on a volume set.

Recompiling with a different compiler

The required tools for recompiling the `src` or `libsrc` directory are as follows:

- `gmake` or `make` command
- `gmake` command
- `gmake` command
- `gmake` command
- `gcc` compiler or `cc` command
- `gcc` compiler
- `gcc` compiler

■ gcc compiler

To recompile the src and libsrc directories

- 1 Edit the `make.env` file and modify it with the path to your compiler.
- 2 Change to the `src` or `libsrc` directory and run the `gmake` command:
- 3 After writing the application, compile it as follows:

```
# gcc -I /opt/VRTSfssdk/5.0/include  
-L /opt/VRTSfssdk/5.0/lib -ldl -o MyApp \  
MyApp.c libvxfsutil.a
```

To compile the src or libsrc directory, edit the `/opt/VRTSfssdk/5.0/make.env` file as follows:

- 1 Select the compiler path on your local system. Set the `CC` variable to be the path on your system:

```
CC=/opt/bin/cc  
#CC=/usr/local/bin/gcc
```

Use whichever path is appropriate for your compiler.

- 2 Change to the `src` or `libsrc` directory and type:

```
# gmake
```

or

```
# make
```


File Change Log

This chapter includes the following topics:

- [About the File Change Log file](#)
- [Record types](#)
- [File Change Log tunables](#)
- [Application programming interface for File Change Log](#)
- [Reverse path name lookup](#)

About the File Change Log file

The VxFS File Change Log (FCL) tracks changes to files and directories in a file system.

Applications that typically use the FCL are usually required to perform the following:

- Scan an entire file system or a subset
- Discover changes since the last scan

These applications may include: backup utilities, webcrawlers, search engines, and replication programs.

Note: The FCL tracks when the data has changed and records the change type, but does not track the actual data changes. It is the responsibility of the application to examine the files to determine the changed data.

Recorded changes

The File Change Log records the following file system changes:

- Creates
- Links
- Unlinks
- Renaming
- Data appended
- Data overwritten
- Data truncated
- Extended attribute modifications
- Holes punched
- Miscellaneous file property updates

Note: The FCL is supported only on disk layout Version 6 and later.

The FCL stores changes in a sparse file, referred to as the FCL file, in the file system namespace. The FCL file is always located in `/mount_point/lost+found/changelog`. The FCL file behaves like a regular file, however, some user-level operations are prohibited, such as writes. The standard system calls `open(2)`, `lseek(2)`, `read(2)` and `close(2)` can access the data in the FCL file. All other system calls such as `mmap(2)`, `unlink(2)`, and `ioctl(2)` are not allowed on the FCL file.

Warning: For compatibility with future VxFS releases, the FCL file might be pulled out of the namespace, and these standard system calls may no longer work. Therefore, Symantec recommends that all new applications be developed using the programmatic interface.

See [“Application programming interface for File Change Log”](#) on page 27.

Using the File Change Log file

VxFS tracks changes to the file system by appending the FCL file with information pertaining to those changes.

This enables you to do the following:

- Use the FCL to determine the sequence of operations that have been performed on the file system in general or on a specific file after a particular point in time.

For example, an incremental backup application can scan the FCL file to determine which files have been added or modified since the file system was last backed up.

- Configure the FCL to track additional information, such as file opens, I/O statistics, and access information, such as user ID.

You can then use this information to gather the following data:

- Space usage statistics to determine how the space usage for different types of data.
- Usage profile for the different files on a file system across different users to help determine which data has been recently accessed and by whom.

Space usage

You can use the FCL file to track space usage when a file system gets close to being full. The FCL file can be searched for recently created files (file creates) or write records to determine newly added files or existing files that have grown recently.

Depending on the application needs, the search can be done on the entire FCL file, or on a portion of the FCL file corresponding to a specific time frame. Additionally, you can look for files created with particular names. For example, if users are downloading *.mp3 files that are taking up too much space, the FCL file can be read to find files created with the name *.mp3.

Full system scan reductions

VxFS creates and logs an FCL record for every update operation performed on an FCL-enabled file system. These operations include creates, deletes, rename, mode changes, and writes. Therefore, incremental backup applications or applications that maintain an index of a file system based on the filename, file attributes, or content can avoid a full system scan by reading the FCL file to detect the files that have changed since the previous backup or previous index update.

File history traces

You can trace a file's history by scanning the FCL file and coalescing FCL record sequences for a file. You can also use the related FCL records from a file's creation, attribute changes, write records, and deletion to track the file's history.

File Change Log logging activation

By default, FCL logging is deactivated and can be activated on a per-file system basis using the `fcladm` command.

See the `fccladm(1M)` manual page.

When FCL login is activated, new FCL records are appended to the FCL file as file system changes occur. When FCL logging is turned off, further recording stops, but the FCL file remains as `/lost+found/changelog`. You can only remove an FCL file by using the `fccladm` command.

The FCL file has an associated version that represents the layout or is the internal representation of the FCL file, along with the list of events recorded in the FCL file.

Whenever a new version of VxFS is released, the following occurs:

- There may either be additional events recorded in the FCL file
- The internal representation of the FCL file may change

This results in the FCL file version getting updated. For example, in VxFS 4.1, the default was Version 3. However, because VxFS 5.0 and later releases record additional sets of events that are not available in Version 3 (such as file opens), the default version in VxFS 5.0 and later releases is 4. To provide backward compatibility for applications developed on VxFS 4.1, VxFS 5.0 and later releases provide an option to specify an FCL version during activation. Depending on the specified version, the logging of the new record types is either allowed or disallowed.

The logging of most of the newly added records in VxFS 5.0 and later releases, such as file opens and I/O statistics, is optional and is turned off by default. Recording of these events can be enabled or disabled using the `[set]` and `[clear]` options of the `fccladm` command.

The FCL meta-information comprising of the file system state, version, and the set of events being tracked is persistent across reboots and file system unmounts or mounts. The version and event information is also persistent across re-activations of FCL logging.

File Change Log file layout


In VxFS 4.1, the internal layout of the FCL file was exposed to the user and the applications were expected to access the FCL file using standard file system interfaces, such as `open(2)`, `read(2)`, and `lseek(2)`. However, this methodology may lead to future compatibility issues, because if the underlying FCL layout and the FCL version changes, the application must be changed and recompiled to accommodate these changes.

VxFS 5.0 introduced a new programming interface that provides improved compatibility, even when the on-disk FCL layout changes. With this API, the FCL

layout is not a concern for applications. Consequently, this section provides only a rudimentary description of the FCL layout.

The FCL file is usually a sparse file containing the FCL superblock and the FCL records. The first information block in the FCL file is the FCL superblock. This block may be followed by an optional hole as well as the FCL records which contain information about the changes in the file system.

Figure 2-1 depicts the FCL file format.



File Change Log superblock

Changes to files and directories in the file system are stored as FCL records. The superblock, which is currently stored in the first block of the FCL file, describes the state of the FCL file.

The superblock indicates the following:

- Whether FCL logging is enabled
- What time it was activated
- The current offsets of the first and last FCL records
- The FCL file version
- The event mask for the set of events currently being tracked
- The time that the event mask was last changed

The FCL file containing just the superblock is created when FCL is first activated using the `fcladm on` command. The superblock gets removed only when the FCL file is removed using the `fcladm rm` command.

When the FCL is activated using `fcladm on`, the state in the superblock and its activation time are changed. Whenever any file system activity results in a record being appended to the FCL file, the last offset gets updated.

As the FCL file grows in size, depending on the file system tunables `fcl_maxalloc` and `fcl_keeptime`, the oldest records at the start of the FCL file are thrown away to free up some space, as the first offset gets updated. When the set of events tracked in the FCL file is changed using the `[set]` or `[clear]` options of the `fcladm` command, the event mask and the event mask change time are updated. An event mask change also results in an event mask change record containing the old event mask and the new event mask change being logged in the FCL file.

File Change Log record

The FCL records contain information about these typical changes:

- The inode number of the file that has changed
See “[Inodes](#)” on page 48.
- The time of change
- The type of change
- Optional information depending on the record type
Depending on the record type, the FCL record may also include the following information:
 - A parent inode number
 - A filename for file deletes, links, and similar operations
 - A command name for a file open record
 - The actual statistics for an I/O statistics record

See [Figure 2-1](#) on page 21.

Record types

[Table 2-1](#) lists actions that generate FCL record types.

Table 2-1 FCL record types

Action to create an FCL record	Record type
Add a link to an existing file or directory	VX_FCL_LINK
Appending write to a file	VX_FCL_DATA_EXTNDWRITE

Table 2-1 FCL record types (*continued*)

Action to create an FCL record	Record type
Create a file or directory	VX_FCL_CREATE
Create a named data stream directory	VX_FCL_CREATE
Create a symbolic link	VX_FCL_SYMLINK
Perform an mmap on a file in a shared and writable mode	VX_FCL_DATA_OVERWRITE
Promote a file from a Storage Checkpoint	VX_FCL_UNDELETE
Punch a hole into a file	VX_FCL_HOLE_PUNCHED
Remove a file or directory	VX_FCL_UNLINK
Remove a named data stream directory	VX_FCL_UNLINK
Rename a file or directory	VX_FCL_RENAME
Rename a file to an existing file	VX_FCL_UNLINKVX_FCL_RENAME
Set file attributes (allocation policies, ACLs, and extended attributes)	VX_FCL_EATTR_CHG
Set file extent reservation	VX_FCL_INORES_CHG
Set file extent size	VX_FCL_INOEX_CHG
Set file group ownership	VX_FCL_IGRP_CHG
Set file mode	VX_FCL_IMODE_CHG
Set file size	VX_FCL_DATA_TRUNCATE
Set file user ownership	VX_FCL_IOWN_CHG
Set mtime of a file	VX_FCL_MTIME_CHG
Truncate a file	VX_FCL_DATA_TRUNCATE
Write to an existing block in a file	VX_FCL_DATA_OVERWRITE
Open a file	VX_FCL_FILEOPEN

Table 2-1 FCL record types (continued)

Action to create an FCL record	Record type
Write I/O statistics of a file to FCL	VX_FCL_FILESTATS
Change the set of events tracked in the FCL	VX_FCL_EVNTMSK_CHG

Note: Table 2-1 lists all the events recorded by default when the `fcladm on` command activates FCL logging, except `fileopen` and `filestat`.

Access information for each of these events is also not recorded by default. Use the `[set]` option of the `fcladm` command to record opens, I/O statistics and access information.

See the `fcladm(1M)` manual page.

These record types belong to `fcl_chgtype.t`. `fcl_chgtype.t`, which is an enumeration that is defined in the `fcl.h` header file.

See Table 2-2 on page 41.

Special records

The following record types are no longer visible through the API:

- VX_FCL_HEADER
- VX_FCL_NOCHANGE
- VX_FCL_ACCESSINFO

Typical record sequences

The life cycle of a file in a file system is recorded in the FCL file from creation to deletion.

When creating a file, the following is a typical sequence of FCL records written to the log:

```
VX_FCL_CREATE
VX_FCL_FILEOPEN (if tracking file opens is enabled)
VX_FCL_DATA_EXTNDWRITE
VX_FCL_IMODE_CHG
```


When writing a file, one of the following FCL records is written to the log for every write operation. The record depends on whether the write is past the current end of the file or within the file.

```
VX_FCL_DATA_EXTNDWRITE  
VX_FCL_DATA_OVERWRITE
```

The following shows a typical sequence of FCL records written to the log, when file *a* is renamed to *b* and both files are in the file system:

```
VX_FCL_UNLINK (for file b, if it already exists)  
VX_FCL_RENAME (for a rename from a to b)
```

File Change Log tunables

You can set four FCL tunable parameters using the `vxtunefs` command.

See the `vxtunefs(1M)` manual page.

The following are the four available FCL tunable parameters:

fcl_keeptime Specifies the duration in seconds that FCL records stay in the FCL file before they can be purged. The first records to be purged are the oldest ones, which are located at the beginning of the file. Additionally, records at the beginning of the file can be purged if the allocation to the FCL file exceeds `fcl_maxalloc` bytes. The default value is “0”. Note that `fcl_keeptime` takes precedence over `fcl_maxalloc`. No hole is punched if the FCL file exceeds `fcl_maxalloc` bytes and the life of the oldest record has not reached `fcl_keeptime` seconds.

Tuning recommendation: The `fcl_keeptime` tunable parameter needs to be tuned only when the administrator wants to ensure that records are kept in the FCL for `fcl_keeptime` length of time. The `fcl_keeptime` parameter should be set to any value greater than the time between FCL scans. For example, if the FCL is scanned every 24 hours, `fcl_keeptime` could be set to 25 hours. This prevents FCL records from being purged before they are read and processed.

fcl_maxalloc Specifies the maximum amount of space in bytes to be allocated to the FCL file. When the space allocated exceeds `fcl_maxalloc`, a hole is punched at the beginning of the file. As a result, records are purged and the first valid offset is updated in the FCL superblock. The minimum value of `fcl_maxalloc` is 4MB. The default value is `fs_size/33`.

`fcl_winterval` Specifies the time in seconds that must elapse before the FCL records multiple overwrite, extending write, or truncation records for the same inode. This helps to reduce the number of repetitive records in the FCL. The `fcl_winterval` time-out is per inode. If an inode happens to go out of cache and returns, its write interval is reset. As a result, there could be more than one write record for that file in the same write interval. The default value is 3600 seconds.

Tuning recommendation: The `fcl_winterval` tunable parameter should be set to a value that is less than the time between FCL scans. For example, if the FCL is scanned every 24 hours, `fcl_winterval` should be set to less than 24 hours. This ensures that there is at least one record in the FCL for each file being overwritten, extended, or truncated between scans.

`fcl_ointerval` Specifies the time interval in seconds within which subsequent opens of a file do not produce an additional FCL record. This helps to reduce the number of repetitive file-open records logged in the FCL, especially in the case of frequent accesses through NFS. If the tracking of access information is also enabled, a subsequent file open event within `fcl_ointerval` might produce a record, if the latter open is by a different user. Similar to `fcl_ointerval`, if an inode goes out of cache and returns, or if there is an FCL sync, there might be more than one file open record within the same open interval. The default value is 600 seconds.

Tuning recommendations: If the application using file-open records only needs to know if a file has been accessed by any user from the last time it scanned the FCL, `fcl_ointerval` can be set to a time period in the range of the time between the scans. If the application is interested in tracking every access, the tunable can be set to zero.

In the case where the file system is extensively accessed over NFS, depending on the platform and the NFS implementation, there might be a large number of file open records logged. In such cases, it is recommended to set the tunable to a higher value to avoid flooding the FCL with repetitive records.

How tunables handle File Change Log growth size

Figure 2-2 illustrates an example of record purging as an FCL file grows in size.


The FCL file on the left contains 8K blocks and no holes. When activity occurs on the file system, it is recorded in the FCL and the growth results in the FCL file on the right.

When the FCL file size reaches the maximum allowable size that is specified by the `fcl_maxalloc` tunable, older records are purged and space is freed. The FCL

feature only purges records that are older than a time specified by `fcl_keeptime`. The freed space is always in units of an internal hole size.

Figure 2-2 displays the file system freeing up space in the FCL file in 8K units.

When the FCL file surpasses the maximum allocation for the first time and the number of older records is 20K, the program purges 16K. This leaves a 16K hole following the FCL superblock. The first valid offset in the FCL superblock is then updated to 24K.



Application programming interface for File Change Log

In addition to the existing programmatic interface exposed through `libvxfsutil: vxfs_fcl_sync`, VxFS 5.0 and later releases provide a new set of programmatic interfaces which replace the mechanism to access an FCL file via the set of standard system calls: `open(2)`, `lseek(2)`, `read(2)` and `close(2)`. This API provides the following improvements:

Ease of use

The API reduces the need to write additional code to parse FCL entries.

Most of the on-disk FCL records are of a fixed size and contain only the default information such as the inode number or time-stamp. However, some records can

be of variable sizes, such as a file remove or rename record. These records contain additional information, such as the name of a file that is removed or renamed.

To ensure that the first few bytes at the start of any file system block is always a valid FCL record (if the filename crosses a block boundary), the file system block may be split across multiple on-disk records. Previously, you were required to write additional code to assemble these records to get the filename. The API in the VxFS 5.0 and later releases provides a mechanism to directly read a single assembled logical record. This makes it easier for applications using the API. The API also lets the application specify a filter to indicate a subset of the events of interest and return only required records.

Backward compatibility

The API lets applications read the FCL independent of the FCL layout changes. For example, consider a scenario where an application directly accesses and interprets the on-disk FCL records. If the next VxFS release adds new records or changes the way the records are stored in the FCL file, the application needs to be rewritten or at least re-compiled to accommodate for the changes (under previous VxFS versions).

With an intermediate API, the on-disk layout of FCL is hidden from the application, so even if the disk layout of FCL changes, the API internally translates the data returns the expected output record to the user. The user application can then continue without a recompilation or a rewrite. This insulates programs from FCL layout changes and provides greater compatibility for existing applications.

API functions

The API uses the following type of functions:

- Functions for accessing FCL records
- Functions for seeking offsets and time stamps

Functions for accessing File Change Log records

The following are general functions for accessing FCL records:

<code>vxfs_fcl_open</code>	Opens the FCL file and returns a handle which can be used for further operations. All subsequent accesses of the FCL file through the API must use this handle.
<code>vxfs_fcl_close</code>	Closes the FCL file and cleans up resources associated with the handle

<code>vxfs_fcl_getinfo</code>	Returns the FCL version number along with the state (on/off) of the FCL file
<code>vxfs_fcl_read</code>	Reads FCL records of interest to the user into a buffer passed in by the user
<code>vxfs_fcl_copyrec</code>	Copies an FCL record. If the source record contains pointers, it relocates them to point to the new location.

Functions for seeking offsets and time stamps in the File Change Log

Users have the option to seek to a particular point in the File Change Log based on the offset from where they left off, or to the first record after a specified time.

The following functions can seek offsets and time stamps in the FCL:

<code>vxfs_fcl_getcookie</code>	Returns an opaque structure (referred to hereinafter as a cookie) which embeds the current FCL activation time and the current offset. This cookie can be saved and later passed into <code>vxfs_fcl_seek</code> to continue reading from where the application left off last time.
<code>vxfs_fcl_seek</code>	Extracts data from the cookie passed and seeks to the specified offset. A cookie is embedded with the FCL activation time and file offset.
<code>vxfs_fcl_seektime</code>	Seeks to the first record in the FCL after the specified time

`vxfs_fcl_open`

The following is the syntax for the `vxfs_fcl_open()` function:

```
int vxfs_fcl_open(char *pathname, int flags, void **handle);
```

This function opens the FCL file and returns a handle which should be used for all further accesses to the FCL through the API (for example, `vxfs_fcl_read`, `vxfs_fcl_seek`, etc.).

`vxfs_fcl_open` has two parameters: *pathname* and *handle*. The *pathname* can be a pointer to an FCL filename or a mount point. If *pathname* is a mount point, `vxfs_fcl_open` automatically determines if the FCL is activated on the mount point and opens the FCL file associated with the mount point (currently `mount_point/lost+found/changelog`).

`vxfs_fcl_open` then determines if it is a valid FCL file, and if the FCL file version is compatible with the library. The `vxfs_fcl_open()` function then assimilates

meta-information about the FCL file into an opaque internal data structure and populates ***handle* with a pointer.

Just like the `lseek(2)` and `read(2)` system calls, the FCL file ***handle* has an internal offset to indicate the position in the file from where the next read starts. When the FCL file is successfully opened, this offset is set to the first valid offset in the FCL file.

Return value

Upon successful completion, a “0” is returned to the caller and the handle is non-NULL. Otherwise, the API returns a non-zero value and the handle is set to NULL. The global value `errno` is also set to indicate the error.

vxfs_fcl_close

`vxfs_fcl_close` closes the FCL file referenced by handle. All data structures allocated with this handle are cleaned. You should not use this handle after a call to `vxfs_fcl_close`.

Parameters

```
void vxfs_fcl_close(void *handle)
```

**handle* is a valid handle returned by the previous call to `vxfs_fcl_open`.

vxfs_fcl_getinfo

```
int vxfs_fcl_getinfo(void *handle, struct fcl_info*fclinfo);
```

The `vxfs_fcl_getinfo()` function returns information about the FCL file in the FCL information structure pointed to by *fcl_info*. It obtains this information from the FCL superblock.

```
struct fcl_info {  
    uint32_tfcl_version;  
    uint32_tfcl_state;  
};
```

An intelligent application that is aware of the record types associated with each can decide from *fcl_version*, whether the FCL file contains the needed information. For instance, a Version 3 FCL file never contains access information along with an FCL record. If *fcl_state* is `FCLS_OFF`, the application can then infer that there are no records added to the FCL file due to file system activity.

Return values

A “0” indicates success; otherwise, the `errno` is set to error and a non-zero value is returned.

vxfs_fcl_read

This function lets the application read the actual file or directory change information recorded in the FCL as logical records. Each record returns a `struct fcl_record` type. `vxfs_fcl_read` lets the application specify a filter comprising a set of desired events.

Parameters

The following is the syntax for the `vxfs_fcl_read()` function:

```
int vxfs_fcl_read(void *hndl, char *buf, size_t *bufsz,
uint64_t eventmask, uint32_t *nentries);
```

Input

This function has the following input:

- *hndl* is a pointer returned by a previous call to `vxfs_fcl_open`
- *buf* is a pointer to a buffer of size at least *bufsz*
- *bufsz* specifies the buffer size
- *eventmask* is a bit-mask that specifies a set of events which is of interest to the application. It should be a “logical or” of a set of event masks specified in the `fcl.h` header. For example, if the *eventmask* is (`VX_FCL_CREATE_MASK` | `VX_FCL_UNLINK_MASK`), `vxfs_fcl_read` returns only file create and delete records.

If an application needs to read all of the record types, the application can specify a default *eventmask* mask as `FCL_ALL_V4_EVENTS`. This returns all valid Version 4 FCL records in the FCL file.

See [Table 2-1](#) on page 22.

Note: If `VX_FCL_EVENTMASKCHG_MASK` is set in *eventmask* and the records returned by `vxfs_fcl_read` contain a `VX_FCL_EVENTMASK_CHG` record, it is always the last record in the buffer. This lets the application to readjust the *eventmask* if required. In addition, if the application discovers from the *eventmask* change record that a particular event is no longer recorded, it can decide to stop further reading.

- **nentries* specifies the number of entries that should be read into the buffer in this call to `vxfs_fcl_read`. If **nentries* is “0,” `vxfs_fcl_read` reads as many entries as will fit in the buffer.

Output

**buf* contains **nentries* FCL records of the `struct fcl_record` type if there is no error.

If the requested number of entries cannot fit in a buffer of the passed size, an `FCL_ENOSPC` error is returned. In this case, **bufsz* is updated to contain the buffer size required for the requested number of records. The application may use this to reallocate a larger sized buffer and invoke `vxfs_fcl_read` again. **bufsz* is not changed if there is no error.

**nentries* is updated to contain the number of entries read in the buffer when `vxfs_fcl_read` is called and there is no error. **nentries* and the returned value are both zero when the application has reached the end of file and there are no more records to be read.

Return values

A “0” indicates success; a non-zero indicates an error.

Note: `FCL_ENOSPC` is returned if there is not enough space in the buffer to store the current record. The minimum size the buffer must be is returned in **bufsz*.

After a successful call to `vxfs_fcl_read`, the current file position is advanced, so that the next call to `vxfs_fcl_read` reads the next set of records.

vxfs_fcl_getcookie

The `vxfs_fcl_getcookie` and `vxfs_fcl_seek()` functions are effective methods for remembering a position in the FCL file that the application has processed earlier. This then can be used as a restarting point. This is a highly useful tool for applications.

See “[vxfs_fcl_seek](#)” on page 33.

The `vxfs_fcl_getcookie()` function returns an opaque `fcl_cookie` structure which embeds information comprising the current activation time of the FCL file and an offset indicating the current position in the FCL file. This cookie can be passed into `vxfs_fcl_seek` to seek to the position in the FCL file defined by the cookie.

A typical incremental backup or index-update program can read to the end of the FCL file and perform actions based on the FCL records. The application can get information about the current position in the FCL file using `vxfs_fcl_getcookie` and then store the cookie in a persistent structure such as a file. The next time the application needs to perform an incremental operation, it reads the cookie and passes it to `vxfs_fcl_seek` to seek to the point where it left off. This enables the application to read only the new FCL records.

Parameters

The following is the syntax for the `vxfs_fcl_getcookie()` function:

```
int vxfs_fcl_getcookie(void *handle, struct fcl_cookie *cookie)
```

The function parameters are as follows:

- *handle* is the FCL file handle returned by a call to `vxfs_fcl_open`
- *cookie* is a pointer to an opaque data block defined as follows:

```
struct fcl_cookie {  
    char    fc_bytes[24];  
};
```

The data stored in the cookie is internal to the VxFS library. The application should not assume any internal representation for the cookie or tamper with the data in the cookie.

vxfs_fcl_seek

You can use `vxfs_fcl_seek` to seek to the start or end of an FCL file depending on the flag passed to it.

See “[vxfs_fcl_getcookie](#)” on page 32.

Parameters

The following is the syntax for the `vxfs_fcl_seek()` function:

```
int vxfs_fcl_seek(void *handle, struct fcl_cookie *cookie, int where)
```

The function parameters are as follows:

- The *handle* parameter should be the same handle that was returned by the most recent call to `vxfs_fcl_open()`. This is not necessarily the same handle used in `vxfs_fcl_getcookie()`. The application may open the FCL file, get the cookie, and close the FCL file in one session, and then open the FCL file and

submit the saved cookie in a later session. For each open session on the FCL file, the valid handle is the one returned by `vxfs_fcl_open()` for that session.

- The **cookie* parameter should point to a valid cookie that has been returned from a call to `vxfs_fcl_getcookie()` on the same FCL file or one of its checkpoints or one of the dumped or restored copies of the same FCL file. It is the responsibility of the user application to decide which FCL file is valid for a particular cookie and to use them in a sensible combination.

Note: The **cookie* parameter may be NULL if *where* has a value of `FCL_SEEK_SET` or `FCL_SEEK_END`.

- The *where* parameter should have a value of `FCL_SEEK_SET`, `FCL_SEEK_END`, or `FCL_SEEK_COOKIE`.

- If *where* is `FCL_SEEK_SET` or `FCL_SEEK_END`, the **cookie* parameter is ignored and `vxfs_fcl_seek()` seeks to either the start or end of the FCL file respectively, that is, where the first FCL record starts or where the last record ends.

- If *where* has a value of `FCL_SEEK_COOKIE`, `vxfs_fcl_seek()` extracts the activation time and offset stored in the **cookie* parameter.

If the FCL has been deactivated (switched off) from the time the application last called the `vxfs_fcl_getcookie()` function, or if the record at the offset contained in the **cookie* was purged by a hole-punch, `vxfs_fcl_seek()` returns an `FCL_EMISSEDRECORD` error. If not, `vxfs_fcl_seek` then sets the current file position to the offset contained in the cookie. Further calls to `vxfs_fcl_read()` return records from this offset.

Return values

A "0" indicates success; a non-zero indicates an error.

Note: `vxfs_fcl_seek()` returns `FCL_EMISSEDRECORD` if the FCL has been reactivated, that is, the activation time in FCL is different than that passed in the cookie, or the first valid offset in the FCL file is greater than the offset present in the cookie.

vxfs_fcl_seektime

The `vxfs_fcl_seektime()` function seeks to the first record in the FCL file that has a timestamp greater than or equal to the specified time.

Parameters

The following is the syntax for the `vxfs_fcl_seektime()` function:

```
int vxfs_fcl_seektime(void *handle, struct fcl_timeval time)
```

The function parameters are as follows:

- *handle* is a valid handle returned by a previous call to `vxfs_fcl_open`
- *time* is an `fcl_time_t` structure type defined as follows:

```
struct fcl_time {  
    uint32_t tv_sec;  
    uint32_t tv_nsec;  
} fcl_time_t;
```

Note: The time specified in `fcl_time_t` is in seconds or nanoseconds, while the time that is returned by a standard system call such as `gettimeofday` may be in seconds or microseconds. Therefore, a conversion may be needed.

`vxfs_fcl_seektime` assumes that the entries in the FCL are in a non-decreasing order of the time-stamps and does a faster-than-linear (binary) search to determine the FCL record with a time-stamp greater than the specified time. This means that `vxfs_fcl_seektime` can seek to a different record when compared to a seek done through a linear search. As a result, the `vxfs_fcl_seektime` interface is not 100% reliable.

The time-stamps in the FCL might be out-of-order under the following circumstances:

- If the system time is modified
- If the FCL file is on a cluster-mounted file system and the times on the different nodes are out-of-sync

Warning: On a cluster file system, you must use a mechanism to keep the system clocks in sync (for example, Network Time Protocol—NTP), to help ensure that the `vxfs_fcl_seektime` interface is kept reasonably accurate.

Return values

`vxfs_fcl_seektime` returns "0" on success. If there are no records in the FCL file newer than the time indicated in the *time* parameter, `vxfs_fcl_seektime` returns `EINVAL`.

vxfs_fcl_sync

The `vxfs_fcl_sync()` function sets a synchronization point within the FCL file. This function is kept for backward compatibility.

Before the availability of the VxFS 5.0 API to access the FCL file, applications would typically call `vxfs_fcl_sync` to get the FCL to a stable state and set an offset in the FCL file to use as a reference point to stop reading. The application would then store the offset and use it to determine files changes since the last FCL read time. A `vxfs_fcl_sync()` call ensured that if a file had been written to or opened, there would be at least one corresponding write or open record in the FCL after the synchronization offset. This would happen even if the time specified by `fcl_winterval` or `fcl_ointerval` had not elapsed since the last record was written.

With FCL access API in the VxFS 5.0 and later releases, synchronization is done automatically when the FCL file is opened through `vxfs_fcl_open()`. The `vxfs_fcl_open()` function sets a synchronization point and determines a reference end offset internally.

Parameters

The following is the syntax for the `vxfs_fcl_sync()` function:

```
int vxfs_fcl_sync(char *fname, uint64_t *offp);
```

The function parameters are as follows:

- *fname* is a pointer to the FCL filename
- *offp* is the address of a 64-bit offset

`vxfs_fcl_sync` brings the FCL file to a stable state and updates *offp* with an offset that can be used by the application as a reference point.

File Change Log record

An application reads the FCL file through the `vxfs_fcl_read()` function.

`vxfs_fcl_read` performs the following tasks:

- Reads the data from the FCL file
- Assembles the data into `fcl_record` structures
- Fills the buffer passed in by the application with these records

Each `fcl_record` structure represents a logical event recorded in the FCL. It is defined as the following:

```

struct fcl_record {
    uint32_t  fr_reclen;           /* Record length */
    uint16_t  fr_op;              /* Operation type. */
    uint16_t  fr_unused1;         /* unused field */
    uint32_t  fr_acsinfovalid : 1; /* fr_acsinfo field valid */
    uint32_t  fr_newnmvalid : 1; /* fr_newfilename field is valid */
    uint32_t  fr_pinogenvalid : 1; /* fr_fr_pinogen field is valid */
    uint32_t  fr_unused2 : 29;    /* Future use */
    uint64_t  fr_inonum;          /* Inode Number. */
    uint32_t  fr_inogen;          /* Inode Generation Count. */
    fcl_time_t fr_time;           /* Time. */
    union fcl_vardata {
        char                *fv_cmdname;
        struct fcl_nminfo    fv_nm;
        struct fcl_iostats    *fv_stats;
        struct fcl_evmaskinfo fv_evmask;
    } fr_var;
    uint64_t      fr_tdino;        /* Target dir ino */
    char          *fr_newfilename; /* For rename */
    struct fcl_acsinfo *fr_acsinfo; /* Access Info */
};

struct fcl_nminfo {
    uint64_t fn_pinonum; /* Parent Inode Number. */
    uint32_t fn_pinogen; /* Parent Inode Gen cnt. */
    char* fn_filename;
};

struct fcl_evmaskinfo {
    uint64_t toldmask; /* Old event mask. */
    uint64_t tnewmask; /* New event mask. */
};

```

Defines

These defines are provided for easier access:

```

#define fr_cmdname      fr_var.fv_cmdname
#define fr_stats        fr_var.fv_stats
#define fr_oldmask      fr_var.fv_evmask.oldmask
#define fr_newmask      fr_var.fv_evmask.newmask
#define fr_pinonum      fr_var.fv_nm.fn_pinonum
#define fr_pinogen      fr_var.fv_nm.fn_pinogen
#define fr_filename     fr_var.fv_nm.fn_filename

```

fcl_iostats structure

VxFS 5.0 and later releases let you gather statistics such as the number of reads and writes occurring on a file. You can enable this through the `fiostat` command. The gathered stats are maintained in a per-file in-core structure and the File Change Log acts as a persistent backing store for the statistics.

The stats are written to the FCL under the following circumstances:

- When the in-core structures need to be freed
- When the stats are reset
- At periodic intervals

These statistics can be read from the FCL as `VX_FCL_FILESTAT` records. Each record contains information as defined by the following `fcl_iostat` structure:

```
struct fcl_iostats {
    uint64_t nbytesread; /* Number of bytes read from the file*/
    uint64_t nbyteswrite; /* Number of bytes written to the file*/
    uint32_t nreads;      /* Number of reads from the file */
    uint32_t nwrites;     /* Number of writes to the file */
    uint32_t readtime;    /* Total time in seconds for the reads */
    uint32_t writetime;   /* Total time in seconds for the writes */
    struct {
        uint32_t tv_sec;
        uint32_t tv_nsec;
    } lastreset; /* Last reset time for the stats */
    uint32_t nodeid; /* Node from which the record was written */
    uint32_t treset; /* Stats have been written due to a reset */
};
```

Each iostat record in the FCL contains I/O statistics accumulated over the time interval from the *lastreset* time to when the FCL record is written.

Over a period of time, the cumulative statistics and aggregate can be computed by the following:

- Traversing the FCL
- Looking for records of type `VX_FCL_FILESTATS`

For example, computing the aggregate for the total number of reads over a period of time requires traversing a set of FCL files to obtain I/O statistics records. This information contains a sequence of records of the type `VX_FCL_FILESTATS` with the same *lastreset* time followed by another sequence of records with a later *lastreset* time for a specific file.

The aggregation considers values only from the latest record from records with the same *lastreset* time and then sums up the number of reads for each such record.

fcl_acsinfo structure

When tracking access-info is enabled, VxFS logs the access information such as:

- The real and effective user and group ID of the accessing application
- The node from where the file was accessed
- The process id of the user application along with each record

When the application reads the FCL, the information is returned in the *fr_acsinfo* field.

The *fr_acsinfo* points to an *FCL_acsinfo* structure, defined as follows:


```
struct fcl_acsinfo {  
    uint32_tfa_ruid;  
    uint32_tfa_rgid;  
    uint32_tfa_euid;  
    uint32_tfa_egid;  
    uint32_tfa_pid;  
    uint32_tfa_nodeid;  
};
```

Note: The *accessinfo* is not returned as a separate record type but as additional information along with the other records. In addition, the *accessinfo* information is not always present with every record (for example, when tracking *accessinfo* is not enabled). However, even when *accessinfo* is enabled in some file system internal operations (for example, truncating a file when it is removed), the access information may not be present. To help determine if access information is available, the FCL record contains a flag called *fcl_acsinfovalid* which is non-zero only if the *accessinfo* is present with a particular record.

Several of the fields in the *fcl_acsinfo* structure are pointers and need memory to store the actual contents. This is handled by storing the actual data immediately after the FCL record, and updating the pointer to point to the data. The record length *fr_reclen* field is updated to account for the whole data. Thus, each FCL record returned by *vxfs_fcl_read* is a variable size record, whose length is indicated by *fr_reclen_field*.

Figure 2-3 illustrates how the data is laid out in a sample link record.

Figure 2-3 Sample link record



The following code sample traverses the set of records returned by a call to `vxfs_fcl_read` and prints the user ID:

```

Struct fcl_record*fr;
Char          *tbuf;
...
    error = vxfs_fcl_read(fh, buf, &bufsz,
                          FCL_ALL_V4_EVENTS,
                          &nentries);

    tbuf = buf;
    while (--nentries) {
        fr = (struct fcl_record *)tbuf;
        if (fr->fr_acsinfovalid) {
            printf("Uid %ld\n", fr->fr_acsinfo->uid;
        }

        tbuf += fr->fr_reclen;
    }
    
```

Note: `FCL_ALL_V4_EVENTS` are event masks.

See “[vxfs_fcl_read](#)” on page 31.

Record structure fields

[Table 2-2](#) briefly describes each field of the `fcl_record` structure and indicates the record types for which it is valid.

Table 2-2 FCL record structure fields

Field	Description	Validity
<code>fr_reclen</code>	Length of the FCL record. This includes length of the FCL record structure and length of the data stored immediately following the structure. This length should be used while traversing fcl records returned in the buffer by <code>vxfs_fcl_read</code> .	Valid for all records.
<code>fr_inonum</code>	The inode number of the file being changed. To generate the full path name of the changed object, the inode number and generation count (<code>fr_inogen</code>) can be used with <code>vxfs_inotopath_gen</code> .	Valid for all FCL records except when the record is <code>FCL_EVTMSK_CHG</code> . For event mask change the file is implicitly the FCL file.
<code>fr_op</code>	The operation for this FCL record. For example, creation, unlink, write, file attributes change, or other change. <code>fr_op</code> takes on one of the values for the record types listed in Table 2-1. Use this parameter to determine which fields of the FCL record are valid.	Valid for all records.
<code>fr_time</code>	The approximate time when the change was recorded in the FCL file. Use the <code>ctime()</code> call to interpret this field.	Valid for all records.

Table 2-2 FCL record structure fields (*continued*)

Field	Description	Validity
fr_inogen	The generation count of the changed file. The generation count in combination with the inode number (of the file) is passed to vxfs_inotopath_gen to provide the exact full path name of the object. Without the generation count, the returned path name can be a re-used inode.	Valid for all FCL records except for event mask changes and unlinks. For event mask changes, the inode number and generation count are implicit. For unlink, the generation count is not needed to get the filename via reverse name lookup, since it is already present with the record.
fr_pinonum fr_pinogen fr_filename	For FCL records like file remove or rename, where the directory entry is removed, the filename cannot be determined by reverse name lookup. Similarly in the case of link record, the filename cannot be determined unambiguously. Therefore in these cases, the filename, inode number, and generation count of the parent directory (containing the file being changed) is recorded. The parent directory inode (<i>fr_pinonum</i>) and generation count (<i>fr_pinogen</i>) can be used with the reverse name lookup API to identify the full path name of the parent directory. Adding the trailing filename yields the object's full name.	Valid when the FCL record is VX_FCL_UNLINK, VX_FCL_RENAME or VX_FCL_LINK. The unlink and rename; filename and the parent inode number; and generation count, contain information about the old file that was removed. For the link, they represent the new filename.
fr_cmdname	A short name of the command which opened the file represented by <i>fr_inonum</i> and <i>fr_inogen</i> .	Valid only when the FCL record is VX_FCL_FILEOPEN.

Table 2-2 FCL record structure fields (*continued*)

Field	Description	Validity
<code>fr_stats</code>	A pointer to an <code>FCL_iostat</code> record. The <code>fcl_iostat</code> record contains I/O statistics such as the number of reads / writes that happened on the file, average time for a read / write, etc. These point-in-time records can be used to compute the aggregate or average I/O statistics for a file over a period of time.	Valid only when the FCL record is <code>VX_FCL_FILESTATS</code> .
<code>fr_oldmask</code> <code>fr_newmask</code>	These fields contain the old and new event masks, respectively. Each event mask is a “logical or” of a set of masks defined in <code>fcl.h</code> .	Valid only when the FCL record is <code>VX_FCL_EVTMASK_CHG</code> .
<code>fr_acsinfo</code>	A pointer to an <code>FCL_acsinfo</code> structure. This structure contains information such as the user and group ID of the application that performed the particular operation, the process id and the ID of the accessing node.	Validity is determined by the <code>fcl_acsinfovalid</code> bit-field. It can potentially exist with all kinds of records. This is an optional field.

Copying File Change Log records

Each FCL record returned by `vxfs_fcl_read` is of variable size and consists of the `fcl_record` structure, followed by the additional data associated with the record. The pointers in the `fcl_record` structure point to the data stored after the `fcl_record` structure and the record length specifies the size of the variable sized record. However, making an in-core copy of the FCL record involves more than replicating `fr_reclen` bytes of data from the source to the copy.

A simple memory copy just copies over the pointers from the source record to the target record. This leaves the pointers in the target record pointing to data from the source. Eventually, this can cause problems when the memory for the source record is re-used or freed. The pointers in the replica must be modified to point to data in the target record. Therefore, to make an in-core copy of the FCL record, the application must use the `vxfs_fcl_copyrec()` function to copy and perform the pointer relocation. The user application must allocate the memory needed for the copy.

Index maintenance application

This sample application is for a system that maintains an index of all files in the file system to enable a fast search similar to the `locate` program in Linux. The system needs to update the index periodically, or as required with respect to the file changes since the last index update. The following lists the basic steps to perform and shows a sample call to the FCL API.

To prepare the application

- 1 Enable the FCL.

```
$ fcladm on mount_point
```

- 2 Tune `fcl_keeptime` and `fcl_maxalloc` to the required values.

```
$ vxtune fs -o fcl_keeptime=value mount_point  
$ vxtune fs -o fcl_maxalloc=value mount_point
```

To test the application

- 1 Open the FCL file.

```
$ vxfs_fcl_open(mount_point, 0, &fh);
```

- 2 Seek to the end.

```
$ vxfs_fcl_seek(fh, NULL, FCL_SEEK_END);
```

- 3 Get the cookie and store it in a file.

```
$ vxfs_fcl_getcookie(fh, &cookie)  
write(fd, cookie, sizeof(struct fcl_cookie));
```

- 4 Create the index.

To update the application

- 1 Open the FCL file.

```
$ vxfs_fcl_open(mount_point, 0, &fh);
```

- 2 Read the cookie and seek to the cookie.

```
$ read(fd, &cookie, sizeof(struct fcl_cookie))  
$ vxfs_fcl_seek(fh, cookie, FCL_SEEK_COOKIE)
```

- 3 Read the FCL file and update the index accordingly.

```
$ vxfs_fcl_read(fh, buf, BUFSZ, FCL_ALL_v4_EVENTS, &nentries)
```

- 4 Get the cookie and store it back in the file.

```
$ vxfs_fcl_getcookie(fh, &cookie)
$ write(fd, cookie, sizeof(struct fcl_cookie));
```

Computing a usage profile

This sample application computes the usage profile of a particular file, that is, the users who have accessed a particular file in the last hour.

Initial setup

This sample application needs additional information such as tracking file opens and access information, which are available only with FCL Version 4. Be sure to enable the correct FCL version.

The following steps perform the required initial setup.

To set up the application

- 1 Switch on the FCL with Version 4.

```
$ fcladm -o version=4 on mount_point
```

If this step fails, use `fcladm print` to check for an existing FCL Version 3 file. If present, remove it with `fcladm rm` and then try switching on FCL with Version 4.

In VxFS 5.0 and later releases, the default FCL version is 4. If there is no existing FCL file, the `fcladm on mount_point` command automatically creates a Version 4 FCL.

- 2 Enable tracking of access information, file-opens, and I/O statistics as needed.

```
$ fcladm set fileopen,accessinfo mount_point
```

- 3 Set tunables `fcl_keeptime`, `fcl_maxalloc`, and `fcl_ointerval` as required. For example:

```
$ vxtunefs fcl_ointerval=value mount_point
```

Sample steps

The following provides sample steps for possible application use.

Sample application setup

- 1 Open the FCL file.

```
vxfs_fcl_open(mount_point, 0, &fh);
```

- 2 Set up the time to perform the seek.
- 3 Get current time using `gettimeofday`.
- 4 Fabricate the `fcl_time_t` for the time an hour before.
- 5 Seek to the record in the FCL file at that time.

```
gettimeofday(&tm, NULL);
tm.sec -= 3600
vxfs_fcl_seektime(fh, tm);
```

- 6 Read the file with the appropriate event masks until the end of file is reached. The application is interested in only the file open records and the access information.
- 7 Check if the file inode number and generation count are same as the ones being sought for each FCL record.
- 8 Print information about the user who has accessed the file, if applicable.

```
vxfs_fcl_read(fh, buf, BUFSZ, VX_FCL_FILEOPEN_MASK |
\VX_FCL_ACCESSINFO_MASK, &nentries);
```

Off host processing

In some scenarios, a user application may choose to save the bandwidth of the actual production server and outsource the job of processing the FCL to a different system. For off-host processing, the FCL file needs to be shipped to the off-host system. Since the FCL file is not a regular file, a command such as `cp` or `ftp` does not work.

To be "shippable," the FCL file must first be dumped into a regular file using the `fcladm dump` command. The file can then be sent to the off-host system using normal file transfer programs. See the following example.

```
$ fcladm -s savefile dump mount_point$ rcp savefile offhost-path
```

On the off-host system, the FCL file must be then restored using the `restore` option through the `fcladm` command. Unlike the original FCL file, the restored file is a regular file.

```
$ fcladm -s savefile restore restorefile
```

The restored FCL file can be passed as an argument to `vxfs_fcl_open` for further use with the FCL API.

Warning: The reverse name lookup API does not work on the off-host system. The off-host processing mechanism should only be used when the application can work with the inode number and generation count, or when it has an independent method to determine the filenames from the inode number.

Veritas File System and File Change Log upgrade and downgrade

VxFS 4.1 supported only FCL Version 3. VxFS 5.0 and later releases support both FCL Version 3 and 4, with Version 4 as the default. When a system is upgraded from VxFS 4.1 to VxFS 5.0 or a later release, and the file system has FCL switched on, the existing Version 3 FCL files remains as is. VxFS 5.0 and later releases continue tracking file system changes in the Version 3 FCL exactly as it was done by VxFS 4.1.

A VxFS 4.1 application that directly accesses the FCL file using the `read(2)` system call can still continue to work in VxFS 5.0 and later releases, provided that the FCL file is Version 3. However, you must develop any new applications using the API. The API has support for both FCL Versions 3 and 4.

If a new application uses the record types that were added in the VxFS 5.0 release, such as file opens or access information, the FCL needs to be at Version 4.

If you are running applications that still read FCL Version 3 directly, you cannot upgrade to FCL Version 4 until those applications are rewritten to use the new API. The API can interpret both Version 3 and Version 4, so applications can be upgraded to use the API while Version 3 is still in effect.

Converting File Change Log version 3 files to version 4

To convert VCL Version 3 files to Version 4

- 1 Switch off the FCL.

```
$ fcladm off mount_point
```

- 2 Remove the existing FCL file.

```
$ fcladm rm mount_point
```

- 3 Re-activate with the required version.

```
$ fcladm [-oversion=4] on mount_point
```

Downgrading Veritas File System versions

In the future, the VxFS version on a particular system may need to be downgraded from a newer VxFS release to VxFS 5.0. This may happen when a file system is migrated from one operating system using the newer VxFS release to another using the VxFS 5.0 release. If the FCL file created by this future VxFS version is Version 3 or 4, it can then be used as is by the VxFS 5.0 installation. Changes will continue to be tracked in the same FCL.

However, if the FCL version is higher than 4, then the FCL can not be activated and the calls to the API functions fail. In this case, the existing FCL file needs to be removed using `fcladm rm` and re-activated with FCL Version 3 or 4.

Reverse path name lookup

The reverse path name lookup feature obtains the full path name of a file or directory from the inode number of that file or directory. The inode number is provided as an argument to the `vxfs_inotopath_gen` library function. See the `vxfs_inotopath_gen(3)` online manual page for more information.

The reverse path name lookup feature can be useful for a variety of applications including the following:

- Clients of the VxFS file change log feature
- Backup and restore utilities
- Replication products

Typically, these applications store information by inode numbers because a path name for a file or directory can be very long and the applications require an easy method to obtain a path name.

Inodes

An inode is a unique identification number for each file in a file system. An inode contains the data and metadata associated with that file, but does not include the filenames to which the inode corresponds. It is therefore relatively difficult to determine the name of a file from an inode number. The `ncheck` command provides a mechanism for obtaining a filename from an inode identifier by scanning each directory in the file system, but this process can take a long time. The VxFS reverse path name lookup feature obtains path names relatively quickly.

Note: Because symbolic links do not constitute a path to the file, the reverse path name lookup feature cannot track symbolic links to files.

A file inode number, generation count, and, in the case of a `VX_FCL_LINK`, `VX_FCL_UNLINK`, or `VX_FCL_RENAME` record, trailing filename, when combined with the use of reverse path name lookup, can generate full path names for each FCL record.

`vxfs_inotopath_gen`

The `vxfs_inotopath_gen()` function takes a mount point name, inode number, and inode generation count and returns a buffer that contains one or more (in the case of multiple links to an inode) full path names representing the inode. The inode generation count parameter ensures that the returned path name is not a false value of a re-used inode. Because of this, use the `vxfs_inotopath_gen()` function whenever possible.

The `vxfs_inotopath()` function is included only for backward compatibility. The `vxfs_inotopath()` function does not take the inode generation count.

The following is the syntax for `vxfs_inotopath` and `vxfs_inotopath_gen`:

```
int vxfs_inotopath(char *mount_point, uint64_t inode_number,
                  int all, char ***bufp, int *inentries)
int vxfs_inotopath_gen(char *mnt_pt, uint64_t inode_number,
                      uint32_t inode_generation, int all,
                      char ***bufp, int *nentries)
```

For the `vxfs_inotopath()` call, the `all` argument must be “0” to obtain a single path name or “1” to obtain all path names. The `mount_point` argument specifies the file system mount point. Upon successful return, `bufp` points to a two-dimensional character pointer containing the path names and `nentries` contains the number of entries. Each entry of the returned two-dimensional array is `MAXPATHLEN` in size and must be freed, along with the array itself, by the calling application.

The `vxfs_inotopath_gen()` call is identical to the `vxfs_inotopath()` call, except that it uses an additional parameter, `inode_generation`. The `vxfs_inotopath_gen()` function returns one or more path names associated with the given inode number, if the `inode_generation` passed matches the current generation of the inode number. If the generations differ, it returns an error. Specify `inode_generation=0` when the generation count is unknown. This is equivalent to using the `vxfs_inotopath()` call.

The `vxfs_inotopath_gen()` and `vxfs_inotopath()` calls are supported only on Version 6 and later disk layouts.

Multi-volume support

This chapter includes the following topics:

- [About multi-volume support](#)
- [Uses for multi-volume support](#)
- [Volume application programming interfaces](#)
- [Allocation policy application programming interfaces](#)
- [Data structures](#)
- [Using policies and application programming interfaces](#)

About multi-volume support

The multi-volume support (MVS) feature lets a VxFS file system use multiple VxVM volumes as underlying storage instead of the traditional single volume per file system. These different volumes can have different characteristics, such as performance, redundancy, or cost, or they could be used to isolate different parts of the file system from each other for performance or administrative purposes.

Administrators and applications can control which files and metadata go into which volumes by using allocation policies. Each file system operation that allocates space examines the applicable allocation policies to see which volumes are specified for that operation. Allocation policies normally only affect new allocations, but there are also interfaces to move existing data to match a new allocation policy.

The following levels of policies can apply to each allocation:

- Per-file policies
- Per-Storage Checkpoint policies

- Per-file-system policies

The most specific allocation policy in effect for a given allocation operation is used.

The MVS APIs fall into the following basic categories:

- Manipulation of volumes within a file system
- Manipulation of allocation policy definitions
- Application of allocation policies

Each of the APIs is also available via options to the `fsvoladm(1M)` and `fsapadm(1M)` commands.

See the `fsvoladm(1M)` and `fsapadm(1M)` manual pages.

Uses for multi-volume support

Possible uses for the multi-volume support feature include the following:

- Controlling where files are stored so that specific files or file hierarchies can be assigned to different volumes
- Placing the VxFS intent log on its own volume to minimize disk head movement and thereby increase performance. This functionality can be used to migrate from the VERITAS QuickLog™ feature.
- Separating Storage Checkpoints so that data allocated to a Storage Checkpoint is isolated from the rest of the file system
- Separating file system metadata from file data
- Encapsulating volumes so that a volume appears in the file system as a file; this is particularly useful for databases that are running on raw volumes
- Migrating files off a volume so that the volume can be replaced or serviced
- Implementing a storage optimization application that periodically scans the file system and modifies the allocation policies in response to changing patterns of storage use

Volume application programming interfaces

The volume APIs can be used to add volumes to a file system, remove volumes from a file system, list which volumes are in a file system, and retrieve information on usage and availability of space in a volume.

Multi-volume file systems can only be used with VxVM volume sets. Volume sets are administered via the `vxvset` command.

See the *Veritas Volume Manager Administrator's Guide*.

Administering volume sets

The following examples show how to administer volume sets.

To convert a volume to a volume set

- To convert `myvol1` to a volume set, use the following function call:

```
# vxvset make myvset myvol1
```

To add a volume to a volume set

- To add `myvol2` to the volume set `myvset`, use the following function call:

```
# vxvset addvol myvset myvol2
```

To list volumes of a volume set

- To list the volumes of `myvset`, use the following function call:

```
# vxvset list myvset
```

To remove a volume from a volume set

- To remove `myvol2` from `myvset`, use the following function call:

```
# vxvset rmvol myvset myvol2
```

Querying the volume set for a file system

The following function calls query a volume set for a file system.

To query all volumes associated with the file system

- To query all volumes associated with the file system, use the following function call:

```
vxfs_vol_enumerate(fd, &count, infop);
```

To query a single volume

- To query a single volume, use the following function call:

```
vxfs_vol_stat(fd, vol_name, infop);
```

Modifying a volume within a file system

The following function calls modify a volume within a file system.

To grow or shrink a volume

- To grow or shrink a volume, use the following function call:

```
vxfs_vol_resize(fd, vol_name, new_vol_size);
```

To remove a volume from a file system

- To remove a volume from a file system, use the following function call:

```
vxfs_vol_remove(fd, vol_name);
```

Add a volume to a file system

- To add a volume to a file system, use the following function call:

```
vxfs_vol_add(fd, new_vol_name, new_vol_size);
```

Encapsulationg and de-encapsulating a volume

The following function calls encapsulate a volume.

To encapsulate a raw volume

- To encapsulate an existing raw volume and make the volume contents appear as a file in the file system, use the following function call:

```
vxfs_vol_encapsulate(encapsulate_name, vol_name, vol_size);
```

To de-encapsulate a raw volume

- To de-encapsulate an existing raw volume to remove the file from the file system, use the following function call:

```
vxfs_vol_deencapsulate(encapsulate_name);
```

See the *Veritas File System Administrator's Guide*.

Allocation policy application programming interfaces

To make full use of multi-volume support features, VxFS supports allocation policies that allow files or groups of files to be assigned to specified volumes within the volume set.

An allocation policy specifies a list of volumes and the order in which to attempt allocations. A policy can be assigned to a file, file system, or Storage Checkpoint created from a file system. When policies are assigned to objects in the file system, you must specify how the policy maps to both metadata and file data. For example, if a policy is assigned to a single file, the file system must know where to place both the file data and metadata. If no policies are specified, the file system places data randomly.


The allocation policies are defined per file system and are persistent. There is no fixed limit on the number of allocation policy definitions in a file system. Once a policy is assigned, new file allocations are governed by the policy. For files allocated before a policy was defined or assigned or when a policy on a file has been changed, the policy can be enforced, causing the file to be re-allocated to the appropriate volumes. Allocation policies can be inherited by a newly created file from its parent directory. This is accomplished by specifying the `FSAP_INHERIT` flag when assigning the policy to the parent directory.

Currently, there is no interface for determining where an existing file is currently allocated. However, these APIs can be used to assign and enforce a policy on a file to assure that the blocks are allocated properly.

Directing file allocations

[Figure 3-1](#) shows how you might use the allocation policies to direct file allocations.

Figure 3-1 Directing File Allocations



The `/mnt` file system has 3 volumes in its volume set: `vol-01`, `vol-02`, and `vol-03`. These volumes correspond to `policy1`, `policy2`, and `policy3`, respectively.

The file system has a policy assignment that allocates data as directed by `policy1` and metadata as directed by `policy2`. These policies cause files to be allocated on

`vol-01` and `vol-02`, except for `dir1`, which has overriding assignments for allocation on `vol-03`.

When the `file3` and `file4` files are created, they are allocated on `vol-02` as directed by the `policy1` and `policy2` assignments. When `file1` and `file2` are created, they are allocated on `vol-03`, as specified by `policy3`.

When `file4` is created, the initial allocation is on `vol-01` and `vol-02`. To move `file4` to `vol-03`, assign `policy3` to `file4` and enforce that policy on the file. This reallocates `file4` to `vol-03`.

To direct file allocations

- 1 Create the allocation policies on the `/mnt` file system.
- 2 Assign the data and metadata allocation policies to the `/mnt` file system as `policy1` and `policy2`.
- 3 Assign the data and metadata allocation policies to `dir1` with the `INHERIT` flag, with both as `policy3`.
- 4 Create `file4` (100MB), which becomes allocated to `vol-02`.
- 5 Create `file3` (10MB), which becomes allocated to `vol-02`.
- 6 Create `file2` (100MB), which becomes allocated to `vol-03`.
- 7 Create `file1` (100MB), which becomes allocated to `vol-03`.
- 8 Assign the data and metadata allocation policies to `file4`, with both as `policy3`.
- 9 Enforce the allocation policies on `file4`, which reallocates the file to `vol-03`.

Creating and assigning policies

The following function calls create and assign a policy using the multi-volume API.

- To define a policy for a file system, use the following function call:

```
vxfs_ap_define(fd, fsap_info_ptr, 0);
```

- To assign a policy to a file system, use the following function call:

```
vxfs_ap_assign_fs(fd, data_policy, meta_policy);
```

- To assign a policy to a file or directory, use the following function call:

```
vxfs_ap_assign_file(fd, data_policy, meta_policy, 0);
```


- To assign a policy to a Storage Checkpoint, use the following function call:

```
vxfs_ap_assign_ckpt(fd, checkpoint_name, data_policy, meta_policy);
```

- To assign a policy to all Storage Checkpoints, use the following function call:

```
vxfs_ap_assign_ckptchain(fd, data_policy, meta_policy);
```

- To set the default allocation policies for newly created Storage Checkpoints, use the following function call:

```
vxfs_ap_assign_ckptdef(fd, data_policy, meta_policy);
```

Querying the defined policies

The following function calls query defined policies.

- To query all policies on a file system, use the following function call:

```
vxfs_ap_enumerate(fd, &count, fsap_info_ptr);
```

- To query a single defined policy, use the following function call:

```
vxfs_ap_query(fd, fsap_info_ptr);
```

- To query a file for its assigned policies, use the following function call:

```
vxfs_ap_query_file(fd, data_policy, meta_policy, 0);
```

- To query a Storage Checkpoint for its assigned policies, use the following function call:

```
vxfs_ap_query_ckpt(fd, check_point_name, data_policy, meta_policy);
```

- To query a file system for its assigned policies, use the following function call:

```
vxfs_ap_query(fd, data_policy, meta_policy);
```

- To query a file system for the default Storage Checkpoint policies, use the following function call:

```
vxfs_ap_query_ckptdef(fd, data_policy, meta_policy);
```

Enforcing a policy

The following function calls enforce a policy.

- To enforce a policy on a file, use the following function call:

```
vxfs_ap_enforce_file(fd, data_policy, meta_policy);
```

Enforcing the policy may cause the file to be reallocated to another volume.

- To enforce a policy on all files in a Storage Checkpoint, use the following function call:

```
vxfs_ap_enforce_ckpt(fd, check_point_name, data_policy, meta_policy, flags);
```

- To enforce a policy on a primary fileset and all of the fileset's Storage Checkpoint, use the following function call:

```
vxfs_ap_enforce_ckptchain(fd, data_policy, meta_policy, flags);
```

Data structures

You can view the `fsap_info` and `fsdev_info` data structures in the `vxfsutil.h` header file and `libvxfsutil.a` library file.

See the `vxfsutil.h` header file and `libvxfsutil.a` library file.

The data structures are provided here for quick reference:

```
#define FSAP_NAMESZ          64
#define FSAP_MAXDEVS         256
#define FSDEV_NAMESZ        32
struct fsap_info {           /* policy structure */
    char ap_name[FSAP_NAMESZ]; /* policy name */
    uint32_t ap_flags;         /* FSAP_CREATE | FSAP_INHERIT |
                               FSAP_ANYUSER */
    uint32_t ap_order;         /* FSAP_ORDER_ASGIVEN |
                               FSAP_ORDER_LEASTFULL |
                               FSAP_ORDER_ROUNDROBIN */
    uint32_t ap_ndevs;         /* number of volumes */
    char ap_devs[FSAP_MAXDEVS][FSDEV_NAMESZ];
                               /* volume names associated with
                               this policy */
};
struct fsdev_info {          /* volume structure */
    int dev_id;              /* a number from 0 to n */
};
```

```

uint64_t dev_size;           /* size in bytes of volume */
uint64_t dev_free;
uint64_t dev_avail;
char dev_name[FSDEV_NAMESZ]; /* volume name */
};

```

Using policies and application programming interfaces

The following examples assume there is a volume set, `volset`, with the volumes `vol-01`, `vol-02`, and `vol-03`. The file system mount point `/mnt` is mounted on `volset`.

Defining and assigning allocation policies

The following pseudocode provides an example of using the allocation policy APIs to define and assign allocation policies.

To define and assign an allocation policy to reallocate an existing file's data blocks to a specific volume

- To reallocate an existing file's data blocks to a specific volume (`vol-03`), create code similar to the following:

```

/* Create a data policy for moving file's data */
strcpy((char *) ap.ap_name, "Data_Mover_Policy");
ap.ap_flags = FSAP_CREATE;
ap.ap_order = FSAP_ORDER_ASGIVEN;
ap.ap_ndevs = 1;
strcpy(ap.ap_devs[0], "vol-03");
fd = open("/mnt", O_RDONLY);
vxfs_ap_define(fd, &ap, 0);
file_fd = open ("/mnt/file_to_move", O_RDONLY);
vxfs_ap_assign_file(file_fd, "Data_Mover_Policy", NULL, 0);
vxfs_ap_enforce_file(file_fd, "Data_Mover_Policy", NULL);

```

To create policies that allocate new files under a directory

In this example, the files are under `dir1`, the metadata is allocated to `vol-01`, and file data is allocated to `vol-02`.

- To create policies to allocate new files under directory `dir1`, create code similar to the following:

```

/* Define 2 policies */
/* Create the RAID5 policy */
strcpy((char *) ap.ap_name, "RAID5_Policy");
ap.ap_flags = FSAP_CREATE | FSAP_INHERIT;
ap.ap_order = FSAP_ORDER_ASGIVEN;
ap.ap_ndevs = 1;
strcpy(ap.ap_devs[0], "vol-02");
fd = open("/mnt", O_RDONLY);
dir_fd = open("/mnt/dir1", O_RDONLY);
vxfs_ap_define(fd, &ap, 0);
/* Create the mirror policy */
strcpy((char *) ap.ap_name, "Mirror_Policy");
ap.ap_flags = FSAP_CREATE | FSAP_INHERIT;
ap.ap_order = FSAP_ORDER_ASGIVEN;
ap.ap_ndevs = 1;
strcpy(ap.ap_devs[0], "vol-01");
vxfs_ap_define(fd, &ap, 0);
/* Assign policies to the directory */
vxfs_ap_assign_file(dir_fd, "RAID5_Policy", "Mirror_Policy",
                    0);
/* Create file under directory dir1 */
/* Meta and data blocks for file1 will be allocated on
   vol-01 and vol-02 respectively. */
file_fd = open("/mnt/dir1/file1");
write(file_fd, buf, 1024);

```

Using volume application programming interfaces

The following pseudocode provides an example of using the volume APIs.

To shrink or grow a volume within a file system

- 1 Use the `vxresize` command to grow the physical volume.
- 2 To use the `vxfs_vol_resize()` call to shrink or grow the file system, create codes similar to the following:

```

/* stat volume "vol-03" to get the size information */
fd = open("/mnt");
vxfs_vol_stat(fd, "vol-03", infop);
/* resize (shrink/grow) accordingly. This example shrinks
   the volume by half */
vxfs_vol_resize(fd, "vol-03", infop->dev_size / 2);

```

To encapsulate a raw volume as a file

- 1 Add the volume to the volume set.
- 2 To encapsulate a raw volume `vol-03` as a file named `encapsulate_name` in the file system `/mnt`, create code similar to the following:

```
/* Take the raw volume vol-03 and encapsulate it. The
   volume's contents will be accessible through the given
   path name. */
vxfs_vol_encapsulate("/mnt/encapsulate_name", "vol-03",
                    infop->dev_size);
/* Access to the volume is through writes and reads of file
   "/mnt/encapsulate_name" */
encap_fd = open("/mnt/encapsulate_name");
write(encap_fd, buf, 1024);
```

To de-encapsulate a raw volume

- To de-encapsulate the raw volume `vol-03` named `encapsulate_name` in the file system `/mnt`, create code similar to the following:

```
/* Use de-encapsulate to remove raw volume. After
   de-encapsulation, vol-03 is still part of volset, but is
   not an active part of the file system. */
vxfs_vol_deencapsulate("/mnt/encapsulate_name");
```


Named data streams

This chapter includes the following topics:


- [About named data streams](#)
- [Uses for named data streams](#)
- [Named data streams application programming interface](#)
- [Listing named data streams](#)
- [Namespace for named data streams](#)
- [Behavior changes in other system calls](#)
- [Querying named data streams](#)
- [Application programming interface](#)
- [Command reference](#)

About named data streams

Named data streams associate multiple data streams with a file. The default unnamed data stream can be accessed through the file descriptor returned by the `open()` function called on the file name. The other data streams are stored in an alternate name space associated with the file.

Note: Named data streams are also known as named attributes.

[Figure 4-1](#) illustrates the alternate namespace associated with a file.



The `file1` file has two named data streams: `data_stream_1` and `data_stream_2`.

Every file can have its own alternate namespace to store named data streams. The alternate namespace can be accessed through the named data stream APIs supported by VxFS.

Access to the named data stream can be done through a file descriptor using the named data stream library functions. Applications can open the named data stream to obtain a file descriptor and perform `read()`, `write()`, and `mmap()` operations using the file descriptor. These system calls work as though they are operating on a regular file. The named data streams of a file are stored in a hidden named data stream directory inode associated with the file. The hidden directory inode for the file can be accessed only through the named data stream application programming interface.

There are no VxFS-supplied administrative commands to use this feature. A VxFS API is provided for creating, reading, and writing the named data streams of a file.

Uses for named data streams

Named data streams allow applications to attach information to a file that appears to be hidden. An administrative program could use this to attach file usage information, backup information, and so on. An application could use this feature to hide or collect file attachments. For example, a multi-media document could have all text, audio clips, and video clips organized in one file rather than in several files. A document being reviewed by multiple people could have each person's comments attached to the file as a named data stream.

Named data streams application programming interface

The following standard system calls can manipulate named data streams:

<code>open()</code>	Opens a named data stream
<code>read()</code>	Reads a named data stream
<code>write()</code>	Writes a named data stream
<code>getdents()</code>	Reads directory entries and puts in a file system independent format
<code>mmap()</code>	Maps pages of memory
<code>readdir()</code>	Reads a directory

VxFS named data stream functionality is available through the following application programming interface functions:

<code>vxfs_nattr_open()</code>	Works similarly to the <code>open()</code> system call, except that the path is interpreted as a named data stream to a file descriptor. If the <code>vxfs_nattr_open()</code> operation completes successfully, the return value is the file descriptor associated with the named data stream. The file descriptor can be used by other input/output functions to refer to that named data stream. If the path of the named data stream is set to ".", the file descriptor returned points to the named data stream directory vnode.
--------------------------------	---

The following is the syntax for the `vxfs_nattr_open()` API:

```
int vxfs_nattr_open(int fd, char *path,
                    int oflag, int cmode);
```

<code>vxfs_nattr_link()</code>	Creates a new directory entry for the existing named data stream and increments its link count by one. There is a pointer to an existing named data stream in the named data stream namespace and a pointer to the new directory entry created in the named data stream namespace. The calling function must have write permission to link the named data stream.
--------------------------------	---

The following is the syntax for the `vxfs_nattr_link()` API:

```
int vxfs_nattr_link(int sfd, char *spath,
                    char *tpath);
```

`vxfs_nattr_unlink()` Removes the named data stream at a specified path. The calling function must have write permission to remove the directory entry for the named data stream.

The following is the syntax for the `vxfs_nattr_unlink()` API:

```
int vxfs_nattr_unlink(int fd, char *path);
```

`vxfs_nattr_rename()` Changes a specified namespace entry at `path1` to a second specified namespace at `path2`. The specified paths are resolved relative to a pointer to the named data stream directory vnodes.

The following is the syntax for the `vxfs_nattr_rename()` API:

```
int vxfs_nattr_rename(int sfd, char *old,
                      char *tnew);
```

`vxfs_nattr_utimes()` Sets the access and modification times of the named data stream.

The following is the syntax for the `vxfs_nattr_utimes()` API:

```
int vxfs_nattr_utimes(int sfd,
                      const char *path,
                      const struct timeval times[2]);
```

See the `vxfs_nattr_open(3)`, `vxfs_nattr_link(3)`, `vxfs_nattr_unlink(3)`, `vxfs_nattr_rename(3)`, and `vxfs_nattr_utimes(3)` manual pages.

Listing named data streams

The named data streams for a file can be listed by calling `getdents()` on the named data stream directory inode, as shown in the following example.

To list named data streams

- 1 To list the named data streams, create code similar to the following:

```
fd = open("foo", O_RDWR); /* open file foo */
afd = vxfs_nattr_open(fd, "stream1",
                      O_RDWR|O_CREAT, 0777);/* create named data stream
                                           stream1 for file foo */
write(afd, buf, 1024);      /* writes to named stream file */
read(afd, buf, 1024);      /* reads from named stream file */
dfd = vxfs_nattr_open(fd, ".", O_RDONLY);
                               /* opens named stream directory
                               for file foo */
getdents(dfd, buf, 1024);/* reads directory entries for
                           named stream directory */
```

- 2 Use the reverse name lookup call to resolve a stream file to a pathname. The resulting pathname's format is similar to the following:

```
/mount_point/file_with_data_stream/./data_stream_file_name
```

Namespace for named data streams

Names starting with “\$vxfs:” are reserved for future use. Creating a data stream in which the name starts with “\$vxfs:” fails with an EINVAL error.

Behavior changes in other system calls

Although the named data stream directory is hidden from the namespace, it is possible to open the name data stream directory inode with a `fchdir()` or `fchroot()` call. Some of the attributes, such as “.”, are not defined for a named data streams directory. Any operation that accesses these fields can fail. Attempts to create directories, symbolic links, or device files on a named data stream directory fail. `VOP_SETATTR()` called on a named data stream directory or named data stream inode also fails.

The following is an alternative method for reading the hidden directory using the `fchdir()` call:

```
fd = open(filename, O_RDONLY)
dfd = vxfs_nattr_open(fd, ".", O_RDONLY, mode)
fchdir(dfd);
```

```
dirp = opendir(".");  
readdir_r(dirp, (struct dirent *)&entry, &result);
```

Note: The usage section of the `getcwd(3C)` man page states that applications should exercise care when using the `chdir()` call in conjunction with `getcwd()`. The current working directory is global to all threads within a process. If more than one thread calls `chdir()` to change the working directory, a subsequent call to `getcwd()` could produce unexpected results.

Querying named data streams

In the following example, a file `named_stream_file` was created with 20 named data streams using the API calls.

The named data streams are not displayed by the `ls` command. When named data streams are created, they are organized in a hidden directory. For example:

```
# ls -al named_stream_file  
-r-xr-lr-xl root  other   1024   Aug 12 09:49 named_stream_file
```

To query named data streams

- Use the `getdents()` or `readdir_r()` system call to query the `named_stream_file` file for its directory contents, which contains the 20 named stream files:

```
Attribute Directory contents for  
    /vxfstest1/named_stream_file  
0x1fff root other 1K Thu Aug 12 09:49:17 2004 .  
0x565 root other 1K Thu Aug 12 09:49:17 2004 ..  
0x177 root other 1K Thu Aug 12 09:49:17 2004 stream0  
0x177 root other 1K Thu Aug 12 09:49:17 2004 stream1  
0x177 root other 1K Thu Aug 12 09:49:17 2004 stream2  
.  
.  
.  
0x177 root other 1K Thu Aug 12 09:49:17 2004 stream17  
0x177 root other 1K Thu Aug 12 09:49:17 2004 stream18  
0x177 root other 1K Thu Aug 12 09:49:17 2004 stream19
```

Application programming interface

The named data streams API uses a combination of standard system calls and VxFS API calls to utilize its functionality.

The following is an example of pseudo code to query named data streams:

```
/* Create and open a file */
if ((fd = open("named_stream_file", O_RDWR | O_CREAT | O_TRUNC,
mode)) < 0) {
    sprintf(error_buf, "%s, Error Opening File %s ", argv[0],
filename);
    perror(error_buf);
    exit(-1);
}
/* Write to the regular file as usual */
write(fd, buf, 1024);
/* Create several named data streams for file
named_stream_file */
for (i = 0; i < 20; i++) {
    sprintf(attrname, "%s%d", "stream", i);
    nfd = vxfs_nattr_open(fd, attrname, O_WRONLY | O_CREAT,
mode);
    if (nfd < 0) {
        sprintf(error_buf,
"%s, Error Opening Attribute file %s/./%s ",
argv[0], filename, attrname);
        perror(error_buf);
        exit(-1);
    }
    /* Write some data to the stream file */
    memset(buf, 0x41 + i, 1024);
    write(nfd, buf, 1024);
    close(nfd);
}
```

Command reference

When you use the `cp`, `tar`, `ls` or similar commands to copy or list a file with named data streams, the file is copied or listed, but the attached named data streams are not copied or listed.

Veritas File System I/O

This chapter includes the following topics:

- [About Veritas File System I/O](#)
- [Freeze and thaw](#)
- [Caching advisories](#)
- [Extents](#)

About Veritas File System I/O

Veritas File System (VxFS) I/O controls the access of data on a VxFS file system. VxFS APIs are provided for freezing and thawing file systems, administering caching advisories, and administering extent attributes.

Note: Unlike the other VxFS APIs described in this document, the APIs described in this chapter are available in previous releases of VxFS on all platforms. The exception is the API that provides concurrent I/O access through the VxFS caching advisories, which is available on VxFS 4.1 and later releases.

Freeze and thaw

Freezing a file system temporarily blocks all I/O operations to a file system and then performs a sync on the file system. Current operations are completed and the file system is synchronized to disk. Freezing a file system is a necessary step for obtaining a stable and consistent image of the file system at the volume level.

Consistent volume-level file system images can be obtained and used with a file system snapshot tool. The freeze operation flushes all buffers and pages in the

file system cache that contain dirty metadata and user data. The operation then suspends any new activity on the file system until the file system is thawed.

VxFS provides ioctl interfaces to application programs to freeze and thaw VxFS file systems. The interfaces are `VX_FREEZE`, `VX_FREEZE_ALL`, and `VX_THAW`.

The `VX_FREEZE` ioctl operates on a single file system. The program performing this ioctl can freeze the specified file system and block any attempts to access the file system until it is thawed. The file system thaws after the timeout value that is specified with the `VX_FREEZE` ioctl has expired, or the `VX_THAW` ioctl is operated on the file system.

The `VX_THAW` ioctl operates on a frozen file system. It can be used to thaw the specified file system before the freeze timeout period has elapsed.

The `VX_FREEZE_ALL` ioctl interface freezes one or more file systems. The `VX_FREEZE_ALL` ioctl operates in an atomic fashion when there are multiple file systems specified with a freeze operation. VxFS blocks access to the specified file systems simultaneously and disallows a user-initiated write operation that may modify more than one file system with a single write operation. Because `VX_FREEZE_ALL` can be used with a single file system, `VX_FREEZE_ALL` is the preferred interface over the `VX_FREEZE` ioctl.

Executing the `VX_FREEZE` or `VX_FREEZE_ALL` ioctls results in a clean file system image that can be mounted after the image is split off from the file system device. In response to a freeze request, all modified file system metadata is flushed to disk with no pending file system transactions in the log that must be replayed before mounting the split off image.

Both the `VX_FREEZE` and `VX_FREEZE_ALL` interfaces can be used to freeze locally mounted file systems, or locally or remotely mounted cluster file systems.

The following table shows freeze/thaw compatibility with VxFS releases:

Table 5-1 Freeze/thaw compatibility with VxFS releases

	VxFS 3.5	VxFS 4.0	VxFS 4.1	VxFS 5.0 and later
VX_FREEZE	Local File System	Local File System	Local File System	Local File System
		Cluster File System	Cluster File System	Cluster File System

Table 5-1 Freeze/thaw compatibility with VxFS releases (*continued*)

	VxFS 3.5	VxFS 4.0	VxFS 4.1	VxFS 5.0 and later
VX_FREEZE_ALL	Local File System	Local File System	Local File System Cluster File System	Local File System Cluster File System

When freezing a file system, care should be taken with choosing a reasonable time-out value for the freeze to reduce impact to external resources targeting the file system. User or system processes and resources are blocked while the file system is frozen. If the specified timeout value is too large, resources are blocked for an extended period of time.

During a file system freeze, any attempt to get a file descriptor from the root directory of the file system for use with the `VX_THAW` ioctl causes the calling process to be blocked as the result of the frozen state of the file system. The file descriptor must be acquired before issuing the `VX_FREEZE_ALL` or `VX_FREEZE` ioctl.

Use the `VX_THAW` ioctl to thaw file systems that were frozen with the `VX_FREEZE_ALL` ioctl before the timeout period has expired.

The programming interface is as follows:

```
include <sys/fs/vx_ioctl.h>
int          timeout;
int          vxfs_fd;
/*
 * A common mistake is to pass the address of "timeout".
 * Do not pass the address of timeout, as that would be
 * interpreted as a very long timeout period
 */
if (ioctl(vxfs_fd, VX_FREEZE, timeout))
    {perror("ERROR: File system freeze failed");
}
```

For multiple file systems:

```
int          vxfs_fd[NUM_FILE_SYSTEMS];
struct       vx_freezeall freeze_info;
freeze_info.num = NUM_FILE_SYSTEMS
freeze_info.timeout = timeout;
freeze_info.fds = &vxfs_fd[0];
if (ioctl(vxfs_fd[0], VX_FREEZE_ALL, &freeze_info))
```

```
        {perror("ERROR: File system freeze failed");  
    }  
    for (i = 0; i < NUM_FILE_SYSTEMS; i++)  
        if (ioctl(vxfs_fd[i], VX_THAW, NULL))  
            {perror("ERROR: File system thaw failed");  
        }  
    }
```

Caching advisories

VxFS allows an application to set caching advisories for use when accessing files. A caching advisory is the application's preferred choice for accessing a file. The choice may be based on optimal performance that is achieved through the specified advisory or to ensure integrity of user data. For example, a database application may choose to access the files containing database data using direct I/O, or the application may choose to benefit from the file system level caching by selecting a buffered I/O advisory. The application chooses which caching advisory to use.

To set a caching advisory on a file, open the file first. When a caching advisory is requested, the advisory is recorded in memory. Recording the advisory in memory implies that caching advisories do not persist across reboots or remounts. Some advisories are maintained on a per-file basis, not a per-file-descriptor basis. As such, the effect of setting such an advisory through a file descriptor impacts other processes' access to the same file. Conflicting advisories also cannot be in effect for accesses to the same file. If two applications set different advisories, both applications use the last advisory that was set on the file. VxFS does not coordinate or prioritize advisories.

Some advisories are not cleared from memory after the last close of the file. Recorded advisories remain in memory for as long as the file system metadata used to manage access to the file remains in memory. Removing file system metadata for the file from memory is not predictable.

All advisories are set using the file descriptor, returned by the `open()` and `ioctl()` calls using the `VX_SETCACHE` `ioctl` command.

See the `vxfsio(7)` manual page.

The caching advisories are described in the following sections.

Direct I/O

Direct I/O is an unbuffered form of I/O for accessing files. If the `VX_DIRECT` advisory is set, the user requests direct data transfer between the disk and the user-supplied buffer for reads and writes. This bypasses the kernel buffering of data, and reduces the CPU overhead that is associated with I/O by eliminating the data copy between

the kernel buffer and the user's buffer. Direct I/O also avoids taking up space in the buffer cache that might be better used for something else, such as an application cache. The direct I/O feature can provide significant performance gains for some applications.

For an I/O operation to be performed as direct I/O, it must meet certain alignment criteria. The disk driver, the disk controller, and the system memory management hardware and software usually determine the alignment constraints. The file offset must be aligned on the block device block size. All user buffers must be aligned on a long or sector boundary. If the file offset is not aligned to sector boundaries, VxFS performs a regular read or write instead of a direct read or write.

If a request fails to meet the alignment constraints for direct I/O, the request is performed as data synchronous I/O. If the file is accessed by using memory mapped I/O, any direct I/O accesses are done as data synchronous I/O.

Because direct I/O maintains the same data integrity as synchronous I/O, it can be used in many applications that currently use synchronous I/O. If a direct I/O request does not allocate storage or extend the file, the inode metadata is not immediately written.

The CPU cost of direct I/O is about the same as a raw disk transfer. For sequential I/O to very large files, using direct I/O with large transfer sizes can provide the same speed as buffered I/O with much less CPU overhead.

If the file is extended or storage is allocated, direct I/O must write the inode change before returning to the application. This write eliminates some of the performance advantages of direct I/O.

The direct I/O advisory is maintained on a per-file-descriptor basis.

Concurrent I/O

Concurrent I/O (`VX_CONCURRENT`) is a form of I/O for file access. This form of I/O allows multiple processes to read or write to the same file without blocking other `read()` or `write()` operations. POSIX semantics requires `read()` and `write()` operations to be serialized on a file with other `read()` and `write()` operations. With POSIX semantics, a read will either read the data before or after the write occurs. With the `VX_CONCURRENT` advisory set on a file, the reads and writes are not serialized similar to character devices. Applications that require high performance for accessing data and do not perform overlapping writes to the same file generally use this advisory. An example is database applications. Such applications perform their own locking at the application level to avoid overlapping writes to the same region of the file.

It is the responsibility of the application or threads to coordinate write activities to the same file when using the `VX_CONCURRENT` advisory to avoid overlapping

writes. The consequence of two overlapping writes to the same file is unpredictable. The best practice for applications is to avoid simultaneous write operations to the same region of the same file.

If the `VX_CONCURRENT` advisory is set on a file, VxFS performs direct I/O for reads and writes to the file. As such, concurrent I/O has the same alignment requirements as direct I/O.

See [“Direct I/O”](#) on page 74.

When concurrent I/O is enabled, the read and write behaves as follows:

- The `write()` system call acquires a shared read-write lock instead of an exclusive lock.
- The `write()` system call performs direct I/O to the disk instead of copying and then writing the user data to the pages in the system page cache.
- The `read()` system call acquires a shared read-write lock and performs direct I/O from disk instead of reading the data into pages in the system page cache and copying from the pages to the user buffer.
- The `read()` and `write()` system calls are not atomic. The application must ensure that two threads do not write to the same region of a file at the same time.

Concurrent I/O (CIO) can be set through the file descriptor and `ioctl()` operation using the `VX_SETCACHE` `ioctl` command with the `VX_CONCURRENT` advisory flag. Only the `read()` and `write()` operations occurring through this file descriptor use concurrent I/O. `read()` and `write()` operations occurring through other file descriptors still follows the POSIX semantics. The `VX_CONCURRENT` advisory can be set by the `VX_SETCACHE` `ioctl` descriptor on a file.

CIO is a licensable feature of VxFS.

Unbuffered I/O

The I/O behavior of the `VX_UNBUFFERED` advisory is the same as the `VX_DIRECT` advisory set with the same alignment constraints as direct I/O. However, for unbuffered I/O, if the file is extended, or storage is allocated to the file, metadata updates on the disk for extending the file are not performed synchronously before the write returns to the user. The `VX_UNBUFFERED` advisory is maintained on a per-file-descriptor basis.

Other advisories

The `VX_SEQ` advisory is a per-file advisory that indicates that the file is accessed sequentially. A process setting this advisory on a file through its file descriptor

impacts the access pattern of other processes currently accessing the same file. When a file with the `VX_SEQ` advisory is read, the maximum read-ahead is performed. When a file with `VX_SEQ` advisory is written, sequential write access is assumed and the modified pages with write operations are not immediately flushed. Instead, modified pages remain in the system page cache and those pages are flushed at some distance point behind the current write point (flush behind).

The `VX_RANDOM` advisory is a per-file advisory that indicates that the file is accessed randomly. A process setting this advisory on a file through its file descriptor impacts the access pattern of other processes currently accessing the same file. This advisory disables read-ahead with read operations on the file, and disables flush-behind on the file. The result of disabling flush behind is that the modified pages in the system page cache from the recent write operations are not flushed to the disk until the system pager is scheduled and run to flush dirty pages. The rate at which the system pager is scheduled is based on availability of free memory and contention.

Note: The `VX_SEQ` and `VX_RANDOM` are mutually exclusive advisories.

Extents

In general disk space is allocated in 512-byte or 1024-byte (`DEV_BSIZE`) sectors to form logical blocks. VxFS supports logical block sizes of 1024, 2048, 4096, and 8192 bytes. The default block size is 1K for file systems up to 2 TB in size, and 8K for other file system sizes. Users can choose any block when creating file systems using the `mkfs` command. VxFS allocates disk space to files in groups of one or more adjacent blocks called extents. An extent is a set of one or more consecutive logical blocks. Extents allow disk I/O to take place in units of multiple blocks if storage is allocated in consecutive blocks. For sequential I/O, multiple block operations are considerably faster than block-at-a-time operations.

VxFS uses an aggressive allocation policy for allocating extents to files. It also allows an application to pre-allocate space or request contiguous space. This results in improved I/O performance and less file system overhead for performing allocations. For an extending write operation, the policy attempts to extend the previously allocated extent by the size of the write operation or larger. Larger allocation is attempted when consecutive extending write operations are detected. If the last extent cannot be extended to satisfy the entire write operation, a new disjoint extent is allocated. This policy leaves excess allocation that is trimmed at the last close of the file or if the file is not written to for some amount of time. The file system can still be fragmented with too many non-contiguous extents, especially file systems of smaller size.

Extent attributes

VxFS allocates disk space to files in groups of one or more extents. In general, the internal allocation policies of VxFS attempt to achieve two goals: allocate extents for optimum I/O performance and reduce fragmentation. VxFS allocation policies attempt to balance these two goals through large allocations and minimal file system fragmentation by allocating from space available in the file system that best fits the data. These extent-based allocation policies provide an advantage over block-based allocation policies. Extent based policies rarely use indirect blocks with allocations and eliminate many instances of disk access that stem from indirect references.

VxFS allows control over some aspects of the extent allocation policies for a given file by two administrative tools, `setext` and `getext`, and an API. The application-imposed policies that are associated with a file are referred to as extent attributes. VxFS provides APIs that allow an application to set or view extent attributes associated with a file and preallocate space for a file.

See the `setext(1)` and `getext(1)` manual pages

Attribute specifics

There are two extent attributes associated with a file: reservation and fixed extent size. You can preallocate space to the file by manipulating a file's reservation. You can also override the default allocation policy of the file system by setting a fixed extent size. Other policies determine the way these attributes are expressed during the allocation process.

You can specify the following:

- The space reserved for a file must be contiguous
- No allocations are made for a file beyond the current reservation
- An unused reservation is released when the file is closed
- Space is allocated, but no reservation is assigned
- The file size is changed to immediately incorporate the allocated space

Some of the extent attributes are persistent and become part of the on-disk information about the file, while other attributes are temporary and are lost after the file is closed or the system is rebooted. The persistent attributes are similar to the file's permissions and are written in the inode for the file. When a file is copied, moved, or archived, only the persistent attributes of the source file are preserved in the new file.

Reservation: preallocating space to a file

Space reservation is used to make sure applications do not fail because the file system is out of space. An application can preallocate space for all the files it needs before the application starts any work. By allocating space in advance, the file is optimally allocated for performance, and file accesses are not slowed down by the need to allocate storage. This allocation of resources can be important in applications that require a guaranteed response time. With very large files, use of space reservation can avoid the need to use indirect extents. It can also improve performance and reduce fragmentation by guaranteeing that the file consists of large contiguous extents.

VxFS provides an API to preallocate space to a file at the time of the request rather than when data is written into the file. Preallocation, or reservation, prevents any unexpected out-of-space condition on the file system by ensuring that a file's required space is associated with the file before data is written to the file. Storage can be reserved for a file at any time, and reserved space to a file is not allocated to other files in the file system. The API provides the application the option to change the size of the file to include the reserved space.

Reservation does not perform zeroing of the allocated blocks to the file. Therefore, this facility is limited to applications running with appropriate privileges, unless the size of the file is not changed with the reservation request. The data that appears in the newly allocated blocks for the file may have been previously contained in another file.

Reservation is a persistent attribute for the file that is saved on disk. When this attribute is set on a file, the attribute is not released when the file is truncated. The reservation must be cleared through the same API, or the file must be removed to free the reserved space. At the time of specifying the reservation, if the file size is less than the reservation amount, space is allocated to the file from the current file size up to the reservation amount. When the file is truncated, space below the reserved amount is not freed.

Fixed extent size

VxFS uses the I/O size of write requests and the default allocation policy for allocating space to a file. For some applications, the default allocation policy may not be optimal. Setting a fixed extent size on a file overrides the default allocation policies for that file. Applications can set a fixed extent size to match the application I/O size so that all new extents allocated to the file are of the fixed size. By using a fixed extent size, an application can reduce allocation attempts and guarantee optimal extent sizes for a file. With the fixed extent size attribute, an extending write operation will trigger VxFS to extend the previously allocated extent by the fixed extent size amount to maintain contiguity of the extent. If the

last extent cannot be extended by the fixed extent size amount, a new disjoint extent is allocated. The size of a fixed extent should factor in the size of file I/O appropriate to the application. Do not use small fixed extent size to eliminate the advantage with extent-base allocation policies.

Another use of a fixed extent size occurs with sparse files. VxFS usually performs I/O in multiples of the system-defined page size. When allocating to a sparse file, VxFS allocates space in multiples of the page size according to the amount of page I/O in need of allocation. If the application always does sub-page I/O, the use of fixed extent size in multiples of the page size reduces allocations.

Applications should not use a large fixed extent size. Allocating a large fixed extent may fail due to the unavailability of an extent of that size, whereas smaller extents are more readily available for allocation.

Custom applications may also use fixed extent sizes for specific reasons, such as the need to align extents to cylinder or striping boundaries on disk.

The fixed extent size attribute is specified in units of file system block size. The attribute specifies the number of contiguous file system blocks to allocate for a new extent, or the number of contiguous blocks to allocate and append to the end of an existing extent. A file with this attribute has fixed size extents or larger extents that are a multiple of the fixed size extent.

Application programming interface for extent attributes

The current API for extent attributes is `ioctl()`. Applications can open a file and use the returned file descriptor with calls to `ioctl()` to retrieve, set, or change extent attributes. To set or change existing extent attributes, use the `VX_SETEXT` `ioctl`. To retrieve existing extent attributes, if any, use the `VX_GETTEXT` `ioctl`.

Applications can set or change extent attributes on a file by providing the attribute information in the structure of type `vx_ext` and passing the `VX_SETEXT` `ioctl` and the address of the structure using the third argument of the `ioctl()` call.

Applications can also retrieve existing extent attributes, if any, by passing the `VX_GETTEXT` `ioctl` and the address of the same structure, of type `vx_ext`, as the third argument with the `ioctl()` call.

```
struct vx_ext {
    off_t    ext_size;    /* extent size in fs blocks */
    off_t    reserve;    /* space reservation in fs blocks */
    int      a_flags;    /* allocation flags */
}
```

The `ext_size` argument is set to specify a fixed extent size. The value of fixed extent size is specified in units of the file system block size. Be sure the file system block

size is known before setting the fixed extent size. If a fixed extent size is not required, use zero to allow the default allocation policy to be used for allocating extents. The fixed extent allocation policy takes effect immediately after successful execution of the `VX_SETTEXT` ioctl. An exception is with the files that already contain indirect blocks, in which case the fixed extent policy has no effect unless file truncation frees all current indirect blocks.

The *reserve* argument can be set to specify the amount of space preallocated to a file. The amount is specified in units of the file system block size. Be sure the file system block size is known before setting the preallocation amount. If a file has already been preallocated, its current reservation amount can be changed with the `VX_SETTEXT` ioctl. If the specified reserve amount is greater than the current reservation, the allocation for the file is increased to match the newly specified reserve amount. If the reserve amount is less than the current reservation, the reservation amount is decreased and the allocation is reduced to the newly set reservation amount or the current file size. File preallocation requires root privilege, unless the size of the file is not changed, and the preallocation size cannot be increased beyond the `ulimit` of the requesting process.

See the `VX_CHGSIZE` flag.

See the `ulimit(2)` manual page.

Allocation flags

Allocation flags can be specified with `VX_SETTEXT` ioctl for additional control over allocation policies.

Allocation flags are specified in the *a_flag* argument of `vx_ext` structure to determine the following:

- Whether allocations are aligned
- Whether allocations are contiguous
- Whether the file can be written beyond its reservation
- Whether an unused reservation is released when the file is closed
- Whether the reservation is a persistent attribute of the file
- When the space reserved for a file will actually become part of the file

Allocation flags with reservation

The `VX_TRIM`, `VX_NOEXTEND`, `VX_CHGSIZE`, `VX_NORESERVE`, `VX_CONTIGUOUS`, and `VX_GROWFILE` flags can be used to modify reservation requests. `VX_NOEXTEND` is the only flag that is persistent; the other flags may have persistent effects, but

the `VX_GETTEXT` ioctl does not return the flags. The non-persistent flags remain active for a file in the file system cache until the file is no longer accessed and is removed from the cache.

Reservation trimming

The `VX_TRIM` flag specifies that the reservation amount must be trimmed to match the file size when the last close occurs on the file. At the last close, the `VX_TRIM` flag is cleared and any unused reservation space beyond the size of the file is freed. This flag can be useful if an application needs enough space for a file, but it is not known how large the file will become. Enough space can be reserved to hold the largest expected file, and when the file has been written and closed, any extra space is released.

Non-persistent reservation

If you do not want reservation to be a persistent attribute, you can specify the `VX_NORESERVE` flag to request allocation of space without making reservation a persistent attribute of the file. Applications that are interested in temporary reservation but want to free any space past the end of the file when the file is closed case use this flag. For example, if an application is copying a file that is 1 MB long, it can request a 1 MB reservation with the `VX_NORESERVE` flag set. The space is allocated, but the reservation in the file is left at 0. If the program aborts for any reason or the system crashes, the unused space past the end of the file is released. When the program finishes, there is no clean up because the reservation was never recorded on disk.

No write beyond reservation

The `VX_NOEXTEND` flag specifies that any attempt to write beyond the current reservation must fail. Writing beyond the current reservation requires the allocation of new space for the file. To allocate new space to the file, the space reservation must be increased. This can be used similar to the function of the `ulimit` command to prevent a file from using too much space.

Contiguous reservation

The `VX_CONTIGUOUS` flag specifies that any space allocated to a file must satisfy the requirement of a single extent allocation. If there is not one extent large enough to satisfy the reservation request, the request fails. For example, if a file is created and a 1 MB contiguous reservation is requested, the file size is set to zero and the reservation to 1 MB. The file has one extent that is 1 MB long. If another reservation request is made for a 3 MB contiguous reservation, the new

request finds that the first 1 MB is already allocated and allocate a 2 MB extent to satisfy the request. If there are no 2 MB extents available, the request fails. Extents are, by definition, contiguous. Because `VX_CONTIGUOUS` is not a persistent flag, space is not allocated contiguously for restoring a file that was previously allocated with the `VX_CONTIGUOUS` flag.

Include reservation in the file size

A reservation request can affect the size of the file to include the reservation amount by specifying `VX_CHGFSIZE`. This flag increases the size of the file to match the reservation amount without zeroing the reserved space. Because the effect of this flag is uninitialized data in a file, which might have been previously contained in other files, the use of this flag is restricted to users with the appropriate privileges. Without this flag, the space of the reservation is not included in the file until an extending write operation requires the space. A reservation that immediately changes the file size can generate large temporary files. Applications can benefit from this type of reservation by eliminating the overhead that is imposed with write operations to allocate space and update the size of the file.

It is possible to use these flags in combination. For example, using `VX_CHGFSIZE` and `VX_NORESERVE` changes the file size, but does not set any reservation. When the file is truncated, the space is freed. If the `VX_NORESERVE` flag is not used, the reservation is set on the disk along with the file size.

Reading the grown part of the file

When the allocation flag (*a.flag*) is set to `VX_GROWFILE`, the size of the file is changed to include the reservation. This flag reads the "grown" part of the file (between the current size of the file and the size after the operation succeeds). `VX_GROWFILE` has persistent effects, but is not visible as an allocation flag. This flag is visible through the `VX_GETTEXT` ioctl.

Allocation flags with fixed extent size

The `VX_ALIGN` flag can be used to specify an allocation flag for fixed extent size. This flag has no effect if it is specified with a reservation request. The `VX_ALIGN` flag specifies the alignment requirement for allocating future extents that are aligned on a fixed extent size boundary relative to the start of the allocation unit. This flag can be used to align extents to disk striping boundaries or physical disk boundaries. The `VX_ALIGN` flag is persistent and the `VX_GETTEXT` ioctl returns the flag.

How to use extent attribute APIs

First, verify that the target file system is VxFS, and then determine the file system block size using the `statfs()` call. The type for VxFS is `MNT_VXFS` on most platforms, and the file system block size is returned in `statfs.f_bsize`. The block size must be known for setting or interpreting the extent attribute information through VxFS extent attribute APIs.

Each invocation of the `VX_SETEXT` ioctl affects all the elements in the `vx_ext` structure.

To use `VX_SETEXT`

- 1 Call the `VX_GETTEXT` ioctl to read the current settings, if any.
- 2 Modify the current values to be changed.
- 3 Call the `VX_SETEXT` ioctl to set the new values.

Warning: Follow this procedure carefully. A fixed extent size may be inadvertently cleared when the reservation is changed. When copying files between VxFS and non-VxFS file systems, the extent attributes cannot be preserved. The attribute values returned for a file in a `vx_ext` structure have a different effect on another VxFS file system with a different file system block size from the source file system. Translation of attribute values for different block sizes may be necessary when copying files with attributes between two file systems of a different block size.

Setting fixed extent size

The following is an example code snippet for setting the fixed extent size of the `MY_PREFERRED_EXTSIZE` attribute on a new file, `MY_FILE`, assuming `MY_PREFERRED_EXTSIZE` is multiple of the file system block size:

```
#include <sys/fs/vx_ioctl.h>
struct vx_ext myext;
fd = open(MY_FILE, O_CREAT, 0644);
myext.ext_size = MY_PREFERRED_EXTSIZE;
myext.reserve = 0;
myext.flags = 0;
error = ioctl(fd, VX_SETEXT, &myext);
```

The following is an example code snippet for preallocating `MY_FILESIZE_IN_BYTES` bytes of space on the new file, `MY_FILE`, assuming that the target file system block size is `THIS_FS_BLOCKSIZE`:

```
#include <sys/fs/vx_ioctl.h>
struct vx_ext myext;
fd = open(MY_FILE, O_CREAT, 0644);
myext.ext_size = 0;
myext.reserve = (MY_FILESIZE_IN_BYTES + THIS_FS_BLOCKSIZE)
/THIS_FS_BLOCKSIZE;
myext.flags = VX_CHGSIZE;
error = ioctl(fd, VX_SETTEXT, &myext);
```


Thin Reclamation

This chapter includes the following topics:

- [About Thin Storage](#)
- [About Thin Reclamation](#)
- [Thin Reclamation application programming interface](#)

About Thin Storage

Thin Storage is the result of using Thin Provisioning-capable arrays. Thin Storage is an array vendor solution for allocating storage to applications only when the storage is truly needed, from a pool of free storage. The Thin Storage solution tries to solve the problem of under utilization of available array capacity. Thin Storage reclaim-capable arrays and LUNs allow the administrators to release previously-used storage to the pool of free storage.

About Thin Reclamation

Some vendors support a reclamation capability on Thin Storage arrays, on which the administrator can initiate the process of reclaiming free storage from the file systems or disks in the LUN or array so that this storage is released to the free storage pool. Such arrays and LUNs are referred to as Thin Provisioning arrays and LUNs. The Storage Foundation Thin Reclamation feature reclaims free blocks through command line and programmatic interfaces.

Thin Reclamation application programming interface

You can use Thin Reclamation with the following API:

```
uint vxfs_ts_reclaim(char *mountpoint, uint64_t offset,
uint64_t length, int32_t volindex, uint64_t unit_size,
uint64_t *bytes_reclaimed, uint32_t flag)
```

This is a non-reentrant API. This API cannot be called when an instance of the `fsadm` command or a reorg of the file system is running.

<i>mountpoint</i>	The pathname of the VxFS file system that is mounted on a Veritas Volume Manager (VxVM) volume.
<i>offset</i>	The offset in bytes in the volume from which to start reclamation.
<i>length</i>	The length in bytes from <i>offset</i> , up to which to reclaim free storage.
<i>volindex</i>	The index of the volume in a volume set. When <i>volindex</i> has a value of -1, all the volumes in the file system ignore <i>offset</i> and <i>length</i> . On a non-multi-volume file system, <i>volindex</i> should be zero.
<i>unit_size</i>	The size in multiples by which the file system issues reclaim requests to VxVM. Each Thin Provisioning array supports reclamation by a factor of some unit size.
<i>bytes_reclaimed</i>	Returns the number of bytes that the file system attempted to reclaim. The value does not give an indication of the number of bytes actually reclaimed.

flag

Possible value for flag is:

- `VXFS_TS_RECLAIM_AGGRESSIVE` – Perform an additional data and metadata reorganization to maximize free space reclamation. This operation might trigger additional space allocation from the underlying Thin Storage, which is released at the end of the operation. This operation can fragment existing large allocations.

Aggressive reclamation is performed only if VxVM reports the volume as `thinrcldm`. In case of multi-volume file systems, only the volumes that VxVM reports as `thinrcldm` are considered.

If the *volindex* argument has a value of `-1`, then the full file system is covered. The *offset* and *length* arguments are ignored. If you specify a value for the *volindex* argument, then the full volume is covered if both the *offset* argument and *length* argument have a value of `0`. If you specify a value for the *offset* argument and *length* argument, `vxfs_ts_reclaim()` does not perform aggressive reclamation, but performs the default the default reclamation instead, regardless if you specified a value for the *volindex* argument.

- `VXFS_TS_RECLAIM_ANALYZE` | `VXFS_TS_RECLAIM_ANALYZE` – Perform an analysis of the file system to recommend whether you should use Normal Reclaim or Aggressive Reclaim. You can use either reclaim policy regardless of the recommendation. Analyse reclamation is performed only if Veritas Volume Manager (VxVM) reports the volume as `thinrcldm`. In the case of multi-volume file systems, the `vxfs_ts_reclaim()` API considers only the volumes that VxVM reports as `thinrcldm`.
- `VXFS_TS_RECLAIM_AUTO` – Perform an analysis of the file system determine which reclaim policy is suitable at this point and, depending upon the analysis, execute the policy on behalf of the user. Auto reclamation is performed only if VxVM reports the volume as `thinrcldm`. In the case of multi-volume file systems, the `vxfs_ts_reclaim()` API considers only the volumes that VxVM reports as `thinrcldm`.

VxFS may align the *offset* and *length* internally for correctness.

Note: Thin Reclamation is a slow process and may take several hours to complete, depending on the file system size. Thin Reclamation is not guaranteed to reclaim 100% of the free space.

vxfs_ts_reclaim return values

The return values from the API are as follows:

-3	Returned if the <code>analyze</code> option of the <code>vxfs_ts_reclaim()</code> API advises Aggressive Reclaim.
-2	Returned if the <code>analyze</code> option of the <code>vxfs_ts_reclaim()</code> API advises Normal Reclaim.
0	Successful reclamation.
EPERM	A non-root user called the API.
ENOENT	The mount point does not exist.
EBADF	The mount point is not the root of the file system.
EPIPE	The device for the mount point cannot be accessed.
ENOTSUP	The mount point is not the root of a VxFS file system, the specified volume is not <code>thinrlm</code> -capable, or none of the volumes in the volume set are <code>thinrlm</code> -capable.
ENOMEM	Memory could not be allocated during the operation of the API.
EBUSY	The metadata on the file system could not be modified.
ENXIO	The specified device does not exist.
EINVAL	The specified offset or length is invalid.
EAGAIN	Another <code>fsadm</code> or <code>reorg</code> instance is running.
EFAULT	The reclaim operation failed due to other system-related issues.

Index

A

- allocation flags 81
- allocation flags with fixed extent size 83
- allocation policies 51
 - multi-volume support 54
- alternate namespace 63
- application interface 12

C

- caching advisories 74
- close 18
- compiling environment 14
- concurrent I/O 75

D

- data copy 75
- data transfer 75
- DEV_BSIZE 77
- direct data transfer 75
- direct I/O 74

E

- extent attributes 78
- extents 77

F

- fchdir 67
- fchroot 67
- fcl_keeptime 25
- fcl_maxalloc 25
- fcl_winterval 26
- File Change Log 12, 17
 - application programming interface 27
 - record types 22
 - special records 24
 - superblock 25
 - tunables 25
- File Change Log file 17
- fixed extent size 78–79
- freeze/thaw 71

- FSAP_INHERIT 55
- fsapadm 52
- fsvoladm 52

G

- getcwd 68
- getdents 65–66
- getext 78

H

- header files 14

I

- I/O
 - direct 75
 - sequential 75
 - synchronous 75
- intent log
 - multi-volume support 52
- ioctl 12, 74, 80

L

- libraries 14
- logical blocks 77
- lseek 18

M

- mkfs 77
- mmap 64–65
- multi-volume support 13, 51
 - allocation policy APIs 54
 - creating and assigning policies 56
 - data structures 58
 - enforcing the policy on a file 58
 - examples of volume set operations 53
 - modifying a volume within a file system 54
 - querying the defined policies 57
 - querying the volume set for a file system 53
 - uses 52

multi-volume support *(continued)*

- volume APIs 52
- volume encapsulation 54

N

- named attributes 63
- named data streams 63
 - application programming interface 64, 69
 - behavior changes in other system calls 67
 - example 68
 - listing 66
 - namespace 67
 - programmer's reference 69
- ncheck 48

O

- open 18, 63, 65, 74
- other advisories 76

R

- read 18, 64–65, 75
- readdir 65
- Record Types
 - special records 24
- record types 22
- reservation 78–79
- reverse path name lookup 48

S

- sequential I/O 75, 77
- setext 78
- Software Developer's Kit 11
 - packages 13
- special records 24
- statfs 84
- Storage Checkpoints 52
- synchronous I/O 75

T

- Thin Reclamation 87
- Thin Storage 87

U

- ulimit 81
- unbuffered I/O 76
- using extent attribute APIs 84

V

- volume APIs 52
- volume set 53
- VOP_SETATTR 67
- VRTSfssdk 13
- VX_ALIGN 83
- VX_CHGSIZE 81–83
- VX_CONCURRENT 75
- VX_CONTIGUOUS 82–83
- VX_DIRECT 76
- vx_ext 80, 84
- VX_FREEZE 72
- VX_FREEZE_ALL 72–73
- VX_GETTEXT 80, 84
- VX_NOEXTEND 82
- VX_NORESERVE 82
- VX_RANDOM 77
- VX_SEQ 77
- VX_SETCACHE 76
- VX_SETTEXT 80, 84
- VX_THAW 72
- VX_TRIM 82
- VX_UNBUFFERED 76
- VxFS I/O 13
 - caching advisories 74
 - concurrent I/O 75
 - direct I/O 74
 - other advisories 76
 - unbuffered I/O 76
 - extents 77
 - allocation flags 81
 - allocation flags with fixed extent size 83
 - API 80
 - attribute specifics 78
 - extent attributes 78
 - fixed extent size 79
 - reservation 79
 - using extent attribute APIs 84
 - freeze/thaw 71
- vxfs_inotopath 49
- vxfs_inotopath_gen 48
- vxfs_nattr_link 65
- vxfs_nattr_open 65
- vxfs_nattr_rename 66
- vxfs_nattr_unlink 66
- vxfs_nattr_utimes 66
- vxfsio 74
- vxtunefs 25
- vxvset 53

W

write 64-65, 75