

Veritas Storage Foundation™ and High Availability Solutions Virtualization Guide

Solaris

6.0.1

Veritas Storage Foundation and High Availability Solutions Virtualization Guide

The software described in this book is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Product version: 6.0.1

Document version: 6.0.1 Rev 0

Legal Notice

Copyright © 2012 Symantec Corporation. All rights reserved.

Symantec, the Symantec logo, Veritas, Veritas Storage Foundation, CommandCentral, NetBackup, Enterprise Vault, and LiveUpdate are trademarks or registered trademarks of Symantec corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation
350 Ellis Street
Mountain View, CA 94043
<http://www.symantec.com>

Technical Support

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our Web site at the following URL:

www.symantec.com/business/support/index.jsp

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

Contacting Technical Support

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/contact_techsupp_static.jsp

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

- Product release level

- Hardware information
- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
 - Error messages and log files
 - Troubleshooting that was performed before contacting Symantec
 - Recent software configuration changes and network changes

Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs or manuals

Support agreement resources

If you want to contact Symantec regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan	customercare_apac@symantec.com
Europe, Middle-East, and Africa	semea@symantec.com
North America and Latin America	supportsolutions@symantec.com

Documentation

Your feedback on product documentation is important to us. Send suggestions for improvements and reports on errors or omissions. Include the title and document version (located on the second page), and chapter and section titles of the text on which you are reporting. Send feedback to:

doc_feedback@symantec.com

For information regarding the latest HOWTO articles, documentation updates, or to ask a question regarding product documentation, visit the Storage and Clustering Documentation forum on Symantec Connect.

<https://www-secure.symantec.com/connect/storage-management/forums/storage-and-clustering-documentation>

About Symantec Connect

Symantec Connect is the peer-to-peer technical community site for Symantec's enterprise customers. Participants can connect and share information with other product users, including creating forum posts, articles, videos, downloads, blogs and suggesting ideas, as well as interact with Symantec product teams and Technical Support. Content is rated by the community, and members receive reward points for their contributions.

<http://www.symantec.com/connect/storage-management>

Contents

Technical Support	4	
Chapter 1	Overview of Veritas Storage Foundation and High Availability Virtualization Solutions	15
	Overview	15
	Reference documentation	16
	About Veritas Storage Foundation and High Availability Virtualization Solutions	17
Chapter 2	Storage Foundation and High Availability Solutions support for Solaris Zones	19
	About Solaris Zones	20
	About VCS support for zones	20
	Overview of how VCS works with zones	20
	About the ContainerInfo service group attribute	21
	About the ContainerOpts resource type attribute	21
	Zone-aware resources	22
	About the Mount agent	23
	About networking agents	26
	About the Zone agent	26
	About configuring failovers among physical and virtual servers	27
	Configuring VCS in zones	27
	Prerequisites for configuring VCS in zones	27
	Deciding on the zone root location	29
	Creating a zone with root on local disk	29
	Creating a zone with root on shared storage	30
	Performing the initial internal zone configuration	32
	About installing applications in a zone	32
	Configuring the service group for the application	32
	Configuring a zone resource in a failover service group with the hazonesetup utility	35
	Configuring zone resource in a parallel service group with the hazonesetup utility	38

Configuring multiple zone resources using same VCS user for password less communication	40
Modifying the service group configuration	41
Verifying the zone configuration	42
Performing maintenance tasks	42
Troubleshooting zones	43
Configuring for physical to virtual and virtual to physical failovers—a typical setup	43
VCS limitations with Solaris zones	44
Adding VxFS file systems to a non-global zone	45
Direct mount of VxFS file systems from global zone	45
Mounting a VxFS file system in a non-global zone	46
Adding a direct mount to a zone's configuration	47
Creating VxFS file systems inside non-global zones	47
Veritas Storage Foundation Cluster File System mounts	49
Concurrent I/O access in non-global zones	50
Veritas extension for Oracle Disk Manager	51
Exporting VxVM volumes to a non-global zone	53
VxVM devices in Oracle Solaris global zones	54
Removing a VxVM volume from a non-global zone	54
About SF Oracle RAC support for Oracle RAC in a zone environment	55
Supported configuration	56
Known issues with supporting SF Oracle RAC in a zone environment	57
Setting up an SF Oracle RAC cluster with Oracle RAC on non-global zones	60
Preparing to install non-global zones	61
Installing non-global zones	66
Creating SF Oracle RAC configuration files inside non-global zones	67
Enabling Oracle Disk Manager file access from non-global zones with Veritas File System	67
Configuring high availability for non-global zones	68
Configuring the cluster name for clustering non-global zones	69
Installing Oracle RAC inside the non-global zones	70
Linking the ODM library	70
Creating the Oracle database	70
Configuring non-global zones under VCS	71
Sample VCS configuration with non-global zones	72
Configuring Solaris non-global zones for disaster recovery	92

	Software limitations of Storage Foundation support of non-global zones	94
	Administration commands are not supported in non-global zone	94
	VxFS file system is not supported as the root of a non-global zone	95
	QIO and CQIO are not supported	95
	Package installation in non-global zones	95
	Package removal with non-global zone configurations	95
	Root volume cannot be added to non-global zones	95
	Some Veritas Volume Manager operations can cause volume device names to go out of sync	95
Chapter 3	Storage Foundation and High Availability Solutions support for Solaris Projects	97
	About Solaris Projects	97
	About VCS support for Solaris projects	98
	Overview of how VCS works with Solaris projects	98
	About the ContainerInfo service group attribute	98
	About the ContainerOpts resource type attribute	99
	Project-aware resources	100
	About the Project agent	100
	Configuring VCS in Solaris projects	100
	Prerequisites for configuring VCS in projects	100
Chapter 4	Storage Foundation and High Availability Solutions support for Branded Zones	103
	About branded zones	103
	System requirements	104
	Veritas Storage Foundation support for branded zone	104
	About migrating VCS clusters on Solaris 10 systems	104
	Preparing to migrate a VCS cluster	105
	Configuring VCS/SF in a branded zone environment	106
Chapter 5	Storage Foundation and High Availability Solutions support for Oracle VM Server for SPARC	111
	Terminology for Oracle VM Server for SPARC	112
	Oracle VM Server for SPARC deployment models	113
	Split Storage Foundation stack	114
	Guest-based Storage Foundation stack	114

Benefits of deploying Storage Foundation High Availability solutions	
in Oracle VM server for SPARC	114
Standardization of tools	114
Array migration	114
Moving storage between physical and virtual environments	115
Boot Image Management	115
Features	115
Storage Foundation features	115
Oracle VM Server for SPARC features	118
Split Storage Foundation stack model	119
How Storage Foundation and High Availability Solutions works	
in the Oracle VM Server for SPARC	119
Veritas Storage Foundation features restrictions	120
Guest-based Storage Foundation stack model	122
How Storage Foundation and High Availability Solutions works	
in the guest domains	122
About Veritas Storage Foundation Cluster File System in an	
Oracle VM Server for SPARC environment	123
Supported configurations with SFCFS and multiple I/O	
Domains	124
Veritas Storage Foundation features restrictions	127
System requirements	128
Hardware requirements	128
Veritas product release notes	129
Veritas Storage Foundation and High Availability	129
Veritas Storage Foundation Cluster File System	129
Product licensing	129
Installing Storage Foundation in a Oracle VM Server for SPARC	
environment	129
Installing and configuring Oracle VM Server for SPARC and	
domains	130
Installing Storage Foundation in the control domain or	
guest	130
Installing Veritas File System in the guest domain	131
Enabling DMP in the control and alternate I/O domains	131
Verifying the configuration	135
Exporting a Veritas volume to a guest domain from the control	
domain	136
Provisioning storage for a guest domain	137
Provisioning Veritas Volume Manager volumes as data disks for	
guest domains	137
Provisioning Veritas Volume Manager volumes as boot disks for	
guest domains	139

	Using Veritas Volume Manager snapshots for cloning logical domain boot disks	141
	Configuring Oracle VM Server for SPARC guest domains for disaster recovery	146
	Software limitations	149
	Memory Corruption in the guest domain during SCSI commands	149
	Exporting the raw volume device node fails	149
	Resizing a Veritas Volume Manager volume (exported as a slice or full disk) does not dynamically reflect the new size of the volume in the guest	150
	Known issues	150
	Guest-based known issues	150
	Split Storage Foundation stack known issues	152
Chapter 6	Veritas Cluster Server support for using CVM with multiple nodes in a Oracle VM Server for SPARC environment	153
	Clustering using Cluster Volume Manager	153
	Installing Storage Foundation on multiple nodes in a Logical Domain	154
	Reconfiguring the clustering agents for Cluster Volume Manager	154
	Cluster Volume Manager in the control domain for providing high availability	156
Chapter 7	Veritas Cluster Server: Configuring Oracle VM Server for SPARC for high availability	159
	About Veritas Cluster Server in a Oracle VM Server for SPARC environment	159
	Dynamic reconfiguration of memory and CPU of a guest domain	160
	Veritas Cluster Server requirements	161
	Veritas Cluster Server limitations	161
	Veritas Cluster Server known issues	161
	About Veritas Cluster Server configuration models in an Oracle VM Server for SPARC environment	162
	Veritas Cluster Server setup to fail over a logical domain on a failure of logical domain	163

Veritas Cluster Server setup to fail over a logical domain on a failure of Application running inside the logical domain or logical domain itself	168
Veritas Cluster Server setup to fail over an Application running inside logical domain on a failure of Application	175
Oracle VM Server for SPARC guest domain migration in VCS environment	176
Overview of a warm migration	177
Overview of a live migration	178
Prerequisites before you perform domain migration	179
Supported deployment models for Oracle VM Server for SPARC domain migration with VCS	180
Migrating Oracle VM guest when VCS is installed in the control domain that manages the guest domain	180
Migrating Oracle VM guest when VCS is installed in the control domain and single-node VCS is installed inside the guest domain to monitor applications inside the guest domain	181
Migrating Oracle VM guest when VCS cluster is installed in the guest domains to manage applications for Oracle VM Server for SPARC version 2.1 and above	183
Migrating Oracle VM guest when VCS cluster is installed in the guest domains to manage applications for Oracle VM Server for SPARC version 2.0	183
About configuring Veritas Cluster Server for Oracle VM Server for SPARC with multiple I/O domains	185
About Alternate I/O domain	186
Setting up the Alternate I/O domain	186
Configuring VCS to manage a Logical Domain with multiple I/O domains	187
Configuring VCS to manage a Logical Domain using services from multiple I/O domains	187
A typical setup for a Logical Domain with multiple I/O services	188
Identify supported storage and network services	189
Determine the number of nodes to form VCS cluster	190
Install and configure VCS inside the control domain and alternate I/O domain	190
Configuring storage services	190
Configure storage service groups	193
Configure network service groups	195
Configure a service group to monitor services from multiple I/O domains	198

	Configure the AlternateIO resource	199
	Configure the service group for a Logical Domain	201
	Failover scenarios	203
	Recommendations while configuring VCS and Oracle VM Server for SPARC with multiple I/O domains	203
	Sample VCS configuration for AlternateIO resource configured as a fail over type	204
Chapter 8	Symantec ApplicationHA: Configuring Oracle VM Server for SPARC for high availability	209
	About Symantec ApplicationHA	209
	Why Symantec ApplicationHA	210
	LDom configurations with Symantec ApplicationHA	211
	Symantec ApplicationHA in the guest domains (LDoms)	211
	VCS in the control domain and Symantec ApplicationHA in the guest domain (LDom)	212
	Installing and configuring ApplicationHA for application availability	214
	Additional documentation	214
	Oracle Solaris documentation	214
	Symantec documentation	214

Overview of Veritas Storage Foundation and High Availability Virtualization Solutions

This chapter includes the following topics:

- [Overview](#)
- [About Veritas Storage Foundation and High Availability Virtualization Solutions](#)

Overview

This document provides information about Veritas Storage Foundation and High Availability Virtualization Solutions. Review this entire document before you install Veritas Storage Foundation and High Availability products in zones, branded zones, projects, and logical domains.

This book provides many high-level examples and information. As such, you should be a skilled user of Veritas products and knowledgeable concerning Oracle's virtualization technologies.

Each chapter in this guide presents information on using a particular Oracle virtualization technology with Veritas products. These chapters follow:

- Storage Foundation and High Availability Solutions support for Solaris Zones
- Storage Foundation and High Availability Solutions support for Solaris Projects

- Storage Foundation and High Availability Solutions support for Branded Zones
- Storage Foundation and High Availability Solutions support for Oracle VM Server for SPARC
- Using multiple nodes in an Oracle VM Server for SPARCn environment
- Configuring logical domains for high availability

Reference documentation

The following documentation provides information on installing, configuring, and using Veritas Cluster Server:

- *Veritas Cluster Server Release Notes*
- *Veritas Cluster Server Installation Guide*
- *Veritas Cluster Server Bundled Agents Reference Guide*
- *Veritas Cluster Server Agent for DB2 Installation and Configuration Guide*
- *Veritas Cluster Server Agent for Oracle Installation and Configuration Guide*
- *Veritas Cluster Server Agent for Sybase Installation and Configuration Guide*

The following documentation provides information on installing, configuring, and using Veritas Storage Foundation products:

- *Veritas Storage Foundation Release Notes*
- *Veritas Storage Foundation and High Availability Installation Guide*
- *Veritas Storage Foundation Administrator's Guide*

The following documentation provides information on installing, configuring, and using Veritas Storage Foundation for Oracle RAC:

- *Veritas Storage Foundation for Oracle RAC Release Notes*
- *Veritas Storage Foundation for Oracle RAC Installation and Configuration Guide*
- *Veritas Storage Foundation for Oracle RAC Administrator's Guide*

The following documentation provides information on installing, configuring, and using Veritas Storage Foundation Cluster File System:

- *Veritas Storage Foundation Cluster File System Release Notes*
- *Veritas Storage Foundation Cluster File System Installation Guide*
- *Veritas Storage Foundation Cluster File System Administrator's Guide*

Note: Veritas Storage Foundation for Oracle RAC and Veritas Storage Foundation Cluster File System does not support branded zones.

For Oracle VM Server for SPARC (formerly Solaris Logical Domains), Branded Zone, Projects, and Zone installation and configuration information, refer to the Oracle site: www.oracle.com.

Oracle provides regular updates and patches for Oracle VM Server for SPARC, Branded Zones, and Zone features. Contact Oracle for details.

About Veritas Storage Foundation and High Availability Virtualization Solutions

Veritas Storage Foundation and High Availability Virtualization Solutions includes support for non-global and Branded zones, Projects, and Oracle VM Server for SPARC.

Solaris Zones, also known as non-global zones is an operating system-level virtualization technology, which provides a means of virtualizing operating system services to create an isolated environment for running applications. Non-global zones function as completely isolated virtual servers with a single operating system instance.

Branded zones are an extension of the Solaris Zone infrastructure. A Branded zone is a non-native zone that allows individual zones to emulate an operating system environment other than the native environment of the global operating system.

Oracle VM Server for SPARC is a virtualization technology that enables the creation of independent virtual machine environments on the same physical system. Oracle VM Server for SPARC provides a virtualized computing environment abstracted from all physical devices, which allows you to consolidate and centrally manage your workloads on a system. The logical domains can be specified roles such as a control domain, service domain, I/O domain, and guest domain. Each domain is a full virtual machine where the operating systems can be started, stopped, and rebooted independently.

The Solaris operating system provides a facility called projects to identify workloads. The project serves as an administrative tag, which you can use to group useful and related work. You can for example create one project for a sales application and another project for a marketing application. By placing all processes related to the sales application in the sales project and the processes for the marketing application in the marketing project, you can separate and control the workloads in a way that makes sense to the business.

Storage Foundation and High Availability Solutions support for Solaris Zones

This chapter includes the following topics:

- [About Solaris Zones](#)
- [About VCS support for zones](#)
- [Configuring VCS in zones](#)
- [Adding VxFS file systems to a non-global zone](#)
- [Direct mount of VxFS file systems from global zone](#)
- [Veritas Storage Foundation Cluster File System mounts](#)
- [Concurrent I/O access in non-global zones](#)
- [Veritas extension for Oracle Disk Manager](#)
- [Exporting VxVM volumes to a non-global zone](#)
- [About SF Oracle RAC support for Oracle RAC in a zone environment](#)
- [Setting up an SF Oracle RAC cluster with Oracle RAC on non-global zones](#)
- [Configuring Solaris non-global zones for disaster recovery](#)
- [Software limitations of Storage Foundation support of non-global zones](#)

About Solaris Zones

Solaris Zones is a software partitioning technology, which provides a means of virtualizing operating system services to create an isolated environment for running applications. This isolation prevents processes that are running in one zone from monitoring or affecting processes running in other zones.

You can configure non-global zones with a shared-IP address or an exclusive-IP address. The shared-IP zone shares a network interface with global-zone and the exclusive-IP zone does not share network interface with global-zone.

See the *Oracle Solaris Administration: Oracle Solaris Zones, Oracle Solaris 10 Zones, and Resource Management* Solaris operating environment document.

Oracle provides regular updates and patches for the Oracle Solaris Zones feature. Contact Oracle for more information.

About VCS support for zones

VCS provides application management and high availability to applications running in zones.

The Zone agent is IMF-aware and uses the asynchronous monitoring framework (AMF) kernel driver for IMF notification. For more information about the Intelligent Monitoring Framework (IMF) and intelligent resource monitoring, refer to the *Veritas Cluster Server Administrator's Guide*. For more information about how to perform intelligent resource monitoring for the Zone agent, see the *Veritas Cluster Server Bundled Agents Reference Guide*.

Overview of how VCS works with zones

You can use VCS to perform the following:

- Start, stop, monitor, and fail over a non-global zone.
- Start, stop, monitor, and fail over an application that runs in a zone.

How VCS models containers

VCS and the necessary agents run in the global zone. For the applications that run in a zone, the agents can run some of their functions (entry points) inside the zone. If any resource faults, VCS fails over the service group with the zone to another node.

You can configure VCS to use Symantec Product Authentication Service to run in a secure environment. Communication from non-global zones to global zones is secure in this environment.

Installing and configuring zones in VCS environments

Install and configure the zone. Create the service group with the standard application resource types (application, storage, networking) and the Zone resource. VCS manages the zone as a resource. You then configure the service group's ContainerInfo attribute.

Configuring the ContainerInfo attribute

The service group attribute ContainerInfo specifies information about the zone. When you have configured and enabled the ContainerInfo attribute, you have enabled the zone-aware resources in that service group to work in the zone environment.

VCS defines the zone information at the level of the service group so that you do not have to define it for each resource. You may specify a per-system value for the ContainerInfo attribute.

About the ContainerInfo service group attribute

The ContainerInfo attribute has the Name key, Type key, and Enabled key. The Name key defines the name of the container. The Type key lets you select the type of container that you plan to use. The Enabled key enables the Zone-aware resources within the service group. The ContainerInfo attribute specifies if you can use the service group with the container.

Assign the following values to the ContainerInfo attribute:

- Name
The name of the container.
- Type
The type of container. You can set this to Zone.
- Enabled
Specify the value as 0, if you want to disable the container. Specify the value as 1, if you want to enable the container. Specify the value as 2, to enable physical to virtual and virtual to physical failovers. When the value is 2, the Zone resource mimics a non-existent entity.

You can set a per-system value for this attribute.

About the ContainerOpts resource type attribute

The ContainerOpts resource attribute is pre-set for Zone-aware resource types. It determines the following:

- Whether the zone-aware resource can run in the zone.

- Whether the container information that is defined in the service group's ContainerInfo attribute is passed to the resource.

These values are only effective when you configure the ContainerInfo service group attribute.

Attribute's keys follow:

The ContainerOpts resource type attribute's definitions for Zone-aware types contain the following values:

- RunInContainer (RIC)

When the value of the RunInContainer key is 1, the agent function (entry point) for that resource runs inside of the local container.

When the value of the RunInContainer key is 0, the agent function (entry point) for that resource runs outside the local container (in the global environment).

A limitation for the RunInContainer value is that only script agent functions (entry points) can run inside a container.

- PassCInfo (PCI)

When the value of the PassCInfo key is 1, the agent function (entry point) receives the container information that is defined in the service group's ContainerInfo attribute. An example use of this value is to pass the name of the container to the agent.

Zone-aware resources

[Table 2-1](#) lists the ContainerOpts attributes default values for resource types. Zone-aware resources have predefined values for the ContainerOpts attribute.

Note: Symantec recommends that you do not modify the value of the ContainerOpts attribute, with the exception of the Mount agent.

See [“About the Mount agent”](#) on page 23.

See [“About networking agents”](#) on page 26.

Table 2-1 ContainerOpts attribute default values for applications and resource types

Resource type	RunInContainer	PassCInfo
Apache	1	0
Application	1	0
ASMinst	1	0

Table 2-1 ContainerOpts attribute default values for applications and resource types (continued)

Resource type	RunInContainer	PassCInfo
ASMDG	1	0
Db2udb	1	0
NIC	0	1
IP	0	1
IPMultiNIC	0	1
IPMultiNICB	0	1
Process	1	0
Zone	0	1
Oracle	1	0
Netlsnr	1	0
Sybase	1	0
SybaseBk	1	0
ProcessOnOnly	1	0
Project	0	1

About the Mount agent

You may need to modify the ContainerOpts values for the Mount resource in certain situations.

In certain situations where the block device is not exported to zone, you can make the file system available inside local zone. Mount the block device on the directory that has a path that includes the zone root from global zone, for example:

```
BlockDevice = /dev/vx/dsk/dg/voll  
MountPoint = /zones/zone-test/root/mntpt
```

Where `/zones/zone-test` is the zone root of the local zone.

Mount agent supports the following configuration for mount points

- 1 Direct mount of file system with mount point as full path seen from global zone. Typical mount resource configuration for this type of mount is shown below:

```
group mntgrp (  
    SystemList = { Sys1 = 0, Sys1 = 1 }  
)  
  
Mount mnt-direct (  
    MountPoint = "/zones/zone-test/root/mnt"  
    BlockDevice = "/dev/vx/dsk/dg/vol"  
    FSType = vxfs  
    FsckOpt = "-y"  
)
```

- 2 Loop-back file system mount inside non-global zone for file system mounted in global zone. Typical mount resource configuration for this type of mount is shown below:

```
group mntgrp (  
    SystemList = { Sys1 = 0, Sys1 = 1 }  
)  
  
Mount mnt-lofs (  
    MountPoint = "/zones/zone-test/root/mnt-zone"  
    BlockDevice = "/mnt"  
    FSType = lofs  
    FsckOpt = "-n"  
)
```


3 Direct mount of NFS based file system inside non-global zone. Typical mount resource configuration for this type of mount is shown below:

```
group mntgrp (
    SystemList = { Sys1 = 0, Sys1 = 1 }
    ContainerInfo = { Name = zone-test, Type = Zone, Enal
)

Mount mntnfs (
    MountPoint = "/mnt"
    BlockDevice = "system:/shared-dir"
    FSType = nfs
    FsckOpt = "-n"
    ContainerOpts = { RunInContainer = 1, PassCInfo = 0 }
)
```

Bringing a Mount resource online in the zone

The Mount resource is brought online in the global zone by default (RunInContainer = 0). If you want to bring a mount resource online inside the non-global zone, perform the following:

- Export the block device to the zone through zone configuration. Ensure that the raw volume is used appropriately to prevent the possibility of data corruption.
- Modify the ContainerInfo attribute for the service group and set values for the Name, Type, and Enabled keys.

```
# hagrps -modify service_group ContainerInfo Name zone_name\
Type Zone Enabled 1
```

- Override the ContainerOpts attribute at the resource level.
- Set the value of the RunInContainer key to 1, for example:

```
# hares -override Mountres ContainerOpts
# hares -modify Mountres ContainerOpts \
RunInContainer 1 PassCInfo 0
```

For information on overriding resource type static attributes, refer to the *Veritas Cluster Server Administrator's Guide*.

Setting the attribute values for a Mount resource for NFS mounts

For NFS mounts, you must mount in the non-global zone.

- Modify the ContainerInfo attribute for the service group and set values for Name, Type and Enabled keys.
- Override the ContainerOpts attribute at the resource level.
- Set the value of the RunInContainer key to 1.
Set the RIC value to 1. When you set RIC=1, specify the value of the MountPoint attribute relative to the zone root, for example:

```
BlockDevice = abc:/fs1  
MountPoint = /mnt1
```

The file system is mounted on `/zone_root/mnt1`.

About networking agents

Enable the attribute ExclusiveIPZone for resources of type IP and NIC when these resources are configured to manage the IP and the NIC inside an exclusive-IP zone. This attribute is disabled by default. The IP agent and the NIC agent assumes the native zone (shared-IP) by default.

VCS brings resources online in the global zone by default.

If you want to bring these resources online inside the exclusive-IP zone, perform the following tasks:

- Make sure that the resource is in a service group that has valid ContainerInfo attribute value configured.
- Set the value of the ExclusiveIPZone attribute to 1.

Note: The exclusive-IP zone supports the IP and NIC networking agents. For more information about these agents, see the *Veritas Cluster Server Bundled Agents Reference Guide*.

About the Zone agent

The Zone agent monitors zones, brings them online, and takes them offline. For more information about the agent, see the *Veritas Cluster Server Bundled Agents Reference Guide*.

Use `hazonesetup` utility to create user account with group administrative privileges. The `DeleteVCSZoneUser` attribute of zone resource controls removing

the user account when the zone resource is taken offline. For more information, see the *Veritas Cluster Server Bundled Agents Reference Guide*.

About configuring failovers among physical and virtual servers

You can configure VCS to fail over from a physical system to a virtual system and vice versa. A physical to virtual failover gives an N + N architecture in an N + 1 environment. For example, several physical servers with applications can fail over to containers on another physical server.

See [“Configuring for physical to virtual and virtual to physical failovers—a typical setup”](#) on page 43.

Configuring VCS in zones

Configuring VCS in zones involves the following tasks:

- | | |
|--------|--|
| First | Review the prerequisites.
See “Prerequisites for configuring VCS in zones” on page 27. |
| Second | Decide on the location of the zone root, which is either on local storage or shared storage.
See “Deciding on the zone root location” on page 29. |
| Third | Install the application in the zone.
See “About installing applications in a zone” on page 32. |
| Fourth | Create the application service group and configure its resources.
See “Configuring the service group for the application” on page 32. |

Prerequisites for configuring VCS in zones

Review the following prerequisites for configuring VCS in zones:

- For Oracle Solaris 10, VCS supports UFS, ZFS, and VxFS mounts for the zone root.
- For Oracle Solaris 11, VCS supports only ZFS for zone root.

Method for file system access inside non-global zone

File system mounts must meet one of the following two conditions:

- Use a loopback file system. All mounts that the application uses must be part of the zone configuration and must be configured in the service group. For

example, you can create a zone, `z-ora`, and define the file system containing the application's data to have the mount point as `/oradata`. When you create the zone, you can define a path in the global zone. An example is `/export/home/oradata`, which the mount directory in the non-global zone maps to. The `MountPoint` attribute of the `Mount` resource for the application is set to `/export/home/oradata`. Confirm that `/export/home/oradata` maps to `/oradata` with the `zonecfg -z zone_name info` command. You can also look into the zone configuration `/etc/zones/zone_name.xml` file. The `Zone` resource depends on the `Mount` resource.

- Use a direct mount file system. All file system mount points that the application uses that run in a zone must be set relative to the zone's root. For example, if the Oracle application uses `/oradata`, and you create the zone with the `zonepath` as `/z_ora`, then the mount must be `/z_ora/root/oradata`. The `MountPoint` attribute of the `Mount` resource must be set to this path. The `Mount` resource depends on the `Zone` resource.

Note: The `Mount` agent does not support mounting VxFS file systems directly inside non-global zones.

Using custom agents in zones

If you use custom agents, review the following information for their use in zones:

- If you use custom agents to monitor the applications that run in zones, make sure that the agents use script-based entry points. VCS does not support running C++ entry points inside a zone.
- If you want the custom agent to monitor an application in the zone, for the custom agent type, set the following values for the `ContainerOpts` attribute: `RunInContainer = 1` and the `PassCInfo = 0`.
- If you don't want the custom agent to monitor an application in the zone, for the custom agent type, set the following values for the `ContainerOpts` attribute: `RunInContainer = 0` and the `PassCInfo = 0`.
- Two main use cases exist where you might want to use a `RunInContainer = 0` and `PassCInfo = 1`, descriptions of these follow.
 - The first is the `Zone` agent's use of these values. The `Zone` agent's entry points cannot run inside of the non-global zone but the agent itself manages the zone. `RunInContainer` requires a value of 0 because the agent must run in the global zone. `PassCInfo` has a value of 1 because the `Zone` agent requires the name of the container from the `ContainerInfo` service group attribute.

- The second case is how the IP agent uses `RunInContainer` and `PassCInfo`. The IP agent's entry points must run outside of the non-global zone because a shared-IP zone may cause the networking stack to not completely run in the non-global zone. You cannot perform an `ifconfig` command and then plumb the IP from inside of a non-global zone. When you run the `ifconfig` command in the global zone with the `zone` option - it plumbs the IP and makes it available to the zone that you specify. The need for the container's name comes from the use of this command, even though it cannot run in the container. This is applicable to all networking agents.

Deciding on the zone root location

Each zone has its own section of the file system hierarchy in the zone root directory. Processes that run in the zone can access files only within the zone root.

You can set the zone root in the following two ways:

- **Zone root on local storage**
In this configuration, you must configure and install a zone on each node in the cluster.
- **Zone root on shared storage**
In this configuration, configure and install a zone in shared storage from one system and duplicate the configuration on each node in the cluster. Setting the zone root on shared storage means you need to install the non-global zone on shared storage from one system only. The zone root can fail over to the other systems. To do this, the system software, including the patches, must be identical on each system during the existence of the zone.

Creating a zone with root on local disk

Create a zone root on the local disk on each node in the cluster. The file system for application data is on a shared device and is either the loopback type or the direct mount type. For a direct mount file system, run the `mount` command from the global zone with the mount point specified as the complete path that starts with the zone root. For a loopback file system, add it into the zone's configuration before you boot the zone.

To create a zone root on local disks on each node in the cluster

- 1 Configure the zone with the `zonecfg` command.

```
zonecfg -z newzone  
zonecfg:newzone> create
```

- 2 Set the `zonepath` parameter to specify a location for the zone root.

```
zonecfg:newzone> set zonepath=/export/home/newzone
```

- 3 If your application data resides on a loopback mount file system, create the loopback file system in the zone.

- 4 Exit the `zonecfg` configuration.

```
zonecfg> exit
```

- 5 Create the zone root directory.

```
mkdir zonepath
```

- 6 Set permissions for the zone root directory.

```
chmod 700 zonepath
```

- 7 Install the non-global zone.

```
zoneadm -z newzone install
```

- 8 Repeat step 1 to step 7 on each system in the service group's `SystemList`.

- 9 If the application data is on a loopback file system, mount the file system containing the application's data on shared storage.

- 10 Boot the zone.

```
zoneadm -z newzone boot
```

- 11 If the application data is on a direct mount file system, mount the file system from the global zone with the complete path that starts with the zone root.

Creating a zone with root on shared storage

Create a zone with root which points to the shared disk's location on each node in the cluster. The file system for application data is on a shared device and is either the loopback type or the direct mount type. For a direct mount file system,

run the mount command from the global zone with the mount point specified as the complete path that starts with the zone root. For a loopback file system, add it into the zone's configuration before you boot the zone.

To create a zone root on shared disks on each node in the cluster

- 1 Create a file system on shared storage for the zone root. The file system that is to contain the zone root may be in the same disk group as the file system that contains the application data.

- 2 Configure the zone with the `zonecfg` command.

```
zonecfg -z newzone  
zonecfg:newzone> create
```

- 3 Set the `zonpath` parameter to specify a location for the zone root.

```
zonecfg:newzone> set zonpath=/export/home/newzone
```

- 4 If your application data resides on a loopback mount file system, create the loopback file system in the zone.

- 5 Exit the `zonecfg` configuration.

```
zonecfg> exit
```

- 6 Create the zone root directory.

```
mkdir zonpath
```

- 7 Set permissions for the zone root directory.

```
chmod 700 zonpath
```

- 8 Repeat step 2 to step 7 on each system in the service group's SystemList.

- 9 Mount the file system that contains the shared storage on one of the systems that share the storage to the directory specified in `zonpath`.

- 10 Run the following command to install the zone on the system where the zone path is mounted.

```
zoneadm -z newzone install
```

- 11 If the application data is on a loopback file system, mount the file system containing the application's data on shared storage.

12 Boot the zone.

```
zoneadm -z newzone boot
```

13 If the application data is on a direct mount file system, mount the file system from the global zone with the complete path that starts with the zone root.

Performing the initial internal zone configuration

When a zone is booted for the first time after installation, the zone is in an unconfigured state. The zone does not have an internal configuration for naming services. Its locale and time zone have not been set, and various other configuration tasks have not been performed. You need to perform the initial internal zone configuration after zone installation.

You can perform the internal zone configuration in the following ways:

- `sysidcfg` tool
- Zone console login

For more details refer to Oracle documentation about "Performing the Initial Internal Zone Configuration" section in the *Oracle Solaris Administration: Oracle Solaris Zones, Oracle Solaris 10 Zones, and Resource Management* guide.

About installing applications in a zone

Perform the following tasks to install the application in a zone:

- If you have created zones locally on each node in the cluster, install the application identically in all zones on all nodes. If you are installing an application that is supported by a Veritas High Availability agent, see the installation and configuration guide for the agent.
- Install the agent packages on the global zone and the currently existing zones. Installs the agents in future zones when they are installed.
- You must define all the mount points that the application uses that are configured in the zone in the service group's configuration.

Configuring the service group for the application


You need to configure the application service group and the required resource dependencies. The following diagrams illustrates different examples of resource dependencies. In one case the zone root is set up on local storage. In the other, zone root is set up on shared storage.

Resource dependency diagrams: zone root on local disks

The following resource dependency diagrams show zone configurations on local disks configured for loopback and direct mounted file systems.


[Figure 2-1](#) depicts the dependency diagram when the zone root is set up on local storage with the loopback file system for the application. You can replace the Mount resource with the CFSMount resource and the DiskGroup resource with the CVMVolDg resource in the following diagram. In this configuration, decide if you want the service group to be a parallel service group. If so, you may need to localize certain attributes for resources in the service group. For example, you have to change the IP resource's Address attribute for each node.

Figure 2-1 Zone root on local disks with loopback file system



[Figure 2-2](#) depicts the dependency diagram when the zone root is set up on local storage with a direct mount file system for the application. You can replace the Mount resource with the CFSMount resource and the DiskGroup resource with the CVMVolDg resource in the following diagram. In this configuration, decide if you want the service group to be a parallel service group. If so, you may need to localize certain attributes for resources in the service group. For example, you have to change the IP resource's Address attribute for each node.

Figure 2-2 Zone root on local disks with direct mount file system



Resource dependency diagrams: zone root on shared disks

The following resource dependency diagrams show zone configurations on shared disks configured for loopback and direct mounted file systems.

Figure 2-3 depicts the dependency diagram when a zone root is set up on shared storage with the loopback file system. You can replace the Mount resource with the CFSMount resource and the DiskGroup resource with the CVMVoIdg resource in the following diagram for application. In this configuration, decide if you want the service group to be a parallel service group. If so, you may need to localize certain attributes for resources in the service group. For example, you have to change the IP resource's Address attribute for each node.

Figure 2-3 Zone root on shared storage with loopback file system





Figure 2-4 depicts the dependency diagram when a zone root is set up on shared storage with the direct mount file system for the application. You can replace the Mount resource with the CFSMount resource and the DiskGroup resource with the CVMVoIdg resource in the following diagram for application. In this configuration, decide if you want the service group to be a parallel service group.

If so, you may need to localize certain attributes for resources in the service group. For example, you have to change the IP resource's Address attribute for each node.

Figure 2-4 Zone root on shared storage a direct mounted file system



Use the following principles when you create the service group:

- Set the MountPoint attribute of the Mount resource to the mount path.
- If the application requires an IP address, configure the IP resource in the service group.

Configuring a zone resource in a failover service group with the hazonesetup utility

The hazonesetup utility helps you configure zone under VCS. This section covers typical scenarios based on where the zone root is located.

Two typical setups for zone configuration in a failover scenario follow:

- Zone root on local storage
[To configure a zone under VCS control using the hazonesetup utility when the zone root is on local storage](#)
- Zone root on shared storage
[To configure a zone under VCS control using the hazonesetup utility when the zone root is on shared storage](#)

Consider an example in a two-node cluster (sysA and sysB). Zone local-zone is configured on both the nodes.

To configure a zone under VCS control using the hazonesetup utility when the zone root is on local storage

- 1 Boot the local zone on first node outside VCS.

```
sysA# zoneadm -z local-zone boot
```

- 2 Make sure that you can reach the global zone from local zone.

```
# zlogin local-zone  
# ping sysA
```

- 3 Run hazonesetup with correct arguments on the first node. This adds failover zone service group and zone resource in VCS configuration.

```
sysA# hazonesetup -g zone_grp -r zone_res -z local-zone\  
-p password -a -s sysA,sysB
```

Note: If you want to use a particular user for password-less communication use `-u` option of the `hazonesetup` command. If `-u` option is not specified a default user is used for password-less communication.

- 4 Switch the zone service group to next node in the cluster.

```
sysA# hagrp -switch zone_grp -sys sysB
```

- 5 Run the hazonesetup utility with correct arguments on the node. The hazonesetup utility detects that the zone service group and zone resource are already present in VCS configuration and update the configuration accordingly for password-less communication.

```
sysB# hazonesetup -g zone_grp -r zone_res -z local-zone\  
-p password -a -s sysA,sysB
```

- 6 Repeat step 4 and step 5 for all the remaining nodes in the cluster.

To configure a zone under VCS control using the hazonesetup utility when the zone root is on shared storage

- 1 Configure a failover service group with required storage resources (DiskGroup, Volume, Mount, etc.) to mount the zone root on the node. Set the required dependency between storage resources (DiskGroup->Volume->Mount).

```
sysA# hagrps -add zone_grp
sysA# hares -add zone_dg DiskGroup zone_grp
sysA# hares -add zone_vol Volume zone_grp
sysA# hares -add zone_mnt Mount zone_grp
sysA# hares -link zone_mnt zone_vol
sysA# hares -link zone_vol zone_dg
```

- 2 Bring the service group online on first node. This mounts the zone root on first node.

```
sysA# hagrps -online zone_grp -sys sysA
```

- 3 Boot the local zone on first node outside VCS.

```
sysA# zoneadm -z local-zone boot
```

- 4 Run hazonesetup with correct arguments on the first node. Use the service group configured in step 1. This adds the zone resource to VCS configuration.

```
sysB# hazonesetup -g zone_grp -r zone_res -z local-zone \
-p password -a -s sysA,sysB
```

Note: If you want to use a particular user for password-less communication use `-u` option of the `hazonesetup` command. If `-u` option is not specified a default user is used for password-less communication.

- 5 Set the proper dependency between the Zone resource and other storage resources. The Zone resource should depend on storage resource (Mount->Zone).

```
sysA# hares -link zone_res zone_mnt
```

- 6 Switch the service group to next node in the cluster.

```
sysA# hagrps -switch zone_grp -sys sysB
```

- 7 Run the `hazonesetup` utility with correct arguments on the node. The `hazonesetup` utility detects that the service group and the zone resource are already present in VCS configuration and update the configuration accordingly for password-less communication.

```
sysB# hazonesetup -g zone_grp -r zone_res -z local-zone\  
-p password -a -s sysA,sysB
```

- 8 Repeat step 6 and step 7 for all the remaining nodes in the cluster

Configuring zone resource in a parallel service group with the `hazonesetup` utility

The `hazonesetup` utility helps you configure a zone under VCS. This section covers typical scenarios based on the location of the zone root.

In the case of a zone resource in parallel service group, the zone root can be on local or shared storage that the node owns.

Consider an example in a two-node cluster (`sysA` and `sysB`). Zone `local-zone1` is configured on `sysA` and `local-zone2` is configured on `sysB`.

To configure a zone under VCS control using `hazonesetup` utility when the zone root is on local storage

- 1 Boot the local zone on all the nodes outside VCS.

```
sysA# zoneadm -z local-zone1 boot
sysB# zoneadm -z local-zone2 boot
```

- 2 Run the `hazonesetup` utility with correct arguments on all the nodes successively.

```
sysA# hazonesetup -g zone_grp -r zone_res -z local-zone1\
-p password -a -l -s sysA,sysB
sysB# hazonesetup -g zone_grp -r zone_res -z local-zone2\
-p password -a -l -s sysA,sysB
```

Note: If you want to use a particular user for password-less communication use `-u` option of the `hazonesetup` command. If `-u` option is not specified a default user is used for password-less communication.

- 3 Running `hazonesetup` on first node adds parallel zone service group and zone resource in VCS configuration. Running `hazonesetup` on other nodes detect that the zone service group and zone resource are already present in VCS configuration and update the configuration accordingly for password-less communication.

Note: Run the `hazonesetup` utility on all the nodes in the cluster that have a zone running on that node. This is required as `hazonesetup` runs the `halogin` command inside the local zone that enables password-less communication between local zone and global zone.

You can use the same user for multiple zones across systems. Specify the same user name using the `-u` option while running `hazonesetup` utility for different zones on different systems. When you do not specify a user name while running `hazonesetup` utility, the utility creates a user with the default user name `z_resname_hostname` for a non-secure cluster and `z_resname_clustername` for a secure cluster.

Configuring multiple zone resources using same VCS user for password less communication

The `hazonesetup` utility helps you configure multiple zones under VCS, which are using same VCS user for password less communication between non-global zone and global zone.

Consider an example in a two-node cluster (sysA and sysB). Zones local-zone1 and local-zone2 are configured on both the nodes.

To configure zones under VCS control in failover mode using the `hazonesetup` utility when the zone root is on local storage

- 1 Boot the local zones on first node outside VCS.

```
sysA# zoneadm -z local-zone1 boot
sysA# zoneadm -z local-zone2 boot
```

- 2 Run the `hazonesetup` utility with the correct arguments on the first node. This adds failover zone service group, zone resource in VCS configuration, configures same VCS user (zone_user) to be used for password less communication between non-global zone, and global zone.

```
sysA# hazonesetup -g zone1_grp -r zone1_res -z local-zone1\
-u zone_user -p password -a -s sysA,sysB
sysA# hazonesetup -g zone2_grp -r zone2_res -z local-zone2\
-u zone_user -p password -a -s sysA,sysB
```

- 3 Switch the zone service group to next node in the cluster.

```
sysA# hagrp -switch zone_grp -sys sysB
```

- 4 Run the `hazonesetup` utility with correct arguments on the node. The `hazonesetup` utility detects that the zone service group, zone resource are already present in VCS configuration, and update the configuration accordingly for password-less communication.

```
sysB# hazonesetup -g zone1_grp -r zone1_res -z local-zone1\
-u zone_user -p password -a -s sysA,sysB
sysB# hazonesetup -g zone2_grp -r zone2_res -z local-zone2\
-u zone_user -p password -a -s sysA,sysB
```

- 5 Repeat step 3 and step 4 for all the remaining nodes in the cluster.

Modifying the service group configuration

Perform the following procedure to modify a service group's configuration.

To modify the configuration to manage a zone

1 Run the `hazonesetup` script to set up the zone configuration.

```
# hazonesetup [-t] -g sg_name -r res_name -z zone_name\  
[-u user_name] -p password [-a] [-l] -s systems
```

Where the values are:

- t Updates the password for the VCS zone user.
- g *sg_name* Name of the zone service group to be created in VCS configuration.
- r *res_name* Name of the zone resource to be created in VCS configuration.
- z *zone_name* Name of the zone that is configured on the system.
- u *user_name* Name of the VCS user used for password less communication between the local zone and the global zone. If no username is specified the default username is used.
- p *password* Password for the VCS user used for password less communication. If Symantec Authentication Service is enabled, the password should be at least six characters long.
- a Populate AutoStartList for the group.
- l Configure a parallel service group. If you do not specify the -l option, a failover service group is created by default.
- s *systems* A comma separated list of systems where the zone service group need to be configured, for example: sys1,sys2,sys3.

If the application service group does not exist, the script creates a service group.

The script adds a resource of type Zone to the application service group. The script logs in to the zone and runs the `halogin` command. It also creates a user account with group administrative privileges to enable password less communication between global zone and local zone for VCS.

2 Modify the resource dependencies to reflect your zone configuration. See the resource dependency diagrams for more information.

See [“Configuring the service group for the application”](#) on page 32.

3 Save the service group configuration and bring the service group online.

Verifying the zone configuration

Run the `hazoneverify` command to verify the zone configuration.

The command verifies the following requirements:

- The systems hosting the service group have the required operating system to run zones.
- The service group does not have more than one resource of type Zone.
- The dependencies of the Zone resource are correct.

To verify the zone configuration

- 1 If you use custom agents make sure the resource type is added to the `APP_TYPES` or `SYS_TYPES` environment variable.

See “[Using custom agents in zones](#)” on page 28.

- 2 Run the `hazoneverify` command to verify the zone configuration.

```
# hazoneverify servicegroup_name
```

Performing maintenance tasks

Perform the following maintenance tasks as necessary:

- Make sure that the zone configuration files are consistent on all the nodes at all times. The file is located at `/etc/zones/zone_name.xml`.
- When you add a patch or upgrade the operating system on one node, make sure to upgrade the software on all nodes.
- Make sure that the application configuration is identical on all nodes. If you update the application configuration on one node, apply the same updates to all nodes.

To update password of VCS user used for password less communication

- 1 Run the `hazonesetup` utility with correct arguments on the node where Zone resource is online.

```
sysA# hazonesetup -t -g zone_grp -r zone_res -z local-zone\  
-u zoneuser -p new_password -a -s sysA,sysB
```

- 2 Switch the zone service group to next node in the cluster.

```
sysA# hagrp -switch zone_grp -sys sysB
```

- 3 Run the `hazonesetup` utility with correct arguments on the node.

```
sysB# hazonesetup -t -g zone_grp -r zone_res -z local-zone\  
-u zoneuser -p new_password -a -s sysA,sysB
```

- 4 Repeat step 2 through step 3 for all the remaining nodes in the cluster.

Troubleshooting zones

Use following information to troubleshoot VCS and zones:

- VCS HA commands do not work.

Recommended actions:

- Verify the VCS packages are installed.
- Run the `halogin` command from the zone.
For more information on the `halogin` command, refer to the *Veritas Cluster Server Administrator's Guide*.
- Verify your VCS credentials. Make sure the password is not changed.
- Verify the VxSS certificate is not expired.
- Resource does not come online in the zone.


Recommended actions:

- Verify VCS and the agent packages are installed correctly.
- Verify the application is installed in the zone.
- Verify the configuration definition of the agent.

Configuring for physical to virtual and virtual to physical failovers—a typical setup

In this configuration, you have two physical nodes. One node runs Solaris without zones configured (`sysA`) and another node runs Solaris with zones configured (`sysB`).

Figure 2-5 An application service group that can fail over into a zone and back



In the `main.cf` configuration file, define the container name, type of container, and whether it is enabled or not in the service group definition.

```
ContainerInfo@sysA = {Name = Z1, Type = Zone, Enabled = 2}
ContainerInfo@sysB = {Name = Z1, Type = Zone, Enabled = 1}
```

On `sysA`, set the value of `Enabled` to 2 to ignore zones so that the application runs on the physical system. When the service group fails over to `sysB`, the application runs inside the zone after the failover because `Enabled` is set to 1 on `sysB`. The application can likewise fail over to `sysA` from `sysB`.

When `ContainerInfo::Enabled` is set to 2, the `Zone` agent reports resource state based on state of the corresponding group.

IMF monitoring must be disabled on the node where `ContainerInfo::Enabled` is set to 2 (`sysA` in this example).

- ◆ To disable IMF monitoring, set the `Mode` key of IMF attribute to 0:

```
# hares -override zone_res IMF
# hares -local zone_res IMF
# hares -modify zone_res IMF Mode 0 MonitorFreq 5 \
RegisterRetryLimit 3 -sys sysA
```

VCS limitations with Solaris zones

- Currently VCS does not support mounting of VxFS file system directly inside non-global zone with `Mount` resource.
- CFS is not supported as Zone root file system.

Adding VxFS file systems to a non-global zone

VxFS file systems that were previously created in the global zone can be made available in the non-global zone using a loopback file system mount. This functionality is especially useful when the sole purpose of making the file system available in the non-global zone is to share access of this file system with one or more non-global zones. For example, if a configuration file is available in a particular file system and this configuration file is required by the non-global zone, then the file system can be shared with the non-global zone using a loopback file system mount.

The following commands share access of file system `/mnt1` as a loopback file system mount with an existing non-global zone `newzone`:

```
# zonecfg -z newzone
zonecfg:newzone> add fs
zonecfg:newzone:fs> set dir=/mnt1
zonecfg:newzone:fs> set special=/mnt1
zonecfg:newzone:fs> set type=lofs
zonecfg:newzone:fs> end
zonecfg:newzone> verify
zonecfg:newzone> commit
zonecfg:newzone> exit
```

The value of `dir` is a directory in the non-global zone. The value of `special` is a directory in the global zone to be mounted in the non-global zone.

Caution: Sharing file systems with non-global zones through a loopback file system mount makes the file system available for simultaneous access from all the non-global zones. This method should be used only when you want shared read-only access to the file system.

Direct mount of VxFS file systems from global zone

Exclusive access of a VxFS file system can be delegated to a non-global zone by direct mounting the file system in the non-global zone. Using direct mounts limits the visibility of and access to the file system to only the non-global zone that has direct mounted this file system.

See [“Mounting a VxFS file system in a non-global zone”](#) on page 46.

See [“Adding a direct mount to a zone's configuration”](#) on page 47.

See [“Creating VxFS file systems inside non-global zones”](#) on page 47.

Mounting a VxFS file system in a non-global zone

To direct mount a VxFS file system in a non-global zone, the directory to mount must be in the non-global zone and the mount must take place from the global zone. The following procedure mounts the directory `dirmnt` in the non-global zone `newzone` with a mount path of `/zonedir/newzone/root/dirmnt`.

Note: VxFS entries in the global zone `/etc/vfstab` file for non-global zone direct mounts are not supported, as the non-global zone may not yet be booted at the time of `/etc/vfstab` execution.

Once a file system has been delegated to a non-global zone through a direct mount, the mount point will be visible in the global zone through the `mount` command, but not through the `df` command.

To direct mount a VxFS file system in a non-global zone

- 1 Log in to the zone and make the mount point:

```
global# zlogin newzone
newzone# mkdir dirmnt
newzone# exit
```

- 2 Mount the file system from the global zone:

- Non-cluster file system:

```
global# mount -F vxfs /dev/vx/dsk/dg/vol1 /zonedir/zone1\
/root/dirmnt
```

- Cluster file system:

```
global# mount -F vxfs -o cluster /dev/vx/dsk/dg/vol1 \
/zonedir/zone1/root/dirmnt
```

- 3 Log in to the non-global zone and ensure that the file system is mounted:

```
global# zlogin newzone
newzone# df | grep dirmnt
/dirmnt (/dirmnt):142911566 blocks 17863944 files
```

Adding a direct mount to a zone's configuration

A non-global zone can also be configured to have a VxFS file system direct mount automatically when the zone boots using `zonecfg`. The `fsck` command is run, before the file system is mounted. If the `fsck` command fails, the zone fails to boot.

To add a direct mount to a zone's configuration

1 Check the status and halt the zone:

```
global# zoneadm list -cv
  ID NAME           STATUS      PATH                BRAND  IP
   0 global          running     /                   solaris shared
   1 myzone         running     /zone/myzone       solaris shared
global# zoneadm -z myzone halt
```

2 Boot the zone:

```
global# zoneadm -z myzone boot
```

3 Log in to the non-global zone and enable `vxfsldlic` service:

```
myzone# svcadm enable vxfsldlic
```

4 Ensure that the file system is mounted:

```
myzone# df | grep dirmnt
/dirmnt (/dirmnt):142911566 blocks 17863944 files
```

Creating VxFS file systems inside non-global zones

You can create a VxFS file system inside of a non-global zone.

To create the VxFS file system inside of a non-global zone

1 Check the zone status and halt the zone:

```
global# zoneadm list -cv
ID NAME          STATUS      PATH                                BRAND  IP
0 global         running    /                                    solaris shared
1 myzone        running    /zone/myzone                       solaris shared
global# zoneadm -z myzone halt
```

2 Add devices to the zone's configuration:

```
global# zonecfg -z myzone
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/vxportal
zonecfg:myzone:device> end
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/fdd
zonecfg:myzone:device> end
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/vx/rdisk/dg_name/vol_name
zonecfg:myzone:device> end
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/vx/dsk/dg_name/vol_name
zonecfg:myzone:device> end
zonecfg:myzone> add fs
zonecfg:myzone:fs> set dir=/etc/vx/licenses/lic
zonecfg:myzone:fs> set special=/etc/vx/licenses/lic
zonecfg:myzone:fs> set type=lofs
zonecfg:myzone:fs> end
zonecfg:myzone> verify
zonecfg:myzone> commit
zonecfg:myzone> exit
```

3 On Solaris 11, you must set fs-allowed=vxfs,odm to the zone's configuration:

```
global# zonecfg -z myzone
zonecfg:myzone> set fs-allowed=vxfs,odm
zonecfg:myzone> commit
zonecfg:myzone> exit
```

If you want to use ufs, nfs and zfs inside the zone, set fs-allowed=vxfs,odm,nfs,ufs,zfs.

4 Boot the zone:

```
global# zoneadm -z myzone boot
```

5 Login to the non-global zone and create the file system inside the non-global zone:

```
global# zlogin myzone  
myzone# mkfs -F vxfs /dev/vx/rdisk/dg_name/vol_name
```

6 Create a mount point inside the non-global zone and mount it:

```
myzone# mkdir /mnt1  
myzone# mount -F vxfs /dev/vx/dsk/dg_name/vol_name /mnt1
```

Mounting a VxFS file system as a cluster file system from the non-global zone is not supported.

Veritas Storage Foundation Cluster File System mounts

Veritas Storage Foundation Cluster File System (SFCFS) provides support for the same file system to be made available from multiple nodes that have been grouped together as a cluster. VxFS supports the sharing or delegation of cluster-mounted file systems in the non-global zone.

Note: Creating a non-global zone root on CFS is not supported. However, a non-global zone can be created on VxFS for Solaris 10 systems.

See [“Direct mount of VxFS file systems from global zone”](#) on page 45.

Note: CFS is not supported as Zone root file system.

The requirements to support SFCFS in non-global zones parallels that of SFCFS support in global zones. Some key points are as follows:

- Both lofs and direct mount are supported; Symantec recommends direct mount.
- The device must be visible and shared on all nodes.
- The zone configuration must be the same on all nodes. The zone name can be different.

Mounting a VxFS file system as a cluster file system from the non-global zone is not supported.

Support for SFCFS in a non-global zone is available in Veritas File System 5.0 Maintenance Pack 1 and later.

To direct mount a VxFS file system as a cluster file system in a non-global zone

- 1 Log in to the zone and make the mount point:

```
global# zlogin newzone  
newzone# mkdir dirmnt  
newzone# exit
```

- 2 Mount the file system from the global zone.

Cluster File System:

```
global# mount -F vxfs -o cluster /dev/vx/dsk/dg/vol1 \  
/zonedir/zone1/root/dirmnt
```

Note: It is not possible to make SFCFS cluster between different non-global zones of the same node.

Note: CFS file system should not be used as a part of non-global zone configuration. It should be used through VCS as a part of `main.cf` configuration or it should be mounted manually from global zone. If using LOFS to mount the CFS filesystem within the non global zone, then do not use any CFS file system related options in the zone configuration since the CFS file system will already be mounted in the global zone.

Concurrent I/O access in non-global zones

Concurrent I/O allows multiple processes to read from or write to the same file without blocking other `read(2)` or `write(2)` calls. POSIX semantics requires `read` and `write` calls to be serialized on a file with other `read` and `write` calls.

Concurrent I/O is generally used by applications that require high performance for accessing data and do not perform overlapping writes to the same file.

Veritas Storage Foundation supports concurrent I/O for applications running in the non-global zones as well. This implies that a process in a non-global zone can access the file concurrently with other processes in the global or non-global zone.

The application or running threads are responsible for coordinating the write activities to the same file when using Concurrent I/O.

An application must perform the following activities to enable the concurrent I/O advisory on a file:

```
fd=open(filename, oflag)
ioctl(fd, VX_SETCACHE, VX_CONCURRENT)
write(fd, buff, numofbytes)
```

Veritas extension for Oracle Disk Manager

The Veritas extension for Oracle Disk Manager (ODM) is specifically designed for Oracle9i or later to enhance file management and disk I/O throughput. The features of Oracle Disk Manager are best suited for databases that reside in a Veritas File System. Oracle Disk Manager allows Oracle9i or later users to improve database throughput for I/O intensive workloads with special I/O optimization.

The Veritas extension for Oracle Disk Manager is supported in non-global zones. To run Oracle 11g Release 2 on a non-global zone and use Oracle Disk Manager, the Oracle software version must be 11.2.0.3.

Care must be taken when installing and removing packages when working with the VRTSodm package, for more information refer to the following:

- See [“Package installation in non-global zones”](#) on page 95.
- See [“Package removal with non-global zone configurations ”](#) on page 95.

The following procedure enables Oracle Disk Manager file access from non-global zones with Veritas File System.

To enable Oracle Disk Manager file access from non-global zones with Veritas File System

- 1 Make global zone licenses visible to the non-global zone by exporting the `/etc/vx/licenses/lic` directory to the non-global zone as a lofs:

```
global# zonecfg -z myzone
zonecfg:myzone> add fs
zonecfg:myzone:fs> set dir=/etc/vx/licenses/lic
zonecfg:myzone:fs> set special=/etc/vx/licenses/lic
zonecfg:myzone:fs> set type=lofs
zonecfg:myzone:fs> end
zonecfg:myzone> commit
```

- 2 Halt the zone:

```
global# zoneadm -z myzone halt
```

- 3 On Solaris 10, you must boot the zone:

```
global# zoneadm -z myzone boot
```

- 4 On Solaris 10, create the `/dev/odm` directory inside the non-global zone from global zone using complete path of non-global zone.

```
global# mkdir -p /zones/myzone/dev/odm
```

- 5 On Solaris 11, you must make global zone `/dev/odm` visible to the non-global zone by exporting the `/dev/odm` directory to the non-global zone:

```
global# zonecfg -z myzone
zonecfg: myzone
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/odm
zonecfg:myzone:device> end
zonecfg:myzone:device> commit
```

- 6 On Solaris 11, you must boot the zone:

```
global# zoneadm -z myzone boot
```

- 7 To display the output from the `df` command:

```
# df | grep dirmnt
/dirmnt    (/dev/vx/dsk/ngsf45/vol1):62761756 blocks  7845216 files
```

Exporting VxVM volumes to a non-global zone

A volume device node can be exported for use in non-global zone using the `zonecfg` command. The following procedure makes a volume `vol1` available in the non-global zone `myzone`.

Caution: Exporting raw volumes to non-global zones has implicit security risks. It is possible for the zone administrator to create malformed file systems that could later panic the system when a mount is attempted. Directly writing to raw volumes, exported to non-global zones, and using utilities such as `dd` can lead to data corruption in certain scenarios.

To export VxVM volumes to a non-global zone

- 1 Create a volume `vol1` in the global zone:

```
global# ls -l /dev/vx/rdisk/rootdg/vol1
crw----- 1 root  root  301, 102000 Jun  3
12:54 /dev/vx/rdisk/rootdg/vol1crw----- 1 root  sys  301, 10200
0 Jun  3 12:54 /devices/pseudo/vxio@0:rootdg,vol1,102000,raw
```

- 2 Add the volume device `vol1` to the non-global zone `myzone`:

```
global# zonecfg -z myzone
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/vx/rdisk/mydg/vol1
zonecfg:myzone:device> end
zonecfg:myzone> commit
```

- 3 Ensure that the devices will be seen in the non-global zone:

```
global# zoneadm -z myzone halt
global# zoneadm -z myzone boot
```

- 4 Verify that `/myzone/dev/vx` contains the raw volume node and that the non-global zone can perform I/O to the raw volume node.

The exported device can now be used for performing I/O or for creating file systems.

VxVM devices in Oracle Solaris global zones

On the Oracle Solaris operating environment, there are two physical nodes corresponding to each volume node entry, `/devices` and `/dev`, respectively, with the same major and minor number. The physical nodes appear as follows:

```
/devices raw volume node : /devices/pseudo/vxio@0:
    dgname,volname,minor_number,raw
/devices block volume node : /devices/pseudo/vxio@0:
    dgname,volname,minor_number,blk
/dev raw volume node : /dev/vx/rdisk/dgname/volumename
/dev block volume node : /dev/vx/dsk/dgname/volumename
```

The following example provides sample values in `/devices`:

```
ls -l /devices/pseudo/vxio*vol1*
brw----- 1 root    sys      302, 66000 Mar 25
17:21 /devices/pseudo/vxio@0:mydg,vol1,66000,blk
crw----- 1 root    sys      302, 66000 Mar 25
17:21 /devices/pseudo/vxio@0:mydg,vol1,66000,raw
```

The following example provides sample values in `/dev`:

```
ls -l /dev/vx/*dsk/mydg/vol1
brw----- 1 root    root     302, 66000 Mar 25 17:21 /dev/vx/dsk/mydg/vol1
crw----- 1 root    root     302, 66000 Mar 25 17:21 /dev/vx/rdisk/mydg/vol1
```

Removing a VxVM volume from a non-global zone

The following procedure removes a VxVM volume from a non-global zone.

To remove a VxVM volume from a non-global zone

- ◆ Remove the volume device `vol1` from the non-global zone `myzone`:

```
global# zonecfg -z myzone
zonecfg:myzone> remove device match=/dev/vx/rdisk/rootdg/vol1
zonecfg:myzone> end
zonecfg:myzone> commit
```

About SF Oracle RAC support for Oracle RAC in a zone environment

This release supports the installation and configuration of two non-global zones in each global zone. The SF Oracle RAC cluster must comprise non-global zones from different global zones.


Note: SF Oracle RAC does not support a cluster formed of non-global zones from the same global zone.

SF Oracle RAC and the necessary agents run in the global zone. Oracle RAC runs in the non-global zone. You must configure non-global zones with an exclusive-IP zone. The exclusive-IP zone does not share the network interface with global-zone.

Using SF Oracle RAC, you can start, stop, and monitor a non-global zone and provide high availability to Oracle RAC instances inside the non-global zone.

[Figure 2-6](#) illustrates the SF Oracle RAC configuration in a zone environment.

Figure 2-6 SF Oracle RAC with Oracle RAC in a zone environment



Supported configuration

The configuration supported by SF Oracle RAC for a zone environment is as follows:

Architecture	Solaris SPARC systems
Oracle RAC version	11.2.0.3
Operating system version	Refer to <i>Veritas Storage Foundation for Oracle RAC Release Notes</i> for the supported OS versions.
Zone IP address type	Exclusive IP zone

Note: For exclusive IP zone, you need a minimum of three network interfaces for each non-global zone, one as public link and two as private links.

Note: All private interfaces inside a non-global zone must be configured under LLT as private interfaces. If you plan to have only one non-global zone cluster across global zones, it is recommended that the private interfaces configured for a non-global zone be exactly the same in name and total number as those which have been used for LLT configuration in the global zone. However, if you configure a subset of LLT interfaces as private interfaces in non-global zones, Oracle Clusterware will take cluster reconfiguration decisions in the event of network partition.

Known issues with supporting SF Oracle RAC in a zone environment

This section describes the known issues in supporting SF Oracle RAC in a zone environment.

Issue with VCS agents

If the host name of the non-global zone is different from the name of the non-global zone, you may observe unexpected behavior with the VCS agents configured for the non-global zone.

Workaround: Ensure that the host name of the non-global zone is the same as the name of the non-global zone.

Stopping non-global zones configured with direct-mount file systems from outside VCS causes the corresponding zone resource to fault or go offline

Stopping non-global zones, which are configured with direct-mount file systems, from outside VCS causes the corresponding zone resource to fault or to go offline. The status of the zone shows `down` and the corresponding zone resource faults or goes offline. As a result, VCS cannot bring the zone resource online.

Workaround:

1. Log into the global zone as the root user.
2. Unmount the CFS mount points that were in use by the zone and are still mounted:

```
# umount -o mntunlock=VCS /mount_point
```

3. Stop the zone:

```
# zoneadm -z zone_name halt
```

This changes the status of the non-global zone to `installed` or `configured`.

Error message displayed for PrivNIC resource if zone is not running

If the PrivNIC resource is configured for a zone in a non-global zone environment and the respective zone is not running, the following error message is displayed in the VCS engine log file `/var/VRTSvcs/log/engine_*.log`:

```
VCS ERROR V-16-20035-0 (sys1)
PrivNIC:ora_priv:monitor:Zone [zone1] not running.
```

Warning messages displayed when VCS restarts

When you restart VCS, the following warning message is displayed before the multi-user services inside a zone are started:

```
VCS WARNING V-16-10001-14056 (sys1)
Zone:vcszoneres:monitor:Zone is running without specified
milestone [multi-user-server] nline - returning offline.
```

You may safely ignore the message.

The installer log of non-global zone contains warning messages

The installer log of non-global zone contains warning messages related to the VRTS packages.

Workaround:

Before installing the new non-global zone, you must set the parent directory of `zonename` to be 755. The parent directory of the zone can be derived from the complete `zonename` by running the `dirname` command on the complete `zonename` including the `zonename`.

Issue with CFS mounts

Attempts to mount the CFS mounts on a global zone, after they are unmounted using the `hares` or `umount` command, fail with the following error if the CFS mounts on the global zone are mounted on a non-global zone as an `lofs` file system:

```
VCS WARNING V-16-20011-5508 (sys1)
CFSMount:ocrvote_mnt:online:Mount Error :
UX:vxfs mount: ERROR: V-3-21264:
/dev/vx/dsk/ocrvotedg/ocrvotevol is already mounted,
/ocrvote is busy, allowable number
of mount points exceeded
```

Workaround:

Perform the following steps to resolve the issue:

1. Log into the global zone as the root user.
2. View the CFS and lofs mounts that are unmounted on the global zone:

```
# cat /etc/mnttab |grep mount_point
```

For example:

```
# cat /etc/mnttab |grep ocrvote/ocrvote \  
/zonevol/sys1_zone1/root/ocrvote lofs \  
dev=53859d8 12971587943
```

3. Unmount the CFS and lofs mounts:

```
# umount /zonevol/sys1_zone1/root/mount_point
```

4. Check if there are any active CFS and lofs mounts:

```
# cat /etc/mnttab |grep mount_point
```

5. Mount the CFS and lofs mounts in one of the following ways on the global zone.

Using hares command:

```
# hares -online res_name -sys sys_name
```

Manually:

```
# mount -F vxfs -o cluster /dev/vx/dsk/  
dg_name/vol_name /mount_point
```

6. Verify if the CFS mounts are mounted successfully:

```
# cat /etc/mnttab |grep mount_point
```

For example:

```
# cat /etc/mnttab |grep ocrvote/dev/vx/dsk/ocrvotedg/ocrvotevol \  
/ocrvote vxfsrw,suid,delaylog,largefiles,qio,cluster,\  
ioerror=mdisable,crw,dev=53859d8 1297159501
```

Setting up an SF Oracle RAC cluster with Oracle RAC on non-global zones

Setting up an SF Oracle RAC cluster with Oracle RAC on non-global zones involves the following steps:

1. Prepare to install non-global zones.
See [“Preparing to install non-global zones”](#) on page 61.
2. Install non-global zones.
See [“Installing non-global zones”](#) on page 66.
3. Create SF Oracle RAC configuration files inside non-global zones.
See [“Creating SF Oracle RAC configuration files inside non-global zones”](#) on page 67.
4. Enable Oracle Disk Manager file access from non-global zones with Veritas File System.
See [“Enabling Oracle Disk Manager file access from non-global zones with Veritas File System”](#) on page 67.
5. Configure high availability for non-global zones.
See [“Configuring high availability for non-global zones”](#) on page 68.
6. Configure the cluster name for clustering non-global zones.
See [“Configuring the cluster name for clustering non-global zones”](#) on page 69.
7. Install Oracle RAC in non-global zones.
See [“Installing Oracle RAC inside the non-global zones”](#) on page 70.
8. Link the ODM library.
See [“Linking the ODM library”](#) on page 70.
9. Create the Oracle database.
See [“Creating the Oracle database”](#) on page 70.
10. Configure the non-global zones under VCS.
See [“Configuring non-global zones under VCS”](#) on page 71.

Preparing to install non-global zones

Note: Ensure that the host name of the non-global zone is the same as the name of the non-global zone. If this convention is violated, you may observe unexpected behavior with the VCS agents configured for the non-global zone.

Perform the following preparatory tasks:

1. Create non-global zones.

For instructions, see the *System Administration Guide: Solaris Containers - Resource Management and Solaris Zones* document.

2. After creating non-global zones, set the zone path.

For example:

```
# zonecfg -z sys1_zone1
zonecfg:sys1_zone1> set zonepath=/zone/sys1_zone1
zonecfg:sys1_zone1> commit
```

where `sys1_zone1` is the name of the non-global zone and `/zone/sys1_zone1` is the zone path.

3. Update the file system configuration for non-global zones by adding the following SF Oracle RAC directories as loop-back mounts:

`/opt` (For accessing SF Oracle RAC binaries)

`/usr/local/bin` (For Oracle utilities)

`/etc/vx/licenses/lic` (For SF Oracle RAC licenses)

For example:

```
sys1#zonecfg:sys1_zone1> add fs
sys1#zonecfg:sys1_zone1:fs>set dir=/opt
sys1#zonecfg:sys1_zone1:fs>set special=/opt
sys1#zonecfg:sys1_zone1:fs>set type=lofs
sys1#zonecfg:sys1_zone1:fs>end
sys1#zonecfg:sys1_zone1> add device
sys1#zonecfg:sys1_zone1:fs>set match=/dev/vxportal
sys1#zonecfg:sys1_zone1:fs>end
sys1#zonecfg:sys1_zone1> add device
sys1#zonecfg:sys1_zone1:fs>set match=/dev/fdd
sys1#zonecfg:sys1_zone1:fs>end
sys1#zonecfg:sys1_zone1> add device
sys1#zonecfg:sys1_zone1:fs>set match=/dev/odm
```

```
sys1#zonecfg:sys1_zone1:fs>end  
sys1#zonecfg:sys1_zone1>commit
```

4. Configure non-global zones to use network interfaces from global zones.
See [“Configuring non-global zones to use network interfaces from global zones”](#) on page 62.
5. Plan the storage for Oracle Cluster Registry, voting disk, and data files.
See [“Planning the storage for Oracle Cluster Registry, voting disk, and data files”](#) on page 63.
6. Configure non-global zones to use devices from global zones.
See [“Configuring non-global zones to use devices from global zones”](#) on page 65.
7. Revise the default set of privileges for non-global zones.
See [“Revising the default set of privileges for non-global zones”](#) on page 66.

Configuring non-global zones to use network interfaces from global zones

Configure the non-global zone to use the network interfaces from the global zone. This is done by adding the required network interfaces to the non-global zones. The interfaces are made available to the zone after the zone is installed and booted.

Note: If you have installed two non-global zones in each global zone, ensure that you do not use the same interface on both non-global zones.

To configure non-global zones to use network interfaces from global zones

- 1 Log into each global zone as the root user.
- 2 Configure the non-global zone:

```
# zonecfg -z sys1_zone1
```

3 Create an exclusive IP zone:

```
# set ip-type=exclusive
```

4 Add the network interfaces to the non-global zone from the global zone.

The following is a sample configuration:

```
# zonecfg:sys1_zone1>add net
# zonecfg:sys1_zone1:net>set physical=bge1
# zonecfg:sys1_zone1:net>end
# zonecfg:sys1_zone1:>commit
```

Planning the storage for Oracle Cluster Registry, voting disk, and data files

There are two ways to make global zone file system visible to non-global zones:

- Loop back mount through zone configuration
- Direct mount under non-global zones root directory

[Table 2-2](#) describes the mount types.

Table 2-2 Mount types

Mount types	Description
Loop back mount through zone configuration	<p>A loopback file system allows mounting of directories from the global zone to a non-global zone in read-write mode. Any changes made to the directories in the non-global zone reflect on the global zone. Similarly, changes made to the directories in the global zone reflect on the non-global zone.</p> <p>Mount the following directories as loopback mounts:</p> <ul style="list-style-type: none"> ■ /ocrvote (For OCR and voting disk files) ■ /oradata (For data files) <p>Oracle RAC directories must be mounted separately as needed. See the Oracle documentation for instructions.</p> <p>Note: If you want to use the database mounts from the global zone as loopback mounts in non-global zones, add them as loopback mounts.</p> <p>The following configuration steps illustrate a loopback-mounted file-system configuration for /ocrvote:</p> <pre> sys1#zonecfg:sys1_zone1> add fs sys1#zonecfg:sys1_zone1:fs>set dir=/ocrvote sys1#zonecfg:sys1_zone1:fs>set special=/ocrvote sys1#zonecfg:sys1_zone1:fs>set type=lofs sys1#zonecfg:sys1_zone1:fs>end sys1#zonecfg:sys1_zone1>commit </pre>
Direct mount under non-global zones root directory	<p>Performing a direct mount of storage under the non-global zones root directory makes it available to non-global zones without adding those directories in the zone configuration.</p> <p>You can direct-mount directories such as /ocrvote, /oradata and database data mounts.</p> <p>For example:</p> <pre> # mount -F vxfs -o cluster /dev/vx/dsk/ocrvotedg/ocrvotevol \ /zone/sys1_zone1/root/ocrvote </pre>

Set the CVMVolDg resource attribute `CVMDeactivateOnOffline` to 1 for the shared disk groups that are created for data files.

For example:


```
# haconf -makerw
# hares -modify ocrvote_voldg CVMDeactivateOnOffline 1
# haconf -dump -makero
```

Configuring non-global zones to use devices from global zones

On Solaris 10, add the following devices from the global zone to the non-global zone:

- /dev/llt
- /dev/vcsmm
- /dev/lmx
- /dev/vxportal
- /dev/fdd
- /dev/gab/*
- /dev/nic_name

where *nic_name* is the name of the network interface, for example, /dev/bge1.

Ensure that you include all the public and private network interfaces configured for each non-global zone.

On Solaris 11, add the following devices from the global zone to the non-global zone:

- /dev/llt
- /dev/odm
- /dev/vcsmm
- /dev/lmx
- /dev/vxportal
- /dev/fdd
- /dev/gab/*
- /dev/nic_name

where *nic_name* is the name of the network interface, for example, /dev/bge1.

Ensure that you include all the public and private network interfaces configured for each non-global zone.

For example, the steps to add the device /dev/llt are as follows:

```
sys1# zonecfg:sys1_zone1>add device
sys1# zonecfg:sys1_zone1:device>set match=/dev/llt
```

```
sys1# zonecfg:sys1_zone1:device>end  
sys1# zonecfg:sys1_zone1:>commit
```

Revising the default set of privileges for non-global zones

Configure the following setting for Oracle Grid Infrastructure

```
sys1# zonecfg -z sys1_zone1 set limitpriv="default, \  
proc_priocntl,proc_clock_highres,sys_time"
```

For more information, see the Oracle Metalink document: 420265.1

Installing non-global zones

Note: Before installing a non-global zone, set the parent directory of zonepath to be 755. Otherwise, some of the VRTS and operating system packages will not be propagated inside the new non-global zone.

```
sys1# dirname zone_path  
sys1# chmod 755 zone_path
```

To install non-global zones

- 1 Log into each global zone as the root user.
- 2 Run the `zoneadm` command with the `install` option:

```
# zoneadm -z sys1_zone1 install  
Preparing to install zone <sys1_zone1>.  
Creating list of files to copy from the global zone.  
Copying <2443> files to the zone.  
Initializing zone product registry.  
Determining zone package initialization order.  
Preparing to initialize <1192> packages on the zone.  
Initialized <1192> packages on zone.  
Zone <sys1_zone1> is initialized.  
Installation of <12> packages was skipped.  
The file </zone/sys1_zone1/root/var/sadm/system/logs/install_log>  
contains a log of the zone installation.
```

- 3 Boot the zone:

```
# zoneadm -z zone_name boot
```

- 4 Update the `/etc/hosts` file of the global and non-global zones. Both the files must contain the IP address and host name information of the global and non-global zones.

- 5 Configure the non-global zone to run in multi-user mode.

After the non-global zone boots up, log in to the non-global zone console and configure all the required services. The following services are mandatory for SF Oracle RAC to function:

```
multi-user
multi-user-server
vxfsldlic
```

Use the following command to log in to the non-global zone console:

```
# zlogin -C sys1_zone1
```

To configure the required services, see the *System Administration Guide: Solaris Containers - Resource Management and Solaris Zones* document.

Creating SF Oracle RAC configuration files inside non-global zones

Create the `/etc/llthosts` file inside the non-global zones.

In the following example, 0 and 1 are the node IDs for the non-global zones. The node IDs must be the same as that present in the corresponding global zone file.

A sample `/etc/llthosts` file for non-global zones is as follows:

```
# cat /etc/llthosts
0 sys1_zone1
1 sys2_zone1
```

A sample `/etc/llthosts` file for global zones is as follows:

```
# cat /etc/llthosts
0 sys1
1 sys2
```

Enabling Oracle Disk Manager file access from non-global zones with Veritas File System

Perform the following steps to enable access from non-global zones.

To enable Oracle Disk Manager file access from non-global zones with Veritas File System

1 Perform this step for Solaris 10 systems:

From the global zone as the root user, create the `/dev/odm` directory in the non-global zone:

```
sys1# mkdir -p /zones/sys1_zone1/dev/odm
```

Log in to the non-global zone and start the `vxodm` service as follows:

```
sys1# zlogin sys1_zone1
sys1_zone1# svcadm enable -r vxodm
```

2 Perform this step for Solaris 11 systems:

From the global zone as the root user, export the `/dev/odm` device.

```
sys1# zoneadm -z sys1_zone1 halt
sys1# zonecfg -z sys1_zone1
sys1_zone1> add device
sys1_zone1:device> set match=/dev/odm
sys1_zone1:device> end
sys1_zone1> set fs-allowed=vxfs,odm
sys1_zone1> verify
sys1_zone1> commit
sys1_zone1> exit
sys1# zoneadm -z sys1_zone1 boot
```

Log in to the global zone and start the `vxodm` service as follows:

```
sys1# svcadm enable vxfsldlic
sys1# svcadm enable vxodm
```

Configuring high availability for non-global zones

Configure the VCS service group and resource for non-global zones.

To configure high availability for non-global zones

- ◆ Log into each global zone and set up the zone configuration:

```
# hazonesetup [-t] -g group_name -r zonerres_name -z zone_name \  
[-u] user_name -p password [-a] [-l] -s systems
```

where *group_name* is the name of the application service group.

zonerres_name is the name of the resource configured to monitor the zone.

zone_name is the name of the non-global zone.

user_name is the name of the VCS user used for passwordless communication between the non-global zone and the global zone. The default username is used if no user name is specified.

password is the password assigned to the VCS or security (Symantec Product Authentication Service) user created by the command.

-a indicates that the AutoStartList attribute for the group is populated.

-l indicates that a parallel service group is configured. If you do not specify the option, a failover service group is created by default.

systems is a comma separated list of systems on which the service group will be configured. Use this option only when you create the service group.

For example:

```
# hazonesetup -g vcszone -r vcszonerres -z sys1_zone1 -p password \  
-a -l sys1,sys2
```

If the application service group does not exist, the script creates a service group with a resource of type Zone. The script adds a resource of type Zone to the application service group. It also creates a user account with group administrative privileges to enable inter-zone communication.

Configuring the cluster name for clustering non-global zones

Create the `/etc/cluster_name` file in non-global zones and provide a unique cluster name. Use this unique cluster name when you are prompted to provide the name of the cluster during Oracle Clusterware installation.

Note: This is a critical file that must be created for supporting multiple non-global zones on a global zone. Issues may be observed if the cluster name is not provided while configuring a non-global zone.

However, make sure that you do not create the file in global zones.

Installing Oracle RAC inside the non-global zones

Install Oracle Clusterware and the Oracle database on non-global zones.

For instructions, see the Oracle documentation.

Note: Do not create the database at this stage.

Linking the ODM library

Perform the steps in the procedure on each node if the Oracle libraries are on local storage. If the Oracle libraries are installed on shared storage, copy the libraries on one node only. Use the mount command to check that the file system containing the Oracle libraries are mounted.

To link the ODM library

- 1 Log in as the Oracle user.
- 2 Change to the `$ORACLE_HOME/lib` directory:

```
sys1_zone1$ cd $ORACLE_HOME/lib
```

- 3 Back up Oracle's ODM library.

For Oracle RAC 11g:

```
sys1_zone1$ mv libodm11.so libodm11.so.`date +%m_%d_%y-%H_%M_%S`
```

- 4 Link the Veritas ODM library with Oracle's `libodm` library:

For Oracle RAC 11g:

```
sys1_zone1$ ln -s /usr/lib/sparcv9/libodm.so libodm11.so
```

- 5 Confirm that the correct ODM library is used:

```
sys1_zone1$ ldd $ORACLE_HOME/bin/oracle | grep odm
```

Note: If the library is not linked correctly, no output is displayed.

Creating the Oracle database

Create the Oracle RAC database in the non-global zone. For information, see the Oracle RAC documentation.

Configuring non-global zones under VCS

Configure the non-global zones to be managed by VCS.

To configure the non-global zones under VCS

- 1 Stop VCS:

```
# hastop -all force
```

- 2 Update the existing configuration file on one of the nodes.

Refer to the following sample configuration file to update the Oracle `main.cf` file.

See “[Sample VCS configuration with non-global zones](#)” on page 72.

- 3 Start VCS on the same node:

```
# hstart
```

- 4 Start VCS on the remaining nodes:

```
# hstart
```

- 5 Disable Oracle Clusterware from starting automatically on all non-global zones:

```
# clus_home/bin/crsctl disable crs
```

where *clus_home* is the full path to the `$CRS_HOME` or `$GRID_HOME` directory depending on the Oracle RAC version.

- 6 For administrator-managed databases that are configured under VCS control, change the management policy for the database from automatic to manual to prevent the Oracle database from starting automatically:

```
# $ORACLE_HOME/bin/srvctl modify database -d db_name -y manual
```

- 7 Set the attribute `Critical` to `1` for the `cssd` resource and the `oracle` resource:

```
# haconf -makerw  
# hares -modify resource_name Critical 1  
# haconf -dump -makero
```

If you have two or more zones running on a system, set the attribute to 1 for each `cssd` and Oracle resource.

Sample VCS configuration with non-global zones


This section illustrates sample VCS configurations for non-global zones.

- Multiple databases with loopback data mounts
See [“Multiple databases with loopback data mounts”](#) on page 72.
- Multiple databases with direct data mounts
See [“Multiple databases with direct data mounts”](#) on page 78.
- Multiple databases with loopback and direct data mounts
See [“Multiple databases on multiple non-global zones”](#) on page 83.

Multiple databases with loopback data mounts

[Figure 2-7](#) illustrates the sample configuration for multiple databases with loopback data mounts.

Figure 2-7 Multiple databases with loopback data mounts



The sample `main.cf` file for the configuration is as follows:

```
include "OracleASMTypes.cf"
include "types.cf"
include "CFSTypes.cf"
include "CRSResource.cf"
include "CVMTypes.cf"
include "MultiPrivNIC.cf"
include "OracleTypes.cf"
include "PrivNIC.cf"
```

```
cluster sfraczone (
```

```
UserNames = { admin = aLMeLG1IMhMMkUMgLJ,  
              z_vcszonereres_sys1 = INOmNKnK,  
              z_vcszonereres_sys2 = aPQoPMpM }  
Administrators = { admin }  
UseFence = SCSI3  
HacliUserLevel = COMMANDROOT  
)  
  
system sys1 (  
)  
  
system sys2 (  
)  
  
group cvm (  
  SystemList = { sys1 = 0, sys2 = 1 }  
  AutoFailOver = 0  
  Parallel = 1  
  AutoStartList = { sys1, sys2 }  
)  
  
CFSfsckd vxfsckd (  
)  
  
CVMcluster cvm_clus (  
  CVMClustName = sfraczone  
  CVMNodeId = { sys1 = 0, sys2 = 1 }  
  CVMTransport = gab  
  CVMTimeout = 200  
)  
  
CVMvxconfigd cvm_vxconfigd (  
  Critical = 0  
  CVMVxconfigdArgs = { syslog }  
)  
  
cvm_clus requires cvm_vxconfigd  
vxfsckd requires cvm_clus  
  
group db1 (  
  SystemList = { sys1 = 0, sys2 = 1 }  
  ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
```

```
ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
Parallel = 1
AutoStartList = { sys1, sys2}
Administrators = { z_vcszonereres_sys1, z_vcszonereres_sys2 }
)

Oracle oradb1 (
    Critical = 1
    Sid @sys1 = db11
    Sid @sys2 = db12
    Owner = oracle
    Home = "/oracle/11g/dbhome"
    StartUpOpt = SRVCTLSTART
    ShutDownOpt = SRVCTLSTOP
)

requires group vcszone online local firm

group db2 (
    SystemList = { sys1 = 0, sys2 = 1 }
    ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
    ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
    Parallel = 1
    AutoStartList = { sys1, sys2}
    Administrators = { z_vcszonereres_sys1, z_vcszonereres_sys2 }
)

Oracle oradb2 (
    Critical = 1
    Sid @sys1 = db21
    Sid @sys2 = db22
    Owner = oracle
    Home = "/oracle/11g/dbhome"
    StartUpOpt = SRVCTLSTART
    ShutDownOpt = SRVCTLSTOP
)

requires group vcszone online local firm

group vcszone (
    SystemList = { sys1 = 0, sys2 = 1 }
    ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
    ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
    Parallel = 1
```

```
AutoStartList = { sys1, sys2 }
Administrators = { z_vcszonerer_sys1, z_vcszonerer_sys2 }
)

Application cssd (
  Critical = 1
  StartProgram = "/opt/VRTSvcs/rac/bin/cssd-online"
  StopProgram = "/opt/VRTSvcs/rac/bin/cssd-offline"
  CleanProgram = "/opt/VRTSvcs/rac/bin/cssd-clean"
  MonitorProgram = "/opt/VRTSvcs/rac/bin/cssd-monitor"
)

CFSMount ocrvote_mnt (
  Critical = 0
  MountPoint @sys1 = "/ocrvote"
  MountPoint @sys2 = "/ocrvote"
  BlockDevice = "/dev/vx/dsk/ocrvotedg/ocrvotevol"
  MountOpt = "mincache=direct"
)

CVMVolDg ocrvote_voldg (
  Critical = 0
  CVMDiskGroup = ocrvotedg
  CVMVolume = { ocrvotevol }
  CVMActivation = sw
  CVMDeactivateOnOffline = 1
)

CFSMount oradata_mnt1 (
  Critical = 0
  MountPoint @sys1 = "/db1"
  MountPoint @sys2 = "/db1"
  BlockDevice = "/dev/vx/dsk/db1dg/db1vol"
)

CVMVolDg oradata_voldg1 (
  Critical = 0
  CVMDiskGroup = db1dg
  CVMVolume = { db1vol }
  CVMActivation = sw
  CVMDeactivateOnOffline = 1
```

```
)

CFSMount oradata_mnt2 (
    Critical = 0
    MountPoint @sys1 = "/db2"
    MountPoint @sys2 = "/db2"
    BlockDevice = "/dev/vx/dsk/db2dg/db2vol1"
)

CVMVolDg oradata_voldg2 (
    Critical = 0
    CVMDiskGroup = db2dg
    CVMVolume = { db2vol1 }
    CVMActivation = sw
    CVMDeactivateOnOffline = 1
)

PrivNIC ora_priv (
    Critical = 0
    Device @sys1 = { bge2 = 0, bge3 = 1 }
    Device @sys2 = { bge2 = 0, bge3 = 1 }
    Address @sys1 = "192.168.1.12"
    Address @sys2 = "192.168.1.13"
    NetMask = "255.255.255.0"
)


Zone vcszonerer (
)

requires group cvm online local firm
cssd requires ora_priv
cssd requires vcszonerer
ocrvote_mnt requires ocrvote_voldg
oradata_mnt1 requires oradata_voldg1
oradata_mnt2 requires oradata_voldg2
vcszonerer requires ocrvote_mnt
vcszonerer requires oradata_mnt1
vcszonerer requires oradata_mnt2
```

Multiple databases with direct data mounts

Figure 2-8 illustrates a sample configuration for multiple databases with direct data mounts.

Figure 2-8 Multiple databases with direct data mounts



The sample `main.cf` file is as follows:

```
include "OracleASMTypes.cf"
include "types.cf"
include "CFSTypes.cf"
include "CRSResource.cf"
include "CVMTypes.cf"
include "MultiPrivNIC.cf"
include "OracleTypes.cf"
include "PrivNIC.cf"

cluster sfraczone (
    UserNames = { admin = aLMeLG1IMhMMkUMgLJ,
                  z_vcszonereres_sys1 = INOmNKnK,
                  z_vcszonereres_sys2 = aPQoPMpM }
    Administrators = { admin }
    UseFence = SCSI3
    HacliUserLevel = COMMANDROOT
)

system sys1 (
)

system sys2 (
)

group cvm (
    SystemList = { sys1 = 0, sys2 = 1 }
    AutoFailOver = 0
    Parallel = 1
    AutoStartList = { sys1, sys2 }
)

CFSfsckd vxfsckd (
)

CVMcluster cvm_clus (
    CVMClustName = sfraczone
    CVMNodeId = { sys1 = 0, sys2 = 1 }
    CVMTransport = gab
    CVMTimeout = 200
)

CVMVxconfigd cvm_vxconfigd (
    Critical = 0
)
```

```
        CVMVxconfigdArgs = { syslog }
    )

cvm_clus requires cvm_vxconfigd
vxfscsd requires cvm_clus

group db1 (
    SystemList = { sys1 = 0, sys2 = 1 }
    ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
    ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
    Parallel = 1
    AutoStartList = { sys1, sys2 }
    Administrators = { z_vcszonerres_sys1, z_vcszonerres_sys2 }
)

CFSMount oradata_mnt1 (
    Critical = 0
    MountPoint @sys1 = "/zones/sys1_zone1/root/db1"
    MountPoint @sys2 = "/zones/sys2_zone1/root/db1"
    BlockDevice = "/dev/vx/dsk/db1dg/db1vol"
)

CVMVolDg oradata_voldg1 (
    Critical = 0
    CVMDiskGroup = db1dg
    CVMVolume = { db1vol }
    CVMActivation = sw
    CVMDeactivateOnOffline = 1
)

Oracle oradb1 (
    Critical = 1
    Sid @sys1 = db11
    Sid @sys2 = db12
    Owner = oracle
    Home = "/oracle/11g/dbhome"
    StartUpOpt = SRVCTLSTART
    ShutDownOpt = SRVCTLSTOP
)

requires group vcszone online local firm
oradata_mnt1 requires oradata_voldg1
```



```
oradb1 requires oradata_mnt1

group db2 (
    SystemList = { sys1 = 0, sys2 = 1 }
    ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
    ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
    Parallel = 1
    AutoStartList = { sys1, sys2 }
    Administrators = { z_vcszonereres_sys1, z_vcszonereres_sys2 }
)

CFSMount oradata_mnt2 (
    Critical = 0
    MountPoint @sys1 = "/zones/sys1_zone1/root/db2"
    MountPoint @sys2 = "/zones/sys2_zone1/root/db2"
    BlockDevice = "/dev/vx/dsk/db2dg/db2vol1"
)

CVMVolDg oradata_voldg2 (
    Critical = 0
    CVMDiskGroup = db2dg
    CVMVolume = { db2vol }
    CVMActivation = sw
    CVMDeactivateOnOffline = 1
)

Oracle oradb2 (
    Critical = 1
    Sid @sys1 = db21
    Sid @sys2 = db22
    Owner = oracle
    Home = "/oracle/11g/dbhome"
    StartUpOpt = SRVCTLSTART
    ShutDownOpt = SRVCTLSTOP
)

requires group vcszone online local firm
oradata_mnt2 requires oradata_voldg2
oradb2 requires oradata_mnt2

group vcszone (
    SystemList = { sys1 = 0, sys2 = 1 }
    ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
```

```
ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
Parallel = 1
AutoStartList = { sys1, sys2 }
Administrators = { z_vcszonerer_sys1, z_vcszonerer_sys2 }
)

Application cssd (
    Critical = 1
    StartProgram = "/opt/VRTSvcs/rac/bin/cssd-online"
    StopProgram = "/opt/VRTSvcs/rac/bin/cssd-offline"
    CleanProgram = "/opt/VRTSvcs/rac/bin/cssd-clean"
    MonitorProgram = "/opt/VRTSvcs/rac/bin/cssd-monitor"
)

CFSMount ocrvote_mnt (
    Critical = 0
    MountPoint @sys1 = "/zones/sys1_zone1/root/ocrvote"
    MountPoint @sys2 = "/zones/sys2_zone1/root/ocrvote"
    BlockDevice = "/dev/vx/dsk/ocrvotedg/ocrvotevol"
    MountOpt = "mincache=direct"
)

CVMVolDg ocrvote_voldg (
    Critical = 0
    CVMDiskGroup = ocrvotedg
    CVMVolume = { ocrvotevol }
    CVMActivation = sw
    CVMDeactivateOnOffline = 1
)

PrivNIC ora_priv (
    Critical = 0
    Device @sys1 = { bge0 = 0, bge1 = 1 }
    Device @sys2 = { bge0 = 0, bge1 = 1 }
    Address @sys1 = "192.168.1.7"
    Address @sys2 = "192.168.1.8"
    NetMask = "255.255.255.0"
)

Zone vcszonerer (
)

requires group cvm online local firm
```

```
cssd requires ocrvote_mnt  
cssd requires ora_priv  
ocrvote_mnt requires ocrvote_voldg  
ocrvote_voldg requires vcszoneress
```

Multiple databases on multiple non-global zones


Figure 2-9 illustrates a sample configuration for multiple databases (administrator-managed databases as well as policy-managed databases) on multiple non-global zones with loopback and direct data mounts.

Table 2-3 lists the loopback and direct mounts in the sample configuration.

Table 2-3 Loopback and direct mounts in the sample configuration

Type of mount	Configuration
Loopback mounts	clus2_db1 clus2_db2 ocrvote_mnt2
Direct mounts	clus1_db1 clus1_db2 ocrvote_mnt1

Figure 2-9 Multiple databases on multiple non-global zones



The sample `main.cf` file is as follows:

```
include "OracleASMTypes.cf"
include "types.cf"
include "CFSTypes.cf"
```

```
include "CRSResource.cf"
include "CVMTypes.cf"
include "MultiPrivNIC.cf"
include "OracleTypes.cf"
include "PrivNIC.cf"

cluster sfraczone (
    UserNames = { admin = aLMeLG1IMhMMkUMgLJ,
        z_vcszonerres1_sys1 = aPQoPpM,
        z_vcszonerres1_sys2 = fIJhIFiF,
        z_vcszonerres2_sys1 = HIJhIFiF,
        z_vcszonerres2_sys2 = dqrPqnQn }
    Administrators = { admin }
    UseFence = SCSI3
    HacliUserLevel = COMMANDROOT
)

system sys1 (
)

system sys2 (
)

group cvm (
    SystemList = { sys1 = 0, sys2 = 1 }
    AutoFailOver = 0
    Parallel = 1
    AutoStartList = { sys1, sys2}
)

CFSfsckd vxfsckd (
)

CVMcluster cvm_clus (
    CVMClustName = sfraczone
    CVMNodeId = { sys1 = 0, sys2 = 1 }
    CVMTransport = gab
    CVMTimeout = 200
)

CVMVxconfigd cvm_vxconfigd (
    Critical = 0
```

```
    CVMVxconfigdArgs = { syslog }
  )

cvm_clus requires cvm_vxconfigd
vxfsckd requires cvm_clus

group clus1_db1_grp (
  SystemList = { sys1 = 0, sys2 = 1 }
  ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
  ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
  Parallel = 1
  AutoStartList = { sys1, sys2}
  Administrators = { z_vcszonerres1_sys1, z_vcszonerres1_sys2}
)

CFMount oradata_mnt1 (
  Critical = 0
  MountPoint @sys1 = "/zones/sys1_zone1/root/db1"
  MountPoint @sys2 = "/zones/sys2_zone1/root/db1"
  BlockDevice = "/dev/vx/dsk/clus1_db1dg/clus1_db1vol"
)

CVMVolDg oradata_voldg1 (
  Critical = 0
  CVMDiskGroup = clus1_db1dg
  CVMVolume = { clus1_db1vol }
  CVMActivation = sw
  CVMDeactivateOnOffline = 1
)

Oracle clus1_oradb1 (
  Critical = 1
  Sid @sys1 = clus1_db11
  Sid @sys2 = clus1_db12
  Owner = oracle
  Home = "/oracle/11g/dbhome"
  StartUpOpt = SRVCTLSTART
  ShutDownOpt = SRVCTLSTOP
)

requires group vcszone1 online local firm
oradata_mnt1 requires oradata_voldg1
```

```
clus1_oradb1 requires oradata_mnt1

group clus1_db2_grp (
    SystemList = { sys1 = 0, sys2 = 1 }
    ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone, Enabled = 1 }
    ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone, Enabled = 1 }
    Parallel = 1
    AutoStartList = { sys1, sys2}
    Administrators = { z_vcszonerres1_sys1, z_vcszonerres1_sys2}
)

CFSMount oradata_mnt2 (
    Critical = 0
    MountPoint @sys1 = "/zones/sys1_zone1/root/db2"
    MountPoint @sys2 = "/zones/sys2_zone1/root/db2"
    BlockDevice = "/dev/vx/dsk/clus1_db2dg/clus1_db2vol"
)

CVMVolDg oradata_voldg2 (
    Critical = 0
    CVMDiskGroup = clus1_db2dg
    CVMVolume = { clus1_db2vol }
    CVMActivation = sw
    CVMDeactivateOnOffline = 1
)

Oracle clus1_oradb2 (
    Critical = 1
    Sid @sys1 = clus1_db21
    Sid @sys2 = clus1_db22
    Owner = o racle
    Home = "/oracle/11g/dbhome"
    StartUpOpt = SRVCTLSTART
    ShutDownOpt = SRVCTLSTOP
)

requires group vcszone1 online local firm
oradata_mnt2 requires oradata_voldg2
clus1_oradb2 requires oradata_mnt2

group vcszone1 (
    SystemList = { sys1 = 0, sys2 = 1 }
```

```
ContainerInfo @sys1 = { Name = sys1_zone1, Type = Zone,
                        Enabled = 1 }
ContainerInfo @sys2 = { Name = sys2_zone1, Type = Zone,
                        Enabled = 1 }

Parallel = 1
AutoStartList = { sys1, sys2}
Administrators = { z_vcszonereres1_sys1, z_vcszonereres1_sys2}
)

Application cssdl (
    Critical = 1
    StartProgram = "/opt/VRTSvcs/rac/bin/cssd-online"
    StopProgram = "/opt/VRTSvcs/rac/bin/cssd-offline"
    CleanProgram = "/opt/VRTSvcs/rac/bin/cssd-clean"
    MonitorProgram = "/opt/VRTSvcs/rac/bin/cssd-monitor"
)

CFSMount ocrvote_mnt1 (
    Critical = 0
    MountPoint @sys1 = "/zones/sys1_zone1/root/ocrvote"
    MountPoint @sys2 = "/zones/sys2_zone1/root/ocrvote"
    BlockDevice = "/dev/vx/dsk/ocrvotedg1/ocrvotevol1"
    MountOpt = "mincache=direct"
)

CVMVolDg ocrvote_voldg1 (
    Critical = 0
    CVMDiskGroup = ocrvotedg1
    CVMVolume = { ocrvotevol1 }
    CVMActivation = sw
    CVMDeactivateOnOffline = 1
)

PrivNIC ora_priv1 (
    Critical = 0
    Device @sys1 = { bge0 = 0, bge1 = 1 }
    Device @sys2 = { bge0 = 0, bge1 = 1 }
    Address @sys1 = "192.168.1.7"
    Address @sys2 = "192.168.1.8"
    NetMask = "255.255.255.0"
)

Zone vcszonereres1 (
```



```
)

requires group cvm online local firm
cssdl requires ocrvote_mnt1
cssdl requires ora_priv1
ocrvote_mnt1 requires ocrvote_voldg1
ocrvote_voldg1 requires vcszonerres1

group clus2_db1_grp (
  SystemList = { sys1 = 0, sys2 = 1 }
  ContainerInfo @sys1 = { Name = sys1_zone2, Type = Zone,
                          Enabled = 1 }
  ContainerInfo @sys2 = { Name = sys2_zone2, Type = Zone,
                          Enabled = 1 }

  Parallel = 1
  AutoStartList = { sys1, sys2 }
  Administrators = { z_vcszonerres2_sys1, z_vcszonerres2_sys2}
)

Oracle clus2_oradb1 (
  Critical = 1
  Sid @sys1 = clus2_db11
  Sid @sys2 = clus2_db12
  Owner = oracle
  Home = "/oracle/11g/dbhome"
  StartUpOpt = SRVCTLSTART
  ShutDownOpt = SRVCTLSTOP
)

requires group vcszone2 online local firm

group clus2_db2_grp (
  SystemList = { sys1 = 0, sys2 = 1 }
  ContainerInfo @sys1 = { Name = sys1_zone2, Type = Zone,
                          Enabled = 1 }
  ContainerInfo @sys2 = { Name = sys2_zone2, Type = Zone,
                          Enabled = 1 }

  Parallel = 1
  AutoStartList = { sys1, sys2 }
  Administrators = { z_vcszonerres2_sys1, z_vcszonerres2_sys2}
)
```

```
Oracle clus2_oradb2 (  
    Critical = 1  
    Sid = zndb  
    Owner = oracle  
    Home = "/oracle/11g/dbhome"  
    DBName = zndb  
    ManagedBy = POLICY  
    StartUpOpt = SRVCTLSTART  
    ShutDownOpt = SRVCTLSTOP  
    IntentionalOffline = 1  
)  
  
requires group vcszone2 online local firm  
  
group vcszone2 (  
    SystemList = { sys1 = 0, sys2 = 1}  
    ContainerInfo @sys1 = { Name = sys1_zone2, Type = Zone,  
                            Enabled = 1 }  
    ContainerInfo @sys2 = { Name = sys2_zone2, Type = Zone,  
                            Enabled = 1 }  
  
    Parallel = 1  
    AutoStartList = { sys1, sys2}  
    Administrators = { z_vcszonereres2_sys1, z_vcszonereres2_sys2}  
)  
  
Application cssd2 (  
    Critical = 1  
    StartProgram = "/opt/VRTSvcs/rac/bin/cssd-online"  
    StopProgram = "/opt/VRTSvcs/rac/bin/cssd-offline"  
    CleanProgram = "/opt/VRTSvcs/rac/bin/cssd-clean"  
    MonitorProgram = "/opt/VRTSvcs/rac/bin/cssd-monitor"  
)  
  
CFSMount ocrvote_mnt2 (  
    Critical = 0  
    MountPoint @sys1 = "/ocrvote"  
    MountPoint @sys2 = "/ocrvote"  
    BlockDevice = "/dev/vx/dsk/ocrvotedg2/ocrvotevol2"  
    MountOpt = "mincache=direct"  
)  
  
CVMVolDg ocrvote_voldg2 (  
    Critical = 0
```

```
CVMDiskGroup = ocrvotedg2
CVMVolume = { ocrvotevol2 }
CVMActivation = sw
CVMDeactivateOnOffline = 1
)

CFSSMount oradata_mnt3 (
  Critical = 0
  MountPoint @sys1 = "/db1"
  MountPoint @sys2 = "/db1"
  BlockDevice = "/dev/vx/dsk/clus2_db1dg/clus2_db1vol"
)

CVMVolDg oradata_voldg3 (
  Critical = 0
  CVMDiskGroup = clus2_db1dg
  CVMVolume = { clus2_db1vol }
  CVMActivation = sw
  CVMDeactivateOnOffline = 1
)

CFSSMount oradata_mnt4 (
  Critical = 0
  MountPoint @sys1 = "/db2"
  MountPoint @sys2 = "/db2"
  BlockDevice = "/dev/vx/dsk/clus2_db2dg/clus2_db2vol"
)

CVMVolDg oradata_voldg4 (
  Critical = 0
  CVMDiskGroup = clus2_db2dg
  CVMVolume = { clus2_db2vol }
  CVMActivation = sw
  CVMDeactivateOnOffline = 1
)

PrivNIC ora_priv2 (
  Critical = 0
  Device @sys1 = { bge2 = 0, bge3 = 1 }
  Device @sys2 = { bge2 = 0, bge3 = 1 }
  Address @sys1 = "192.168.1.12"
  Address @sys2 = "192.168.1.13"
  NetMask = "255.255.255.0"
```

```
)  
  
Zone vcszonerer2 (  
)  
  
requires group cvm online local firm  
cssd2 requires ora_priv2  
cssd2 requires vcszonerer2  
ocrvote_mnt2 requires ocrvote_voldg2  
vcszonerer2 requires ocrvote_mnt2  
vcszonerer2 requires oradata_mnt3  
vcszonerer2 requires oradata_mnt4  
oradata_mnt3 requires oradata_voldg3  
oradata_mnt4 requires oradata_voldg4
```

Configuring Solaris non-global zones for disaster recovery

Solaris Zones can be configured for disaster recovery by replicating the zone root using replication methods like Hitachi TrueCopy, EMC SRDF, Veritas Volume Replicator, and so on. The network configuration for the Zone in the primary site may not be effective in the secondary site if the two sites are in different IP subnets. Hence, you need to make these additional configuration changes to the Zone resource.

To configure the non-global zone for disaster recovery, configure VCS on both the sites in the global zones with GCO option.

Refer to the *Veritas Cluster Server Administrator's Guide* for more information about global clusters, their configuration, and their use.

To set up the non-global zone for disaster recovery

- 1 On the primary site, create the non-global Zone and configure its network parameters.
 - Create the non-global zone on the primary site using the `zonecfg` command.
 - Add the network adapters to the non-global zone's configuration if the zone is configured as an exclusive IP zone. Assign an IP address to the network adapter along with the Netmask and Gateway.

- After the zone boots, set up the other network-related information such as the HostName, DNS Servers, DNS Domain, and DNS Search Path in the appropriate files (/etc/hostname, /etc/resolve.conf).
- 2 On the primary site, shut down the zone.
 - 3 Use replication-specific commands to failover the replication to the secondary site from primary site.
 - 4 Repeat step 1 on the secondary site.
 - 5 Perform step 6, step 7, step 8, and step 9 on the primary cluster and secondary clusters.
 - 6 Create a VCS service group with a VCS Zone resource for the non-global zone. Configure the DROpts association attribute on the Zone resource with the following keys and site-specific values for each: HostName, DNSServers, DNSSearchPath, and DNSDomain. If the non-global zone is an exclusive IP zone in this site, configure the following keys in the DROpts association attribute on the Zone resource: Device (network adapter name), IPAddress, Netmask, and Gateway.
 - 7 Add the appropriate Mount resources and DiskGroup resources for the File System and DiskGroup on which the non-global zone's zoneroot resides. Add a resource dependency from the Zone resource to the Mount resource and another dependency from the Mount resource to the Diskgroup resource.
 - 8 Add one of the following VCS replication resources to the service group for managing the replication.
 - A hardware replication agent
Examples of these agents include SRDF for EMC SRDF, HTC for Hitachi TrueCopy, MirrorView for EMC MirrorView, etc. Refer to the appropriate VCS replication agent guide for configuring the replication resource.
 - The VVRPrimary agent
For VVR-based replication, add the RVGPrimary resource to the service group. Refer to the following manuals for more information:
 - For information about configuring VVR-related resources, see the *Veritas Storage Foundation and High Availability Solutions Replication Administrator's Guide*.
 - For information about the VVR-related agents, see the *Veritas Cluster Server Bundled Agents Reference Guide*.
 - 9 Add a dependency from the DiskGroup resource to the replication resource.

Figure 2-10 Sample resource dependency diagram for hardware replication based non-global zones





Figure 2-11 Sample resource dependency diagram for VVR replication-based non-global zones



When the resource is online in a site, the replication resource makes sure of the following:

- The underlying replicated devices are in primary mode, and the underlying storage and eventually the zone root goes into read-write mode.
- The remote devices are in secondary mode.

Thus, when the Zone resource goes online the resource modifies the appropriate files inside the non-global zone to apply the disaster recovery-related parameters to the non-global zone.

Software limitations of Storage Foundation support of non-global zones

This section describes the software limitations of Storage Foundation support of non-global zones in this release.

Administration commands are not supported in non-global zone

All administrative tasks, such as resizing a volume, adding a volume to a volume set, and file system reorganization, are supported only in the global zone.

Consequently, administrative commands, such as `fsadm`, `fsvoladm`, and `vxassist`, and administrative `ioctl`s are not supported in the non-global zone by both VxFS and VxVM.

VxFS file system is not supported as the root of a non-global zone

For Solaris 11, the root of a non-global zone cannot currently be on a VxFS file system.

QIO and CQIO are not supported

Quick I/O and Cached Quick I/O are not supported by VxFS in non-global zones.

Package installation in non-global zones

On Solaris 10 or 11, the packages are not propagated to the non-global zones automatically whenever the package is installed in the global zone. Refer to Install Guide of the product for instructions to install packages inside the non-global zone.

Package removal with non-global zone configurations

If non-global zones are part of the system configuration and the `VRTSodm` package is installed, ensure that `/dev/odm` is unmounted in each non-global zone prior to `VRTSodm` package removal or product uninstallation. This ensures there are no non-global zone `odm` module references that might prevent the global zone from unloading the `odm` module.

You can unmount `/dev/odm` in the non-global zone with the following commands:

```
global# zlogin myzone
myzone# svcadm disable vxodm
```

Root volume cannot be added to non-global zones

The root volume cannot be added to non-global zones.

Some Veritas Volume Manager operations can cause volume device names to go out of sync

If a volume is exported to a non-global zone, some Veritas Volume Manager operations can cause the global and non-global volume device names to go out of sync, which can create data corruption. This is because the Solaris operating

environment zone support is not aware of the `devfsadm(1M)` command, and thus the zone configuration is not updated with any changes to the `/dev` or `/devices` namespaces.

The following operations can cause device names to go out of sync:

- Removing a volume
- Importing a disk group
- Deporting a disk group
- Renaming a disk group or volume
- Reminoring a disk group
- Restarting `vxconfigd` or resetting the kernel

To prevent device names from to going out of sync, if a volume is exported to a non-global zone and an operation that can cause device names to go out of sync occurs on that volume, remove the volume from the zone configuration using the `zonecfg` command and reboot the zone using the `zoneadm` command.

See the `zonecfg(1M)` and `zoneadm(1M)` manual pages.

Note: This issue applies to any Solaris device for which the `/dev` or `/devices` device node is changed and has been configured in the non-global zone before the change.

Storage Foundation and High Availability Solutions support for Solaris Projects

This chapter includes the following topics:

- [About Solaris Projects](#)
- [About VCS support for Solaris projects](#)
- [Configuring VCS in Solaris projects](#)

About Solaris Projects

The Solaris operating system provides the projects facility to identify workloads. The project serves as an administrative tag that you use to group related work in a useful manner. You can create one project for a sales application and another project for a marketing application. By placing all processes related to the sales application in the sales project and the processes for the marketing application in the marketing project, you can separate and control the workloads in a way that makes sense to the business.

A user that is a member of more than one project can run processes in multiple projects at the same time. This multiple project approach makes it possible for users to participate in several workloads simultaneously. All processes that a process starts inherits the project of the parent process. As a result, switching to a new project in a startup script runs all child processes in the new project.

For more information, refer to the Solaris operating environment document *System Administration Guide: Solaris Containers--Resource Management and Solaris Zones*.

About VCS support for Solaris projects

VCS provides application management and high availability to applications that run in Solaris projects.

Overview of how VCS works with Solaris projects

You can use VCS to perform the following:

- Start, stop, monitor, and fail over a Solaris project.
- Start, stop, monitor, and fail over an application that runs inside a Solaris project.

How VCS models containers

VCS and necessary agents run in the global zone. For the applications that run in a Solaris project, the agents can run online entry point inside the project. If any resource faults, VCS fails over the service group.

Installing and configuring projects in a VCS environment

Install and configure the project. Create the service group with the standard application resource types (application, storage, networking) and the Project resource. VCS manages the project as a resource. You then configure the service group's ContainerInfo attribute.

Configuring the ContainerInfo attribute

The service group attribute ContainerInfo specifies information about the Solaris project. When you have configured and enabled the ContainerInfo attribute, you have enabled the project-aware resources in that service group to work in the project environment. VCS defines the project information at the level of the service group so that you do not have to define it for each resource. You need to specify a per-system value for the ContainerInfo attribute.

About the ContainerInfo service group attribute

The ContainerInfo attribute has the Name key, Type key, and Enabled key. The Name key defines the name of the container. The Type key lets you select the type of container that you plan to use. The Enabled key enables the Project-aware resources within the service group. The ContainerInfo attribute specifies if you can use the service group with the container.

Assign the following values to the ContainerInfo attribute:

- **Name**
The name of the container.
- **Type**
The type of container. You can set this to Project.
- **Enabled**
Specify the value as 0, if you want to disable the container. Specify the value as 1, if you want to enable the container. Specify the value as 2, to enable physical to virtual and virtual to physical failovers. When the value is 2, the Project resource mimics a non-existent entity.

You can set a per-system value for this attribute.

About the ContainerOpts resource type attribute

The ContainerOpts resource attribute is pre-set for project-aware resource types. It determines the following:

- Whether the project-aware resource can run in the project.
- Whether the container information that is defined in the service group's ContainerInfo attribute is passed to the resource.

These values are only effective when you configure the ContainerInfo service group attribute.

attribute's keys follow:

The ContainerOpts resource type attribute's definitions for project-aware types contain the following values:

- **RunInContainer**
When the value of the RunInContainer key is 1, only online agent function (entry point) for that resource runs inside of the project.
When the value of the RunInContainer key is 0, the agent function (entry point) for that resource runs outside the local container (in the global environment).
A limitation for the RunInContainer value is that only script agent functions (entry points) can run inside a container.
- **PassCInfo**
When the value of the PassCInfo key is 1, the agent function receives the container information that is defined in the service group's ContainerInfo attribute. An example use of this value is to pass the name of the container to the agent.

Project-aware resources

At present Process, Application and Oracle resources are project aware. If a service group, which is configured for Solaris Project contains resources other than Process, Application, or Oracle, Symantec recommends you set `RunInContainer` to 0.

About the Project agent

The Project agent monitors Solaris Project, brings them online, and takes them offline.

For more information about the agent, see the *Veritas Cluster Server Bundled Agents Reference Guide*.

Configuring VCS in Solaris projects

Configuring VCS in projects involves the following tasks:

- | | |
|--------|---|
| First | Review the prerequisites.
See “Prerequisites for configuring VCS in projects” on page 100. |
| Second | Decide on the location of the project root, which is either on local storage or shared storage. |
| Third | Install the application in the project. |
| Fourth | Create the application service group and configure its resources. |

Prerequisites for configuring VCS in projects

Review the following prerequisites for configuring VCS in projects: VCS support only Process, Application and Oracle agent.

Using custom agents in projects

If you use custom agents, review the following information for their use in projects:

- If you use custom agents to monitor the applications that run in project, make sure that the agents use script-based entry points. VCS does not support running C++ entry points inside a project.

- If you want the custom agent to monitor an application in the project, for the custom agent type, set the following values for the ContainerOpts attribute: RunInContainer = 1 and the PassCInfo = 0.
- If you don't want the custom agent to monitor an application in the project, for the custom agent type, set the following values for the ContainerOpts attribute: RunInContainer = 0 and the PassCInfo= 0.

For an example, refer to the *Veritas Cluster Server Bundled Agents Reference Guide*.

Storage Foundation and High Availability Solutions support for Branded Zones

This chapter includes the following topics:

- [About branded zones](#)
- [System requirements](#)
- [Veritas Storage Foundation support for branded zone](#)
- [About migrating VCS clusters on Solaris 10 systems](#)
- [Preparing to migrate a VCS cluster](#)
- [Configuring VCS/SF in a branded zone environment](#)

About branded zones

Branded zones (BrandZ) is a framework that extends the Solaris Zones infrastructure to create branded zones. Branded zone is a non-native zone that allows you to emulate an operating system environment other than the native operating system. Each operating system is plugged into the BrandZ framework with a brand associated to the operating system.

See the Oracle documentation for more information on branded zones.

System requirements

See the *Veritas Storage Foundation and High Availability Release Notes* for the system requirements.

Veritas Storage Foundation support for branded zone

SF provides support for the following in a branded zone environment:

- VxVM volume devices
- VxFS file systems using loopback file system mount or direct mount

You can export a VxVM volume or a VxFS file system to a branded zone and access the volume or the file system in the branded zone. The procedure to export the volumes or the file systems are the same as that for the non-global zones.

Refer to the *Veritas Volume Manager Administrator's Guide* or the *Veritas File System Administrator's Guide* for more details.

About migrating VCS clusters on Solaris 10 systems

You can migrate VCS clusters that run on Solaris 10 systems to solaris10 brand zones on Solaris 11 systems. For example, with BrandZ you can emulate a Solaris 10 operating system as Solaris 10 container in the Solaris 11 branded zone. This Solaris 10 non-global zone acts as a complete runtime environment for Solaris 10 applications on Solaris 11 systems. You can directly migrate an existing Solaris 10 system into a Solaris 10 container.

[Figure 4-1](#) illustrates the workflow to migrate a VCS cluster on Solaris 10 systems to branded zones on Solaris 11 systems.

Figure 4-1 Workflow to migrate VCS cluster to branded zones

On Solaris 10 systems:

Uninstall VCS/SF

Create a flash archive of the Solaris system image

On Solaris 11 systems:

Install VCS/SF in the global zone

Configure a solaris10 branded zone

Install the branded zone using the flash archive

Boot the branded zone

Install VCS components in the branded zone

Configure a Zone resource for the branded zone in the VCS configuration file in the global zone

Preparing to migrate a VCS cluster

You must perform the following steps on the Solaris 10 systems from where you want to migrate VCS.

To prepare to migrate a VCS cluster

- 1 Uninstall VCS on the systems.

See the *Veritas Cluster Server Installation Guide*.

If SF is installed, uninstall SF on the systems.

See the *Veritas Storage Foundation Installation Guide*.

- 2 Create a flash archive. For example:

```
# flarcreate -S -n sol10image /tmp/sol10image.flar
```

Configuring VCS/SF in a branded zone environment

You must perform the following steps on the Solaris 11 systems.

To configure VCS/SF in a branded zone environment

- 1 Install VCS, SF, or SFHA as required in the global zone.

See the *Veritas Cluster Server Installation Guide*.

See the *Veritas Storage Foundation and High Availability Installation Guide*.

- 2 Configure a solaris10 brand zone. For example, this step configures a solaris10 zone.

- Run the following command in the global zone as the global administrator:

```
# zonecfg -z sol10-zone
sol10-zone: No such zone configured
Use 'create' to begin configuring a new zone.
```

- Create the solaris10 brand zone using the SYSsolaris10 template.

```
zonecfg:sol10-zone> create -t SYSsolaris10
```

- Set the zone path. For example:

```
zonecfg:sol10-zone> set zonepath=/zones/sol10-zone
```

Note that zone root for the branded zone can either be on the local storage or the shared storage (VxFS or UFS).

- Add a virtual network interface.

```
zonecfg:sol10-zone> add net
zonecfg:sol10-zone:net> set physical=net1
zonecfg:sol10-zone:net> set address=192.168.1.20
zonecfg:sol10-zone:net> end
```

- Verify the zone configuration for the zone and exit the zonecfg command prompt.

```
zonecfg:sol10-zone> verify
zonecfg:sol10-zone> exit
```

The zone configuration is committed.

- 3 Verify the zone information for the solaris10 zone you configured.

```
# zonecfg -z sol10-zone info
```

Review the output to make sure the configuration is correct.

- 4 Install the solaris10 zone that you created using the flash archive you created previously.

See [“Preparing to migrate a VCS cluster”](#) on page 105.

```
# zoneadm -z sol10-zone install -p -a /tmp/sol10image.flar
```

After the zone installation is complete, run the following command to list the installed zones and to verify the status of the zones.

```
# zoneadm list -iv
```

- 5 Boot the solaris10 brand zone.

```
# /usr/lib/brand/solaris10/p2v sol10-zone
```

```
# zoneadm -z sol10-zone boot
```

After the zone booting is complete, run the following command to verify the status of the zones.

```
# zoneadm list -v
```

- 6 Install VCS in the branded zone:

- Install only the following VCS 6.0.1 packages and patches:

- VRTSperl
- VRTSat
- VRTSvc
- VRTSvcsg

- 7 If you configured Oracle to run in the branded zone, then install the VCS agent for Oracle packages (VRTSvcsea) and the patch in the branded zone.

See the *Veritas Cluster Server Agent for Oracle Installation and Configuration Guide* for installation instructions.

- 8 For ODM support, install the following additional packages and patches in the branded zone:

- Install the following 6.0 packages and patches:

- VRTSvlic
- VRTSvxfs
- VRTSodm

9 If using ODM support, relink Oracle ODM library in Solaris 10 brand zones:

- Log into Oracle instance.
- Relink Oracle ODM library.
If you are running Oracle 10gR2:

```
$ rm $ORACLE_HOME/lib/libodm10.so
$ ln -s /opt/VRTSodm/lib/sparcv9/libodm.so \
$ORACLE_HOME/lib/libodm10.so
```

If you are running Oracle 11gR1:

```
$ rm $ORACLE_HOME/lib/libodm11.so
$ ln -s /opt/VRTSodm/lib/sparcv9/libodm.so \
$ORACLE_HOME/lib/libodm11.so
```

- To enable odm inside branded zone, enable odm in global zone using smf scripts as described as below:

```
global# svcadm enable vxfsldlic
global# svcadm enable vxodm
```

To use ODM inside branded zone, export `/dev/odm`, `/dev/fdd`,
`/dev/vxportal` devices and `/etc/vx/licenses/lic` directory.

```
global# zoneadm -z myzone halt
global# zonecfg -z myzone
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/vxportal
zonecfg:myzone:device> end
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/fdd
zonecfg:myzone:device> end
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/odm
zonecfg:myzone:device> end
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/vx/rdsk/dg_name/vol_name
zonecfg:myzone:device> end
zonecfg:myzone> add device
zonecfg:myzone:device> set match=/dev/vx/dsk/dg_name/vol_name
zonecfg:myzone:device> end
zonecfg:myzone> add fs
zonecfg:myzone:fs> set dir=/etc/vx/licenses/lic
```

```
zonecfg:myzone:fs> set special=/etc/vx/licenses/lic
zonecfg:myzone:fs> set type=lofs
zonecfg:myzone:fs> end
zonecfg:myzone> set fs-allowed=vxfs,odm
zonecfg:myzone> verify
zonecfg:myzone> commit
zonecfg:myzone> exit
global# zoneadm -z myzone boot
```

10 Configure the resources in the VCS configuration file in the global zone. For example:

```
group g1 (
  SystemList = { vcs_sol1 = 0, vcs_sol2 = 1 }
  ContainterInfo@vcs_sol1 {Name = sol10-zone, Type = Zone,
  Enabled = 1 }
  ContainterInfo@vcs_sol2 {Name = sol10-zone, Type = Zone,
  Enabled = 1 }
  AutoStartList = { vcs_sol1 }
  Administrators = { "z_z1@vcs_lzs@vcs_sol2.symantecexample.com" }
)

Process p1 (
  PathName = "/bin/ksh"
  Arguments = "/var/tmp/cont_yoyo"
)

Zone z1 (
)

p1 requires z1
```

See the *Veritas Cluster Server Bundled Agents Reference Guide* for VCS Zone agent details.

Storage Foundation and High Availability Solutions support for Oracle VM Server for SPARC

This chapter includes the following topics:

- [Terminology for Oracle VM Server for SPARC](#)
- [Oracle VM Server for SPARC deployment models](#)
- [Benefits of deploying Storage Foundation High Availability solutions in Oracle VM server for SPARC](#)
- [Features](#)
- [Split Storage Foundation stack model](#)
- [Guest-based Storage Foundation stack model](#)
- [System requirements](#)
- [Veritas product release notes](#)
- [Product licensing](#)
- [Installing Storage Foundation in a Oracle VM Server for SPARC environment](#)
- [Exporting a Veritas volume to a guest domain from the control domain](#)
- [Provisioning storage for a guest domain](#)

- [Using Veritas Volume Manager snapshots for cloning logical domain boot disks](#)
- [Configuring Oracle VM Server for SPARC guest domains for disaster recovery](#)
- [Software limitations](#)
- [Known issues](#)

Terminology for Oracle VM Server for SPARC

The following terminology is used in configuring the Veritas software in Oracle VM Server for SPARC.

Table 5-1 Lists the terminology for Oracle VM Server for SPARC

Term	Definition
Logical domain	Logical domain or virtual machine with its own operating system, resources, and identity within the same physical host.
Hypervisor	A firmware layer that provides a set of hardware-specific support functions to the operating systems running inside logical domains through a stable interface, known as the sun4v architecture. The hypervisor is interposed between the operating system and the hardware layer.
Logical Domains Manager	Software that communicates with the Hypervisor and logical domains to sequence changes, such as the addition and removal of resources or creation of a logical domain. The Logical Domains Manager provides an administrative interface and keeps track of the mapping between the physical and virtual devices in a system.
Control domain	The primary domain which provides a configuration platform to the system for the setup and teardown of logical domains. Executes Logical Domains Manager software to govern logical domain creation and assignment of physical resources.

Table 5-1 Lists the terminology for Oracle VM Server for SPARC (*continued*)

Term	Definition
I/O domain	Controls direct, physical access to input/output devices, such as PCI Express cards, storage units, and network devices. The default I/O domain is the control domain.
Guest domain	Utilizes virtual devices offered by control and I/O domains and operates under the management of the control domain.
Virtual devices	Physical system hardware, including CPU, memory, and I/O devices that are abstracted by the Hypervisor and presented to logical domains within the platform.
Logical Domains Channel (LDC)	A logical domain channel is a point-to-point, full-duplex link created by the Hypervisor. LDCs provide a data path between virtual devices and guest domains and establish virtual networks between logical domains.
Virtual Disk Client	A Solaris kernel module in the guest domain which controls the virtual disks visible to that guest, providing standard device interfaces to applications.
Virtual Disk Server	A Solaris kernel module in the control domain which is responsible for exporting various backend devices as virtual disks to guest domains.

Oracle VM Server for SPARC deployment models

Oracle VM Server for SPARC is a virtualization technology on the Solaris SPARC platform that enables the creation of independent virtual machine environments on the same physical system. This allows you to consolidate and centrally manage your workloads on one system.

Veritas Storage Foundation supports logical domains in the following two deployments models:

- Split Storage Foundation stack
- Guest-based Storage Foundation stack

Veritas Storage Foundation Cluster File System (SFCFS) is supported only in the guest-based Storage Foundation stack.

See [“About Veritas Cluster Server configuration models in an Oracle VM Server for SPARC environment”](#) on page 162.

Split Storage Foundation stack

The support for this model was introduced in 5.0 MP1 release and this model continues to be supported in this release.

See [“Split Storage Foundation stack model”](#) on page 119.

Guest-based Storage Foundation stack

The support for this model was introduced in 5.0 MP3 release.

See [“Known issues”](#) on page 150.

Note: The SFCFS stack can be installed across multiple I/O domains within or across physical servers.

See [“Veritas Cluster Server limitations”](#) on page 161.

Benefits of deploying Storage Foundation High Availability solutions in Oracle VM server for SPARC

There are several benefits to a Oracle VM Server for SPARC environment.

Standardization of tools

Independent of how an operating system is hosted, consistent storage management tools save an administrator time and reduce the complexity of the environment.

Storage Foundation in the control domain provides the same command set, storage namespace, and environment as in a non-virtual environment.

Array migration

Data migration for Storage Foundation can be executed in a central location, migrating all storage from an array utilized by Storage Foundation managed hosts.

This powerful, centralized data migration functionality is available with Storage Foundation Manager 1.1 and later.

Moving storage between physical and virtual environments

Storage Foundation can make painful migrations of data from physical to virtual environments easier and safer to execute.

With Storage Foundation, there is no need to copy any data from source to destination, but rather the administrator reassigns the same storage or a copy of the storage for a test migration, to the virtual environment.

Boot Image Management

Using Storage Foundation in this environment the user can utilize features such as instant snapshots to contain boot images and manage them from a central location in the control domain.

Features

This section describes some of the features in Oracle VM Server for SPARC using the products in the Veritas Storage Foundation and High Availability Solutions.

Storage Foundation features

The following features apply for Storage Foundation.

The vxloadm utility enables access to a file system contained in a VxVM volume from the Control Domain

The `vxloadm` utility lets you access a file system contained inside a VxVM volume from outside the guest domain, that is from the Control Domain. This is done by mapping all the partitions contained within that volume using the `vxlo` driver. The partitions can then be mounted if they contain valid file systems.

To use this vxloadm utility

- 1 Check if the driver is loaded in memory:

```
# modinfo | grep vxlo
226 7b3ec000 3870 306 1 vxlo (Veritas Loopback Driver 0.1)
```

- 2 Run the `vxloadm` utility:

```
# /etc/vx/bin/vxloadm
```

- 3 You can now use the utility.
See “[Examples of using the vxloadm utility](#)” on page 116.
- 4 Symantec recommends once you are done using the `vxloadm` utility to unload the `vxlo` driver:

```
# rem_drv vxlo
# modinfo | grep vxlo
226 7b3ec000 3870 306 1 vxlo (Veritas Loopback Driver 0.1)
# modunload -i 226
```

where `226` is the module ID from the `modinfo | grep vxlo` command.

Examples of using the vxloadm utility

Use the `vxloadm addall` command to create device(s) mapping the various partition(s) contained in a VxVM volume. For example:

```
# /etc/vx/bin/vxloadm addall vol1 /dev/vx/dsk/testdg/vol1
```

This creates a device node entry for every slice or partition contained within the volume in the `/dev/vxlo/dsk/` and `/dev/vxlo/rdsk/` directories.

```
# ls -l /dev/vxlo/dsk/
lrwxrwxrwx 1 root root 46 Sep 25 14:04 vol1s0
-> ../../../../devices/pseudo/vxlo@0:vol1s0,1,blk
lrwxrwxrwx 1 root root 46 Sep 25 14:04 vol1s3
-> ../../../../devices/pseudo/vxlo@0:vol1s3,2,blk

# ls -l /dev/vxlo/rdsk/
lrwxrwxrwx 1 root root 46 Sep 25 14:04 vol1s0
-> ../../../../devices/pseudo/vxlo@0:vol1s0,1,raw
lrwxrwxrwx 1 root root 46 Sep 25 14:04 vol1s3
-> ../../../../devices/pseudo/vxlo@0:vol1s3,2,raw
```

Use the `vxloadm get` command to display the list of all currently mapped partition(s) created using the `vxloadm` utility. For example:

```
# /etc/vx/bin/vxloadm get
VxVM  INFO V-5-1-0      NAME      FILENAME
MOUNT  OFFSET  C/H/S
VxVM  INFO V-5-1-15260  vol1s0   /dev/vx/dsk/testdg/vol1
6180      6787/1/618
VxVM  INFO V-5-1-15260  vol1s3   /dev/vx/dsk/testdg/vol1
4326000  50902/1/618
```

Use the appropriate file system commands to access the file system(s). For example:

```
# fstyp /dev/vxlo/rdisk/voll1s0
ufs
# mount -F ufs /dev/vxlo/dsk/voll1s0 /mnt
```

Use the `vxloadm delete` to remove the partition mappings of a volume. For example:

```
# /etc/vx/bin/vxloadm delete voll1s0
# /etc/vx/bin/vxloadm delete voll1s3
```

Note: This `vxloadm` utility should only be used on volumes that are currently not in use or held open by a guest domain.

The `vxformat` utility automatically relabels the virtual disk backed by a VxVM volume in the guest domain

The `vxformat` utility provides the user the ability to automatically relabel a virtual disk backed by a VxVM volume. This utility is meant to be executed from inside the guest domain only.

The `vxformat` utility is particularly useful when a VxVM volume with existing partitions is grown in size and you need to access the new size from the guest domain.

Requirements for relabeling to succeed

- The relabel succeeds only- if it can find a new cylinder size that is aligned with the start and size of each of the existing partitions.

In case the `vxformat` command cannot find such cylinder size, it displays the following descriptive message and then exits:

```
Cannot re-label device /dev/rdsk/c0t1d2s2 since we failed to
find new cylinder size that's aligned with all the existing partitions
```

- The relabel succeeds only - if the available blocks is greater than the last sector of each and every non-s2 partition.

Otherwise, the `vxformat` command displays the following message and then exits:

```
Cannot re-label device /dev/rdsk/c0d2s2 since the last sector of a
non-s2 partition is greater than the available blocks
```

Example of using the vxformat utility

Use the `vxformat` command to relabel the virtual disk. For example:

```
# /etc/vx/bin/vxformat c0d1s2
rawpath: /dev/rdisk/c0d1s2
Old disk capacity: 2097000 blocks
New disk capacity: 4194000 blocks
Device /dev/rdisk/c0d1s2 has been successfully re-labeled.
Please use prtvtoc(1) to obtain the latest partition table information
```

If the underlying device size has not changed, the `vxformat` command displays the following message without changing the label. For example:

```
# /etc/vx/bin/vxformat c0d1s2
Old disk capacity: 2343678 blocks
New disk capacity: 2343678 blocks
size of device /dev/rdisk/c0d2s2 is unchanged
```

Oracle VM Server for SPARC features

SFHA solutions support the following features for Oracle VM server for SPARC.

Guest domain migration

The guest domain migration feature is supported for cold, warm, and live migrations by Storage Foundation with both deployment models:

- Split Storage Foundation stack
- Guest-based Storage Foundation stack

Virtual I/O dynamic reconfiguration

The virtual I/O dynamic reconfiguration feature is supported with both deployment models:

- Split Storage Foundation stack
- Guest-based Storage Foundation stack


Note: For resizing a volume exported as a single slice: The new size should be visible dynamically in the guest immediately.

For resizing a volume exported as a full disk: Even though the new size is visible dynamically in the guest, the new space allocated in the volume cannot be utilized unless the label in the vdisk has been adjusted to reflect the new sectors. This adjustment of the label needs to be done carefully.

Split Storage Foundation stack model

Figure 5-1 illustrates the split Storage Foundation stack model with Oracle VM Server for SPARC logical domains.

Figure 5-1 Split Storage Foundation stack model with logical domains



How Storage Foundation and High Availability Solutions works in the Oracle VM Server for SPARC

Veritas Storage Foundation and High Availability Solutions supports Oracle VM Server for SPARC logical domains in both single-node, multiple-node, and multiple-node high availability configurations.

[Figure 5-1](#) illustrates the recommended placement of Storage Foundation stack component products in this model.

Following indicates the recommended placement of Storage Foundation stack component products:

- For a single node configuration, Veritas Volume Manager (VxVM) including DMP is placed in the control domain, and Veritas File System (VxFS) is placed in the guest domain.
- For clustered nodes, Cluster Volume Manager (CVM) is placed in the control domain, and VxFS is placed in the guest domain.
See [“Clustering using Cluster Volume Manager”](#) on page 153.
See [“Installing Storage Foundation on multiple nodes in a Logical Domain”](#) on page 154.
See [“Cluster Volume Manager in the control domain for providing high availability”](#) on page 156.
- For clustered nodes in a highly available environment, install Veritas Cluster Server (VCS) in the control domain.
See [“About Veritas Cluster Server in a Oracle VM Server for SPARC environment”](#) on page 159.
See [“About Veritas Cluster Server configuration models in an Oracle VM Server for SPARC environment”](#) on page 162.
See [“Configuring Veritas Cluster Server to fail over an application on a failure”](#) on page 176.
- VxFS drivers in the guest domain cannot currently interact with the VxVM drivers in the control domain. This renders some features, which require direct VxVM-VxFS coordination, unusable in such a configuration.
See [“Veritas Storage Foundation features restrictions”](#) on page 120.

Note: VxFS can also be placed in the control domain, but there will be no coordination between the two VxFS instances in the guest and the control domain.

Veritas Storage Foundation features restrictions

The following Veritas Storage Foundation software features are restricted in the split Storage Foundation stack model:

- Smartmove and Thin Reclamation – These features require co-ordination between VxVM and VxFS and hence are not supported in this model.

- VxVM volume snapshots – Due to the inability of VxFS in the guest domain to coordinate with VxVM in the control domain, taking a data consistent snapshot of a VxVM volume containing a VxFS file system requires shutting down the application and unmounting the file system before taking the snapshot.

- Resizing VxVM volumes and any type of file system on top of the volume with `vxresize` – Resizing any type of file system on the guest whose underlying device is backed by a VxVM volume in the control domain, requires resizing the VxVM volume and the file system in the guest individually.

If you are growing a VxFS file system in the guest whose underlying device is backed by a VxVM volume requires you to first grow the volume in the control domain using the `vxassist` command, and then the file system in the guest domain using the `fsadm` command.

Shrinking a VxFS file system, on the other hand, requires you to first shrink the file system in the guest domain using the `fsadm` command, and then the volume in the control domain using the `vxassist` command. Using the `vxassist` command requires you to use the `-f` option of the command, as in the following example.

```
# vxassist -g [diskgroup] -f shrinkto volume length
```

Caution: Do not shrink the underlying volume beyond the size of the VxFS file system in the guest as this can lead to data loss.

- Exporting a volume set to a guest domain is not supported.
- Veritas Volume Replicator is not supported in the Split Storage Foundation stack model.
- Multi-volume filesets/DST
- File-level Smartsync
- The following VxFS tunables are not set to their default values based on the underlying volume layout, due to VxFS being in the guest domain and VxVM being installed in the control domain:
 - `read_pref_io`
 - `write_pref_io`
 - `read_nstream`
 - `write_nstream`

If desired, you can set the values of these tunables based on the underlying volume layout in the `/etc/vx/tunefstab` file.

See the *Veritas Storage Foundation Administrator's Guide* for more information about tuning I/O.

- Storage Foundation Cluster File System is not recommended in this deployment model.

Guest-based Storage Foundation stack model

Figure 5-2 Guest-based Storage Foundation stack model




Figure 5-2 illustrates the guest-based Storage Foundation stack model with guest logical domains.

How Storage Foundation and High Availability Solutions works in the guest domains

The entire Storage Foundation stack is co-located within the guest in this deployment model.

Symantec recommends that you export all paths to a disk which is being exported to a guest and let Veritas DMP do the multi-pathing of the disk in the guest domain.

Note: Only full SCSI disks can be used under Veritas Volume Manager (VxVM) and DMP in this model. Non-SCSI devices (volume, file, slice, etc) are not supported.

Veritas Storage Foundation and High Availability Solutions and Veritas Storage Foundation Cluster File System supports running in the guest domains in both single-node, multiple-node, and multiple-node high availability configurations.

- For a single node configuration, VxVM (including DMP) and VxFS are co-located in the guest domain.
- For clustered nodes, CVM can also be used inside the guest domain. As with regular physical nodes, forming a CVM cluster of logical domain guests requires shared storage visibility across the guests that are part of the cluster. See the *Veritas Storage Foundation Cluster File System High Availability Administrator's Guide* for CVM information. See the *Veritas Storage Foundation Installation Guide* for installation and configuration information.
- For clustered nodes in a highly available environment, install Veritas Cluster Server (VCS) in the guest domains. See the *Veritas Cluster Server* documentation for more information.

Veritas Volume Replicator (VVR) is supported in the guest-based Storage Foundation stack model in the following configurations:

- A guest domain on one host acting as the VVR primary, and another guest on another host acting as the VVR secondary.
- Two guest domains on the same physical host, but you must export separate LUNs or disks to the data volumes and Storage Replicator Logs of the two guest domains.

In this model, the boot disk of the guest can be a VxVM volume. For more details on this support:

See [“Provisioning Veritas Volume Manager volumes as boot disks for guest domains”](#) on page 139.

About Veritas Storage Foundation Cluster File System in an Oracle VM Server for SPARC environment

Veritas Storage Foundation Cluster File System (SFCFS) allows clustered servers to mount and use a file system simultaneously as if all applications using the file system were running on the same server for a Oracle VM Server for SPARC.

Veritas Storage Foundation Cluster File System limitations

Depending on the configuration model, the following limitations apply to using SFCFS in an Oracle VM Server for SPARC environment.

Limitations for SFCFS configuration in the guest domain:

- There is no support for replicating a shared disk group using VVR, when one or more guest domains share the disk group.
- If you want to configure I/O fencing in guest domain, then do not export physical devices to more than one guest domain on the same physical node. Otherwise, I/O fencing fences off the device whenever one of the guest domain dies. This situation causes the other guest domains also to lose access to the device.

Symantec recommends you to disable I/O fencing if you exported the same physical device to multiple guest domains.

Supported configurations with SFCFS and multiple I/O Domains

Figure 5-3 SFCFS cluster across two guest domains




Figure 5-3 illustrates that each guest domain gets network and disk storage redundancy from the two I/O domains.

Figure 5-4 SFCFS cluster across two guest domains




Figure 5-4 illustrates that each guest domain gets network and disk storage redundancy from the two I/O domains on that physical server. The guest cluster spans across two physical servers.

Figure 5-5 SFCFS cluster across four guest domains




Figure 5-5 illustrates that each guest domain gets network and disk storage redundancy from two I/O domains on that physical server. The guest cluster spans across two physical servers.

Figure 5-6 SFCFS cluster across four guest domains




Figure 5-6 illustrates each guest gets its disk storage redundancy from two out of the four I/O domains. Each guest gets its network redundancy from all the four I/O domains.

Veritas Storage Foundation features restrictions

The following Veritas Storage Foundation software features are restricted in the Oracle VM Server for SPARC guest domain environment.

Veritas Volume Replicator bunker replication

Veritas Volume Replicator (VVR) currently does not support configuring a guest domain as a bunker node in the bunker replication mode. This restriction may be removed in a later release.

Mirroring across controllers using vxassist the mirror=ctrl option

Currently, all virtual disks in the guest are under the same virtual controller c0. When `vxassist` tries to look for a second controller to place the mirror on, it fails and therefore the command fails.

All disks fall under the c0 controller, even if they are exported using different physical paths in the backend and coming from different HBAs.

DMP SCSI bypass

The virtual disk client (VDC) driver controls all virtual disks in the guest domain and not the SCSI driver.

Therefore, it is not possible to construct a SCSI packet and send the packet down through DMP. Setting the tunable `dmp_fast_recovery` to on has no effect.

Event Source Daemon (vxesd) fabric monitoring capabilities

One of the features of the `vxesd` daemon is to register with the HBA API to listen to fabric events. Even though the HBA API is loaded in the guest, since there is currently no concept of a directly connected HBA in the guest, this API is not of any use. Therefore, this capability of `vxesd` is not available.

Physical WWN for a path

It is not possible to create a Sub Path Failover Group (SFG) without Physical WWN. Physical World Wide IDs cannot be obtained from inside the guest because they are fetched by DMP using the HBA API which is currently not functional inside the guest.

System requirements

See the *Veritas Cluster Server Release Notes* for the system requirements.

Hardware requirements

Visit the Oracle Web site for information about the supported hardware for Oracle VM Server for SPARC

Veritas product release notes

Read the relevant Veritas product release notes before installing any version of Veritas Storage Foundation and High Availability or Veritas Storage Foundation Cluster File System.

Veritas Storage Foundation and High Availability

Release notes for Veritas Storage Foundation are located under the `docs/storage_foundation` directory and the Veritas Cluster Server are located under the `docs/cluster_server` directory of the Veritas Storage Foundation disc.

- *Veritas Storage Foundation Release Notes*
- *Veritas Cluster Server Release Notes*

Veritas Storage Foundation Cluster File System

Release notes for Veritas Storage Foundation Cluster File System are located under the `docs/sf_cluster_file_system_ha` directory of the Veritas Storage Foundation disc.

- *Veritas Storage Foundation Cluster File System.*

Product licensing

Customers running Veritas Storage Foundation or Veritas Storage Foundation Cluster File System in a Oracle VM Server for SPARC environment are entitled to use an unlimited number of logical domains on each licensed server or CPU.

Installing Storage Foundation in a Oracle VM Server for SPARC environment

This section describes how to install Storage Foundation in several Oracle VM Server for SPARC environments.

To install the Split Storage Foundation stack model environment, you must complete the following sections in order:

- See [“Installing and configuring Oracle VM Server for SPARC and domains”](#) on page 130.
- See [“Installing Storage Foundation in the control domain or guest”](#) on page 130.
- See [“Installing Veritas File System in the guest domain”](#) on page 131.

- See [“Verifying the configuration”](#) on page 135.

To install the Guest based Storage Foundation stack model environment, which includes Veritas Storage Foundation Cluster File System, you must complete the following sections in order:

- See [“Installing and configuring Oracle VM Server for SPARC and domains”](#) on page 130.
- See [“Installing Storage Foundation in the control domain or guest”](#) on page 130.
- See [“Verifying the configuration”](#) on page 135.

To install and configure Veritas Cluster Server in a Oracle VM Server for SPARC environment, see the following sections:

-
- See [“Configuring Veritas Cluster Server to fail over an application on a failure”](#) on page 176.

Installing and configuring Oracle VM Server for SPARC and domains

Refer to the Oracle documentation for instructions about installing and configuring the Oracle VM Server for SPARC software and configuring the control and guest domains.

Installing Storage Foundation in the control domain or guest

This section describes how to install Storage Foundation in the control domain or guest domain.

Installing the split Storage Foundation stack model

If you are installing the split Storage Foundation stack model, the entire stack must be in the control domain and VxFS must be in the guest domain.

Use the procedures in the Veritas installation documentation and Release Notes to install Storage Foundation in the control domain.

To install the split Storage Foundation stack model

- ◆ Install the product.
 - See the *Veritas Storage Foundation Installation Guide for Solaris*.
 - See the *Veritas Storage Foundation Release Notes for Solaris*.

Installing the guest-based Storage Foundation stack model

If you are installing the guest-based Storage Foundation stack model environment, the entire stack must be in the guest domain.

Use the procedures in the SF or SFCFS Installation Guide and Release Notes, as appropriate, to install SF or SFCFS in a guest domain.

To install the guest-based Storage Foundation stack model

- ◆ Install the product.

See the *Veritas Storage Foundation Installation Guide for Solaris* for SF.

See the *Veritas Storage Foundation Release Notes for Solaris* for SF.

See the *Veritas Storage Foundation Cluster File System Installation Guide for Solaris* for SFCFS.

See the *Veritas Storage Foundation Cluster File System Release Notes for Solaris* for SFCFS.

Installing Veritas File System in the guest domain

This section describes how to install VxFS in the guest domain.

To install Veritas File System in the guest domain

- ◆ If the guest OS is Oracle Solaris 11, refer to the Installation Guide for the product to install VxFS inside the guest domain.

If the guest OS is Oracle Solaris 10:

- Copy the VxFS packages from the `/pkgs` directory on the disc to a location in the guest domain where you have write permissions.


- Install the packages:

```
# pkgadd -d VRTSvlic.pkg
# pkgadd -d VRTSvxfs.pkg
# pkgadd -d VRTSfssdk.pkg
```

- Reboot the guest domain.

Enabling DMP in the control and alternate I/O domains

This section describes how to enable Dynamic Multi-Pathing (DMP) in the control and alternate I/O domains.



To enable DMP in the control and alternate I/O domains

- 1 Install VRTSvxvm and VRTSaslapm packages on both the control and alternate I/O domains.
- 2 Turn on the enclosure-based naming default setting in both the control and alternate domains.

```
# vxddladm set namingscheme=ebn
```

- 3 Create the VDS devices on DMP metanodes that can be provisioned to the guest domains.

For example:

```
# ldm add-vdsdev /dev/vx/dmp/xyz vo10015-001-p1@primary-vds0
# ldm add-vdsdev /dev/vx/dmp/xyz vo10015-001-p2@alternate-vds0
```

- 4 While provisioning, export the DMP metanodes from both the control and alternate I/O domain. This allows DMP in the guest domain to see two access paths, one through the control domain and the other through the alternate domain to the storage.

```
# ldm add-vdsdev /dev/vx/dmp/xyz vo10015-001-p1@primary-vds0
# ldm add-vdsdev /dev/vx/dmp/xyz vo10015-001-p2@alternate-vds0
# ldm add-vdisk timeout=30 vdisk0015-001-p1 \
vo10015-001-p1@primary-vds0 hscsd0015
# ldm add-vdisk timeout=30 vdisk0015-001-p2 \
vo10015-001-p2@alternate-vds0 hscsd0015
```

DMP in the guest domain can take care of the control and alternate I/O domain failures.

See [“Enabling DMP path failover in the guest domain”](#) on page 133.

Enabling DMP path failover in the guest domain

In Oracle VM Server configurations the VDC driver timeout is set to zero by default which signifies infinity. This can cause the failed I/O not to return to the guest domain, if either the control or alternate I/O domain crashes unexpectedly. As a result the guest domain cannot get back the failed I/Os and cannot route them through the alternate domain. If this issue occurs or to avoid this issue, you must set the VDC driver timeout.

There are two ways to set the VDC driver timeout:

This procedure modifies globally all the LUNs that are exported to the current guest domain. This requires a reboot to all the guest domains. See [“To change the VDC driver timeout globally”](#) on page 134.

This procedure you manually export every LUN directly to the guest domain and set the timeout parameter to 30 seconds. No reboot is required. See [“To change the VDC driver timeout for each LUN”](#) on page 134.

To change the VDC driver timeout globally

- 1 On each guest domain, edit the `/etc/system` file and add the following line to set the VDC driver timeout to 30 seconds:

```
set vdc:vdc_timeout=30
```

- 2 Reboot the guest domains.

To change the VDC driver timeout for each LUN

You will need to export any LUN directly to the guest domain and set the timeout parameter to 30 seconds.

- 1 Create the primary domain using four internal disks and get all required SAN LUNs for the guest domains allocated to the primary domain.
- 2 Turn on enclosure-based naming in the primary domain.

```
# vxddladm set namingscheme=ebn
```

- 3 Remove half of the system's I/O from the primary domain:

```
# ldm remove-io pci_X primary_domain_name
```

where `pci_x` is the name of the PCI bus for your system.

where `primary_domain_name` is the name of the primary domain.

For example:

```
# ldm remove-io pci_@400 primary
```

- 4 Create the alternate I/O domain on the other four internal disks and add the I/O that was removed from the primary domain:

```
# ldm add-io pci_X primary_domain_name
```

where `pci_x` is the name of the PCI bus for your system.

where `primary_domain_name` is the name of the primary domain.

For example:

```
# ldm add-io pci_@400 primary
```

- 5 Turn on enclosure-based naming in the alternate I/O domain.

```
# vxddladm set namingscheme=ebn
```

At this point you have one of the two paths to each SAN LUN in the primary domain and the other path is in the alternate I/O domain. Both will have the same name: `/dev/vx/dmp/enclosure_based_name`.

- 6 On the primary domain, create the guest domains. In the sample the enclosure-based name of one of the LUNs is `xyz` and the guest domain is `hsxd0015`:

```
# ldm add-vdsdev /dev/vx/dmp/xyz vol0015-001-p1@primary-vds0
# ldm add-vdsdev /dev/vx/dmp/xyz vol0015-001-p2@alternate-vds0
# ldm add-vdisk timeout=30 vdisk0015-001-p1 \
vol0015-001-p1@primary-vds0 hsxd0015
# ldm add-vdisk timeout=30 vdisk0015-001-p2 \
vol0015-001-p2@alternate-vds0 hsxd0015
```

The same set of four commands for each SAN LUN that gets placed in a guest domain. Use three SAN LUNs for SAN boot in the guest domain and the rest for application data. Each LUN in the guest domain has one path backup through the primary domain and one backup through the alternate domain. That means each LUN only uses one LDC in each domain. Also, since you are using DMP you still only use 1 LDC in each domain, even if the LUN has more than two paths from the array.

Verifying the configuration

Verify the configuration of Oracle VM server for SPARC in the control domain and the guest domain. Refer to the Oracle documentation for details.

Verify the Storage Foundation installation in both the control domain and the guest domain. Refer to the following guides for more information:

- See the *Veritas Storage Foundation Installation Guide for Solaris*.
- See the *Veritas Storage Foundation Release Notes for Solaris*.
- See the *Veritas Storage Foundation and High Availability Installation Guide for Solaris*.
- See the *Veritas Storage Foundation and High Availability Release Notes for Solaris*.
- See the *Veritas Storage Foundation Cluster File System and High Availability Installation Guide for Solaris*.

- See the *Veritas Storage Foundation Cluster File System and High Availability Release Notes for Solaris*.

Exporting a Veritas volume to a guest domain from the control domain

Use the following procedure to migrate a VxVM disk group from a non-logical domain environment to a Oracle VM Server for SPARC environment.

Note: This section applies to only the Split Storage Foundation model.

In the following example control domain is named “primary” and the guest domain is named “logical domain1.” The prompts in each step show in which domain to run the command.

To create virtual disks on top of the Veritas Volume Manager data volumes using the `ldm` command

- 1 The VxVM diskgroup on the target host is imported in the control domain, after which volumes are visible from inside the control domain.

See the *Veritas Storage Foundation Administrator's Guide* to move disk groups between systems.

- 2 In the control domain (primary), configure a service exporting the VxVM volume containing a VxFS or UFS filesystem as a slice using the `options=slice` option:

```
primary# ldm add-vdiskserverdevice options=slice \  
/dev/vx/dsk/dg-name/volume_name \  
volume_name volume_name@primary-vds0
```

Caution: A volume by default shows up as a full disk in the guest. The Virtual Disk Client driver writes a VTOC on block 0 of the virtual disk, which will end up as a WRITE on block 0 of the VxVM volume. This can potentially cause data corruption, because block 0 of the VxVM volume contains user data. Using `options=slice` exports a volume as a slice to the guest and does not cause any writes to block 0, therefore preserving user data.

- 3 Add the exported disk to a guest domain:

```
primary# ldm add-vdisk vdisk1 volume_name \  
volume_name@primary-vds0 logical domain1
```


- 4 Start the guest domain, and ensure that the new virtual disk is visible.

```
primary# ldm bind logical domain1  
  
primary# ldm start logical domain1
```

- 5 If the new virtual disk device node entries do not show up in the `/dev/[r]dsk` directories, then run the `devfsadm` command in the guest domain:

```
logical domain1# devfsadm -C
```

In this example, the new disk appears as `/dev/[r]dsk/c0d1s0`.

```
logical domain1# ls -l /dev/dsk/c0d1s0  
  
lrwxrwxrwx 1 root root 62 Sep 11 13:30 /dev/dsk/c0d1s0 ->  
../../../../devices/virtual-devices@100/channel-devices@200/disk@1:a
```

- 6 Mount the file system on the disk to access the application data:

```
logical domain1# mount -F vxfs /dev/dsk/c0d1s0 /mnt  
  
logical domain1# mount -F ufs /dev/dsk/c0d1s0 /mnt
```

Provisioning storage for a guest domain

Use the following procedure to provision storage for a guest domain. You can provision both boot disks and data disks.

Note: This section applies to the Split Storage Foundation stack model only.

For the guest-based Storage Foundation model:

See [“How Storage Foundation and High Availability Solutions works in the guest domains”](#) on page 122.

Provisioning Veritas Volume Manager volumes as data disks for guest domains

The following procedure uses VxVM volumes as data disks (virtual disks) for guest domains.

VxFS can be used as the file system on top of the data disks.

The example control domain is named “primary” and the guest domain is named “logical domain1.” The prompts in each step show in which domain to run the command.

To provision Veritas Volume Manager volumes as data disks

- 1 Create a VxVM disk group (`mydatadg` in this example) with some disks allocated to it:

```
primary# vxvg init mydatadg TagmaStore-USP0_29 TagmaStore-USP0_30
```

- 2 Create a VxVM volume of the desired layout (in this example, creating a simple volume):

```
primary# vxassist -g mydatadg make datavol1 500m
```

- 3 Configure a service exporting the volume `datavol1` as a virtual disk:

```
primary# ldm add-vdiskserverdevice /dev/vx/dsk/mydatadg/datavol1 \  
datadisk1@primary-vds0
```

- 4 Add the exported disk to a guest domain.

```
primary# ldm add-vdisk vdisk1 datadisk1@primary-vds0 logical domain1
```

- 5 Start the guest domain, and ensure that the new virtual disk is visible:

```
primary# ldm bind logical domain1
```

```
primary# ldm start logical domain1
```

- 6 If the new virtual disk device node entries do not show up in the `/dev/[r]dsk` directories, then run the `devfsadm` command in the guest domain:

```
logical domain1# devfsadm -C
```

- 7 Label the disk using the `format` command to create a valid label before trying to access it.

See the `format(1M)` manual page.

- 8 Create the file system where `c0d1s2` is the disk.

```
logical domain1# mkfs -F vxfs /dev/rdsk/c0d1s2
```

9 Mount the file system.

```
logical domain1# mount -F vxfs /dev/dsk/c0d1s2 /mnt
```

10 Verify that the file system has been created:

```
logical domain1# df -hl -F vxfs
```

```
Filesystem size used avail capacity Mounted on  
/dev/dsk/c0d1s2 500M 2.2M 467M 1% /mnt
```

Provisioning Veritas Volume Manager volumes as boot disks for guest domains

The following procedure provisions boot disks for a guest domain.

A VxVM volume appears as a full disk by default and can be used as a boot disk for a guest domain.

The following process gives the outline of how a VxVM volume can be used as a boot disk.

The example control domain and is named “primary” the guest domain is named “logical domain1.” The prompts in each step show in which domain to run the command.

To provision Veritas Volume Manager volumes as boot disks for guest domains

- 1 On the control domain, create a VxVM volume of a size that is recommended for Solaris 11 installation. In this example, a 7GB volume is created:

```
primary# vxassist -g boot_dg make bootdisk-vol 7g
```

- 2 Configure a service by exporting the `/dev/vx/dsk/boot_dg/bootdisk1-vol` volume as a virtual disk:

```
primary# ldm add-vdiskserverdevice \  
/dev/vx/dsk/boot_dg/bootdisk1-vol bootdisk1-vol@primary-vds0
```

- 3 Add the exported disk to logical domain1:


```
primary# ldm add-vdisk vdisk1 bootdisk1-vol@primary-vds0 \  
logical domain1
```

- 4 Follow Oracle’s recommended steps to install and boot a guest domain, and use the virtual disk `vdisk1` as the boot disk during the net install.

Note: It is not supported to encapsulate such a boot disk inside the guest using VxVM or any other 3rd party Volume Management software.

Using VxVM mirrored volumes as boot devices for Ldoms

Figure 5-8 VxVM mirrored volumes as boot devices for Ldoms



For providing high availability and redundancy of the guest boot disks, Symantec recommends that you use mirrored volumes as the backend storage for the boot disks.

The following are some advantages of using this configuration:

- You need to export only a single “vdisk” to the guest LDOM, using only a single LDC channel. This saves on the overall LDC channels being utilized in the control domain.
- Boot disks are managed in a single central location, possibly even in one disk group in the control domain.
- You can easily take snapshots of the boot image using VxVM snapshot feature in the control domain.
- With VxVM doing mirroring in the control domain and a single device being exported to the LDOM, even if the primary boot disk goes bad, the volume still remains enabled in the control domain and is accessible using the same device in the LDOM.

- There is no need to carry out the extra step of encapsulating the boot disk inside the guest for mirroring as it is already mirrored in the Control Domain.


Using Veritas Volume Manager snapshots for cloning logical domain boot disks

The following highlights the steps to clone the boot disk from an existing logical domain using VxVM snapshots, and makes use of the third-mirror breakoff snapshots.

See “[Provisioning Veritas Volume Manager volumes as boot disks for guest domains](#)” on page 139.

[Figure 5-9](#) illustrates an example of using Veritas Volume Manager snapshots for cloning Logical Domain boot disks.

Figure 5-9 Example of using Veritas Volume Manager snapshots for cloning Logical Domain boot disks



Before this procedure, logical domain1 has its boot disk contained in a large volume, `/dev/vx/dsk/boot_dg/bootdisk1-vol`.

This procedure involves the following steps:

- Cloning the logical domain configuration to form a new logical domain configuration.

This step is a Solaris logical domain procedure, and can be achieved using the following commands:

```
# ldm list-constraints -x
```

```
# ldm add-domain -i
```

Refer to the Oracle documentation for more information about cloning the logical domain configuration to form a new logical domain configuration. See the *Logical Domains Administration Guide*.

- After cloning the configuration, clone the boot disk and provision it to the new logical domain.

To create a new logical domain with a different configuration than that of logical domain1, skip this step of cloning the configuration and create the desired logical domain configuration separately.

To clone the boot disk using Veritas Volume Manager snapshots

- 1 Create a snapshot of the source volume bootdisk1-vol. To create the snapshot, you can either take some of the existing ACTIVE plexes in the volume, or you can use the following command to add new snapshot mirrors to the volume:

```
primary# vxsnap [-b] [-g diskgroup] addmir volume \  
[nmirror=N] [alloc=storage_attributes]
```

By default, the `vxsnap addmir` command adds one snapshot mirror to a volume unless you use the `nmirror` attribute to specify a different number of mirrors. The mirrors remain in the SNAPATT state until they are fully synchronized. The `-b` option can be used to perform the synchronization in the background. Once synchronized, the mirrors are placed in the SNAPDONE state.

For example, the following command adds two mirrors to the volume, bootdisk1-vol, on disks mydg10 and mydg11:

```
primary# vxsnap -g boot_dg addmir bootdisk1-vol \  
nmirror=2 alloc=mydg10,mydg11
```

If you specify the `-b` option to the `vxsnap addmir` command, you can use the `vxsnap snapwait` command to wait for synchronization of the snapshot plexes to complete, as shown in the following example:

```
primary# vxsnap -g boot_dg snapwait bootdisk1-vol nmirror=2
```

- 2 To create a third-mirror break-off snapshot, use the following form of the `vxsnap make` command.

Caution: Shut down the guest domain before executing the `vxsnap` command to take the snapshot.

```
primary# vxsnap [-g diskgroup] make \  
source=volume[/newvol=snapvol] \  
{/plex=plex1[,plex2,...]|/nmirror=number}
```

Either of the following attributes may be specified to create the new snapshot volume, `snapvol`, by breaking off one or more existing plexes in the original volume:

plex Specifies the plexes in the existing volume that are to be broken off. This attribute can only be used with plexes that are in the ACTIVE state.

nmirror Specifies how many plexes are to be broken off. This attribute can only be used with plexes that are in the SNAPDONE state. Such plexes could have been added to the volume by using the `vxsnap addmir` command.

Snapshots that are created from one or more ACTIVE or SNAPDONE plexes in the volume are already synchronized by definition.

For backup purposes, a snapshot volume with one plex should be sufficient.

For example,

```
primary# vxsnap -g boot_dg make \  
source=bootdisk1-vol/newvol=SNAP-bootdisk1-vol/nmirror=1
```

Here `bootdisk1-vol` makes source; `SNAP-bootdisk1-vol` is the new volume and `1` is the `nmirror` value.

The block device for the snapshot volume will be
`/dev/vx/dsk/boot_dg/SNAP-bootdisk1-vol`.

- 3 Configure a service by exporting
the `/dev/vx/dsk/boot_dg/SNAP-bootdisk1-vol` file as a virtual disk.

```
primary# ldm add-vdiskserverdevice \  
/dev/vx/dsk/boot_dg/SNAP-bootdisk1-vol vdisk2@primary-vds0
```


- 4 Add the exported disk to logical domain1 first.

```
primary# ldm add-vdisk vdisk2 \  
SNAP-bootdisk1-vol@primary-vds0 logical domain1  
  
primary# ldm bind logical domain1  
  
primary# ldm start logical domain1
```

- 5 Start logical domain1 and boot logical domain1 from its primary boot disk vdisk1.

```
primary# ldm bind logical domain1  
  
primary# ldm start logical domain1
```

- 6 If the new virtual disk device node entries do not show up in the `/dev/[r]dsk` directories, then run the `devfsadm` command in the guest domain:

```
logical domain1# devfsadm -C
```

where `vdisk2` is the `c0d2s#` device.

```
logical domain1# ls /dev/dsk/c0d2s*
```

```
/dev/dsk/c0d2s0 /dev/dsk/c0d2s2 /dev/dsk/c0d2s4 /dev/dsk/c0d2s6  
/dev/dsk/c0d2s1 /dev/dsk/c0d2s3 /dev/dsk/c0d2s5 /dev/dsk/c0d2s7
```

- 7 Mount the root file system of `c0d2s0` and modify the `/etc/vfstab` entries such that all `c#d#s#` entries are changed to `c0d0s#`. You must do this because logical domain2 is a new logical domain and the first disk in the operating system device tree is always named as `c0d0s#`.

- 8 Stop and unbind logical domain1 from its primary boot disk vdisk1.

```
primary# ldm stop logical domain1  
primary# ldm unbind logical domain1
```

- 9 After you change the `vfstab` file, unmount the file system and unbind `vdisk2` from logical domain1:

```
primary# ldm remove-vdisk vdisk2 logical domain1
```

- 10 Bind vdisk2 to logical domain2 and then start and boot logical domain2.

```
primary# ldm add-vdisk vdisk2 vdisk2@primary-vds0 logical domain2
```

```
primary# ldm bind logical domain2
```

```
primary# ldm start logical domain2
```

After booting logical domain2, appears as logical domain1 on the console because the other host-specific parameters like hostname and IP address are still that of logical domain1.

```
logical domain1 console login:
```

- 11 To change the parameters bring logical domain2 to single-user mode and run the `sys-unconfig` command.
- 12 Reboot logical domain2.
During the reboot, the operating system prompts you to configure the host-specific parameters such as hostname and IP address, which you must enter corresponding to logical domain2.
- 13 After you have specified all these parameters, logical domain2 boots successfully.

Configuring Oracle VM Server for SPARC guest domains for disaster recovery

The Oracle VMs can be configured for disaster recovery by replicating the boot disk using replication methods like Hitachi TrueCopy, EMC SRDF, Veritas Volume Replicator, and so on. The network configuration for the Oracle VM in the primary site may not be effective in the secondary site if the two sites are in different IP subnets. You will need to make these additional configuration changes to the LDom resource.

To configure the guest domains for disaster recovery, you need to configure VCS on both the sites in the Control Domains with GCO option.

Refer to the *Veritas Cluster Server Administrator's Guide* for more information about global clusters.

To set up the guest domain for disaster recovery

- 1 On the primary site, create the guest domain using `ldm` commands and configure the network-related parameters.
- 2 On the primary site after you boot the guest domain, copy and install the package `VRTSvcsnr` from the VCS installation media in the guest domain. This package installs the `vcs-network-reconfig` service in the guest domain. This service makes sure that the site-specific network parameters are applied when the guest domain boots.
- 3 On the primary site, shut down the guest domain.
- 4 Use replication specific commands to failover the replication to the secondary site from the primary site.
- 5 Repeat step 1 on the secondary site.
- 6 Perform step 7, step 8, step 9, and step 10 on both the primary cluster and the secondary clusters.
- 7 Create a VCS service group and add a VCS LDom resource for the guest domain.

Configure the following disaster recovery-related attributes on the LDom resource with site-specific values for each: IPAddress, Netmask, Gateway, DNS (DNS Server).

Set the value of the `ConfigureNetwork` attribute to 1 to make the changes effective. The LDom agent does not apply the disaster recovery-related attributes to the guest domain if the value of the `ConfigureNetwork` attribute is 0.

- 8 Add the appropriate `Mount` and `DiskGroup` resources in the service group for the file system and the disk group on which the boot image of the guest domain resides.

Add a resource dependency from the LDom resource to the `Mount` resource and another dependency from the `Mount` resource to the `Diskgroup` resource.

- 9 Add the appropriate VCS replication resource in the service group. Examples of hardware replication agents are SRDF for EMC SRDF, HTC for Hitachi TrueCopy, MirrorView for EMC MirrorView, etc.

Refer to the appropriate VCS Replication agent guide for configuring the replication resource.

For VVR-based replication, add the appropriate `RVGPrimary` resource to the service group.

Refer to the following manuals for more information:

- For information about configuring VVR-related resources, see the *Veritas Storage Foundation and High Availability Solutions Replication Administrator's Guide*.
- For information about the VVR-related agents, see the *Veritas Cluster Server Bundled Agents Reference Guide*.

10 Add a dependency from the DiskGroup resource to the replication resource.

Figure 5-10 Sample resource dependency diagram for hardware replication based guest domains





Figure 5-11 Sample resource dependency diagram for VVR replication-based guest domains



The replication resource makes sure that when the resource is online in a site, the underlying replicated devices are in primary mode and the remote devices are in secondary mode. Thus, when the LDom resource goes online, the underlying storage will always be in read-write mode. When the LDom resource goes online, it sets the DR related parameters in the EEPROM parameter network-boot-arguments for the guest domain before starting the guest domain. When the guest domain boots, the vcs-network-reconfig service starts inside the guest domain. This service reads the EEPROM parameter and applies the disaster recovery related parameters by modifying the appropriate files inside the guest domain.

Software limitations

The following section describes some of the limitations of the Oracle VM server for SPARC software and how those software limitations affect the functionality of the Veritas Storage Foundation products.

Memory Corruption in the guest domain during SCSI commands

When running VxVM and DMP the system panics in the guest domain. The following error messages display on the console:

```
vxddmp: NOTICE: VxVM vxddmp V-5-3-289 DMP: Memory Overrun!  
Caller dmpscsi_sys.c(170) Ptr 0x3000528e580 Size 0x100
```

```
vxddmp: NOTICE: VxVM vxddmp V-5-3-289 DMP: Memory Overrun!  
Caller dmpgrio.c(824) Ptr 0x3002d7f1a80 Size 0xe8
```

These error messages are due to a kernel memory corruption occurring in the Solaris kernel driver stacks (virtual disk drivers). This issue occurs when issuing USCSICMD with the sense request enable (USCSI_RQENABLE) on a virtual disk from the guest.

Symantec has an open escalation with Oracle and an associated Oracle (SUN) bug id for this issue:

Oracle (SUN) Escalation number: 1-23915211

Oracle (SUN) bug id: 6705190 (ABS: uscsicmd on vdisk can overflow the sense buffer)

This Oracle (SUN) bug has been fixed in Sun patch 139562-02.

Exporting the raw volume device node fails

Following messages can be observed in the `/var/adm/messages` file:

```
vds: [ID 998409 kern.info] vd_setup_vd():  
/dev/vx/rdisk/testdg/testvol identification failed  
vds: [ID 790452 kern.info] vd_setup_vd():  
/dev/vx/rdisk/testdg/testvol can not be exported as a virtual disk  
(error 5)  
vds: [ID 556514 kern.info] vds_add_vd(): Failed to add vdisk ID 21  
vds: [ID 970787 kern.info] vds_add_vd(): No vDisk entry found for  
vdisk ID 21
```

Workaround: Export VxVM volumes using their block device nodes instead. Oracle is investigating this issue.

Oracle (SUN) bug id: 6716365 (disk images on volumes should be exported using the ldi interface)

This Oracle (Sun) bug is fixed in Oracle (Sun) patch 139562-02.

Resizing a Veritas Volume Manager volume (exported as a slice or full disk) does not dynamically reflect the new size of the volume in the guest

On resizing a VxVM volume exported to a guest, the virtual disk still shows the old size of the volume. The virtual disk drivers do not update the size of the backend volume after the volume is resized.

Oracle has an RFE for this issue (CR 6699271 Dynamic virtual disk size management).

Workaround: The guest must be stopped and rebound for the new size to be reflected.

This Oracle (Sun) bug is fixed in Oracle (Sun) patch 139562-02.

Known issues

The following section describes some of the known issues of the Oracle VM Server for SPARC software and how those known issues affect the functionality of the Veritas Storage Foundation products.

Guest-based known issues

The following are new known issues in this release of Veritas Storage Foundation and High Availability Solutions Support for Oracle VM Server for SPARC.

Encapsulating a non-scsi disk may fail

Trying to encapsulate a non-scsi disk which is a slice of a disk or a disk exported as a slice may fail with the following error:

```
VxVM vxslicer ERROR V-5-1-599 Disk layout does not support swap shrinking  
VxVM vxslicer ERROR V-5-1-5964 Unsupported disk layout.  
Encapsulation requires at least 0 sectors of unused space either at the  
beginning or end of the disk drive.
```

This is because while installing the OS on such a disk, it is required to specify the entire size of the backend device as the size of slice "s0", leaving no free space on the disk.

Boot disk encapsulation requires free space at the end or the beginning of the disk for it to proceed ahead.

Guest domain node shows only one PGR key instead of two after rejecting the other node in the cluster

For configuration information concerning the guest domain node shows only 1 PGR key instead of 2 after rejecting the other node in the cluster:

See [Figure 5-4](#) on page 125.

This was observed while performing a series of reboots of the primary and alternate I/O domains on both the physical hosts housing the two guests. At some point one key is reported missing on the coordinator disk.

This issue is under investigation. The `vxfsen` driver can still function as long as there is 1 PGR key. This is a low severity issue as it will not cause any immediate interruption. Symantec will update this issue when the root cause is found for the missing key.

Disk paths intermittently go offline while performing I/O on a mirrored volume

This was observed while testing the SFCFS stack inside a 4-node guest cluster where each node gets its network and virtual disk resources from multiple I/O domains within the same host.

See [“Supported configurations with SFCFS and multiple I/O Domains”](#) on page 124.

While performing I/O on a mirrored volume inside a guest, it was observed that a vdisk would go offline intermittently even when at least one I/O domain which provided a path to that disk was still up and running.

Symantec recommends that you install Solaris 10 Update 7 that contains the fix for Oracle (Sun) bug id 6742587 (vds can ACK a request twice).

Deadlock between DMP kernel and VDC driver during volume creation

This was observed by Oracle during their interoperability testing of 5.0 MP3. The deadlock happens when creating a mirrored VxVM volume, while there is ongoing I/O to a UFS file system on another disk which is not under VxVM. This issue has been observed typically in a large configuration such as 14 virtual CPUs and around 10Gig of memory configured for the guest domain running VxVM.

Relevant Oracle (Sun) bug id: 6744348

This known issue has been fixed and verified in the 5.0 MP3 RP1 release.

For the latest information on updates, patches, documentation, and known issues regarding this 5.0 MP3 RP1 release, see the following TechNote on the Symantec Technical Support website:

For Solaris SPARC:

<http://entsupport.symantec.com/docs/281987>

For Solaris x64:

<http://entsupport.symantec.com/docs/286955>

Split Storage Foundation stack known issues

The following are new known issues in this release of Veritas Storage Foundation and High Availability Solutions Support for Oracle VM Server for SPARC.

Caching of data writes on the backend volume in the service domain

This was observed by a customer during their evaluation of Oracle VM Server for SPARC with Storage Foundation. This issue occurs because data written to the virtual disk might get cached into the service domain before it is effectively written to the virtual disk backend. This can cause potential data loss if the service domain crashes while the data is still cached.

Oracle (Sun) bug id is: 6684721 (file backed virtual I/O should be synchronous)

This Oracle (Sun) bug is fixed in Oracle (Sun) patch 139562-02 that has been obsoleted by 138888-07.

A volume can become inaccessible from the guest in the event of control domain reboot

All access to such a volume hangs if the primary domain is rebooted. This is due to the vdisk corresponding to the volume does not come back online after the control domain reboots.

This issue has been identified and fixed under Oracle (Sun) bug id: 6795836 (vd_setup_vd() should handle errors from vd_identify_dev() better)

This Oracle (Sun) bug is fixed in Oracle (Sun) patch 141777-01.

Veritas Cluster Server support for using CVM with multiple nodes in a Oracle VM Server for SPARC environment

This chapter includes the following topics:

- [Clustering using Cluster Volume Manager](#)
- [Installing Storage Foundation on multiple nodes in a Logical Domain](#)
- [Cluster Volume Manager in the control domain for providing high availability](#)

Clustering using Cluster Volume Manager

The Veritas Volume Manager cluster functionality (CVM) makes logical volumes and raw device applications accessible throughout a cluster.

In the split Storage Foundation model, CVM is placed in the control domain and VxFS is placed in the guest domain. In this model, CVM provides high availability and shared storage visibility at the control domain level across multiple physical nodes in the cluster.

See [“Cluster Volume Manager in the control domain for providing high availability”](#) on page 156.

In the guest-based Storage Foundation stack model, CVM is placed in the guest domain, providing high availability and shared storage visibility at the guest domain level across multiple guest domains that act as the nodes in the cluster.

Installing Storage Foundation on multiple nodes in a Logical Domain

To install Storage Foundation on multiple nodes in a Solaris Logical Domains environment, you must complete the following operations, which are the same as on a single node:

- See [“Installing and configuring Oracle VM Server for SPARC and domains”](#) on page 130.
- See [“Installing Storage Foundation in the control domain or guest”](#) on page 130.
- See [“Installing Veritas File System in the guest domain”](#) on page 131.
- See [“Verifying the configuration”](#) on page 135.

Reconfiguring the clustering agents for Cluster Volume Manager

This section applies to only the Split Storage Foundation model.

For a Storage Foundation CVM, the following additional configuration steps are necessary:

- See [“Removing the vxfsckd resource”](#) on page 154.
- See [“Creating CVMVolDg in a group”](#) on page 155.

Removing the vxfsckd resource

After configuring Storage Foundation and CVM, remove the vxfsckd resource.

To remove the vxfsckd resource

- 1 Make the configuration writeable:

```
# haconf -makerw
```

- 2 Delete the resource:

```
# hares -delete vxfsckd
```

- 3 Make the configuration read-only:

```
# haconf -dump -makero
```

4 Stop the resources:

```
# hastop -all
```

5 Restart the resources.

```
# hastart
```

Run the `hastart` command on all nodes in the cluster.

Creating CVMVolDg in a group

The following procedure creates CVMVolDg in a given group.

To create CVMVolDg

1 Make the configuration writeable:

```
# haconf -makerw
```

2 Add the CVMVolDg resource:

```
# hares -add name_of_resource CVMVolDg name_of_group
```

3 Add a diskgroup name to the resource:

```
# hares -modify name_of_resource CVMDiskGroup diskgroup_name
```

4 Make the attribute local to the system:

```
# hares -local name_of_resource CVMActivation
```

5 Add the attribute to the resource.

```
# hares -modify name_of_resource CVMActivation \  
activation_value -sys nodename
```

Repeated this step on each of the nodes.

6 If you want to monitor volumes, enter the following command:

```
# hares -modify name_of_resource CVMVolume -add \  
name_of_volume
```

In a database environment, Symantec recommends you monitor volumes.

- 7 Modify the resource so that a failure of this resource does not bring down the entire group:

```
# hares -modify name_of_resource Critical 0
```

- 8 Enable the resources:

```
# hares -modify name_of_resource Enabled 1
```

- 9 Make the configuration read-only:

```
# haconf -dump -makero
```

- 10 Verify the configuration:

```
# hacf -verify
```

This should put the resource in the `main.cf` file.


Cluster Volume Manager in the control domain for providing high availability

The main advantage of clusters is protection against hardware failure. Should the primary node fail or otherwise become unavailable, applications can continue to run by transferring their execution to standby nodes in the cluster.

CVM can be deployed in the control domains of multiple physical hosts running Oracle VM Server for SPARC, providing high availability of the control domain.

[Figure 6-1](#) illustrates a CVM configuration.

Figure 6-1 CVM configuration in an Oracle VM Server for SPARC environment



If a control domain encounters a hardware or software failure causing the domain to shut down, all applications running in the guest domains on that host are also affected. These applications can be failed over and restarted inside guests running on another active node of the cluster.

Caution: As such applications running in the guests may resume or time out based on the individual application settings. The user must decide if the application must be restarted on another guest on the failed-over control domain. There is a potential data corruption scenario if the underlying shared volumes get accessed from both of the guests simultaneously.

Shared volumes and their snapshots can be used as a backing store for guest domains.

Note: The ability to take online snapshots is currently inhibited because the file system in the guest cannot coordinate with the VxVM drivers in the control domain.

Make sure that the volume whose snapshot is being taken is closed before the snapshot is taken.

The following example procedure shows how snapshots of shared volumes are administered in such an environment. In the example, `datavol1` is a shared volume being used by guest domain `logical domain1` and `c0d1s2` is the front end for this volume visible from `logical domain1`.

To take a snapshot of `datavol1`

- 1 Unmount any VxFS file systems that exist on `c0d1s0`.
- 2 Stop and unbind `logical domain1`:

```
primary# ldm stop logical domain1
```

```
primary# ldm unbind logical domain1
```

This ensures that all the file system metadata is flushed down to the backend volume, `datavol1`.

- 3 Create a snapshot of `datavol1`.

See the *Veritas Storage Foundation Administrator's Guide* for information on creating and managing third-mirror break-off snapshots.

- 4 Once the snapshot operation is complete, rebind and restart `logical domain1`.

```
primary# ldm bind logical domain1
```

```
primary# ldm start logical domain1
```

- 5 Once `logical domain1` boots, remount the VxFS file system on `c0d1s0`.

Veritas Cluster Server: Configuring Oracle VM Server for SPARC for high availability

This chapter includes the following topics:

- [About Veritas Cluster Server in a Oracle VM Server for SPARC environment](#)
- [About Veritas Cluster Server configuration models in an Oracle VM Server for SPARC environment](#)
- [Oracle VM Server for SPARC guest domain migration in VCS environment](#)
- [About configuring Veritas Cluster Server for Oracle VM Server for SPARC with multiple I/O domains](#)
- [Configuring VCS to manage a Logical Domain using services from multiple I/O domains](#)

About Veritas Cluster Server in a Oracle VM Server for SPARC environment

Veritas Cluster Server (VCS) provides high availability (HA) for Oracle VM Server for SPARC. You can configure VCS to monitor the Logical Domain, services to the Logical Domain, and the applications that run in logical domain, or to monitor only the applications that run in the logical domain.

See [“About Veritas Cluster Server configuration models in an Oracle VM Server for SPARC environment”](#) on page 162.

Table 7-1 lists the failure scenarios and the VCS failover options based on which you can plan your VCS configuration in an Oracle VM Server for SPARC environment.

Table 7-1 Veritas Cluster Server failover options for logical domain failure

Failure scenario	VCS failover	Typical VCS configuration
Logical domains, their storage, or switches fail	VCS fails over the logical domain from one node to another node	VCS is installed in the control domain of each node. See “Veritas Cluster Server setup to fail over a logical domain on a failure of logical domain” on page 163.
Logical domains, their storage, or switches fail Or Applications that run in logical domains fail	VCS fails over the logical domain from one node to another node. The application starts on the same logical domain after the logical domain failover.	VCS is installed in the control domain of each node, and single node VCS is installed on each guest domain. See “Veritas Cluster Server setup to fail over a logical domain on a failure of Application running inside the logical domain or logical domain itself” on page 168.
Applications that run in logical domains fail Or logical domain where the application is running fails	VCS fails over the application from one logical domain to another.	VCS is installed in the guest domain of each node. See “Veritas Cluster Server setup to fail over an Application running inside logical domain on a failure of Application” on page 175.

Dynamic reconfiguration of memory and CPU of a guest domain

VCS supports dynamic reconfiguration of memory and CPU assigned to a guest domain. Modify the values of the Memory and NumCPU attributes of an LDom resource to dynamically reconfigure the memory and CPU of a guest domain.

Veritas Cluster Server requirements

For installation requirements:

See “[System requirements](#)” on page 128.

For the configuration model where VCS is installed on the control domain:

- VCS requires shared storage that is visible across all the nodes in the cluster.
- Configure Logical Domain on each cluster node.
- The logical domain’s boot device and application data must reside on shared storage.

For the configuration model where VCS is installed on the guest domain:

- VCS requires the application data to reside on the shared storage.
- Each node can have more than one logical domain.
- Each logical domain can have its own boot device.

Veritas Cluster Server limitations

Depending on the configuration model, the following limitations apply to VCS in an Oracle VM Server for SPARC environment.

Limitations for VCS configuration in the control domain:

- Each logical domain configured under VCS must have at least two VCPUs. With one VCPU, the control domain always registers 100% CPU utilization for the logical domain. This is an Oracle VM Server for SPARC software issue.

Limitation for VCS configuration in the guest domain:

- Do not export a physical device to more than one guest domains on the same physical node. For example: If you configure I/O fencing in guest domain, and if one of the guest domains dies, then I/O fencing fences off the other guest domains as well.

Veritas Cluster Server known issues

The following section describes known issues with VCS in a Oracle VM Server for SPARC environment.

Shutting down the control domain may cause the guest domain to crash (1631762)

Set up	Two Oracle SPARC Enterprise T5240 server physical boxes, each with a control domain and a guest domain. The guest domains in each of the physical boxes form a two node cluster. The nodes are named node 0 and node 1 in the following text.
Symptom	Gracefully shutting down the control domain of node 0 causes the guest domain of node 0 to crash.
Analysis	<p>Even though the guest domain can continue to function when the control domain is shut down, the heartbeats between node 0 and node 1 are lost as the control domain shuts down. As a result, the cluster forms two separate sub-clusters without the sub-clusters being able to see each others' heartbeats.</p> <p>I/O fencing resolves the split brain situation and determines that only one sub-cluster will continue to function while the other sub-cluster should panic. Therefore, the panic of node 0 is expected behavior.</p>
Resolution:	<p>None; this is expected behavior. However, Symantec recommends keeping the control domain highly available for the proper function of the SFCFS and SFRAC stack in the guest domains.</p> <p>If you have set up a virtual private LLT heartbeats between the two guests (node 0 and node1), the guest will not crash.</p>

About Veritas Cluster Server configuration models in an Oracle VM Server for SPARC environment

When you configure VCS in an Oracle VM Server for SPARC environment, you need some specific information about the logical domain, network, and the storage devices that the logical domain requires to run.

You need to know the following information about your logical domain:

- The logical domain's name
- The names of the primary network interfaces for each node
- The virtual switch that the logical domain uses
- The name and type of storage that the logical domain uses

VCS configuration depends on whether you want VCS to fail over the logical domain or the application on a failure:


- See [“Veritas Cluster Server setup to fail over a logical domain on a failure of logical domain”](#) on page 163.
- See [“Veritas Cluster Server setup to fail over a logical domain on a failure of Application running inside the logical domain or logical domain itself”](#) on page 168.
- See [“Veritas Cluster Server setup to fail over an Application running inside logical domain on a failure of Application”](#) on page 175.

See [“About Veritas Cluster Server in a Oracle VM Server for SPARC environment”](#) on page 159.

Veritas Cluster Server setup to fail over a logical domain on a failure of logical domain

[Figure 7-1](#) illustrates a typical setup where VCS installed in the control domain provides high availability to the logical domain and its resources.

Figure 7-1 Typical setup for logical domain high availability with VCS installed in control domains




A typical two-node VCS configuration for logical domain high availability has the following software and hardware infrastructure:

- Oracle VM Server for SPARC software is installed on each system Node1 and Node2.
- Shared storage is attached to each system.
- A logical domain (logical domain1) exists on both the nodes with a shared boot device.
- Each LDom has an operating system installed.
- VCS is installed in the control domains of each node.

Figure 7-2 Workflow to configure VCS to fail over a logical domain on a failure


For VCS to monitor the LDom:



Configuration scenarios

Figure 7-3 shows the basic dependencies for an logical domain resource.

Figure 7-3 A logical domain resource depends on storage and network resources



Network configuration

Use the NIC agent to monitor the primary network interface, whether it is virtual or physical. Use the interface that appears using the `ifconfig` command.

Recommended network device to monitor.

Figure 7-4 is an example of an logical domain service group. The logical domain resource requires both network (NIC) and storage (Volume and DiskGroup) resources.

See the *Veritas Cluster Server Bundled Agents Reference Guide* for more information about the NIC agent.

Storage configurations

Depending on your storage configuration, use a combination of the Volume, DiskGroup, and Mount agents to monitor storage for logical domains.


Note: Symantec recommends volumes or flat files in volumes that are managed by VxVM for LDom storage for configurations where VCS is in control domain.

Veritas Volume Manager exposed volumes

Veritas Volume Manager (VxVM) exposed volumes is the recommended storage solution for VCS in a control domain configuration. Use the Volume and DiskGroup agents to monitor a VxVM volume. VCS with VxVM provides superior protection for your highly available applications.

Figure 7-4 shows an logical domain resource that depends on a Volume and DiskGroup resource.

Figure 7-4 The logical domain resource can depend on resources such as NIC, Volume, and DiskGroup depending on the environment




For more information about the Volume and DiskGroup agents, refer to the *Veritas Cluster Server Bundled Agents Reference Guide*.

Image files

Use the Mount, Volume, and DiskGroup agents to monitor an image file.

[Figure 7-5](#) shows how the LDom resource depends on the resources with image file.

Figure 7-5 The LDom resource in conjunction with different storage resources



See the *Veritas Cluster Server Bundled Agents Reference Guide* for more information about the Mount agent.

Configuring logical domain

You must perform the following steps to configure logical domain.

To configure logical domain

- 1 Make sure that the network and storage setup meet the VCS requirements.
See [“Veritas Cluster Server requirements”](#) on page 161.
- 2 Make sure that you have installed the required Solaris operating system in the logical domain.
- 3 Create logical domain (ldom1) on each system with an identical configuration and boot device.

Installing Veritas Cluster Server inside the control domain

You must install VCS in the control domain of each system.

To install Veritas Cluster Server inside the control domain

- ◆ Install and configure VCS in the control domain of each system.

The process for installing VCS in the control domain is very similar to the regular installation of VCS. However, you must specify the host name of the control domain for the name of the host where you want to install VCS.

See the *Veritas Cluster Server Installation Guide* for VCS installation and configuration instructions.

Creating the Veritas Cluster Server service groups for logical domains

You can also create and manage service groups using the Veritas Operations Manager (VOM), or through the command line.

See the *Veritas Cluster Server Administrator's Guide* for complete information about using and managing service groups.

Verifying a logical domain service group failover

Verify the configuration in different situations.

Using hagr - switch command

Switch the logical domain service group to another node in the cluster to make sure the service group fails over. If all the resources are properly configured, the service group shuts down on the first node and comes up on the second node.

Other verification scenarios

In all of these verification scenarios, you are stopping or moving an logical domain, or stopping a resource for that logical domain. VCS should detect the failure, or the movement, and either failover the effected logical domain or take no action.


The following list presents some quick testing scenarios;

- From outside of VCS control, stop the logical domain. VCS should fail the logical domain over to the other node.
- Boot the logical domain through VCS by entering a `hagr -online` command. move the logical domain to another node by shutting it down through VCS on the node where the logical domain is running. Boot the logical domain outside of VCS control on the other node- the service group comes online on that node.

Veritas Cluster Server setup to fail over a logical domain on a failure of Application running inside the logical domain or logical domain itself

[Figure 7-6](#) illustrates a typical setup where VCS installed in the control domain provides high availability to applications that run in the guest domains.

Figure 7-6 Typical setup for application high availability with VCS installed in control domains




A typical two-node VCS configuration that fails over the logical domains to keep the applications that run in them highly available has the following infrastructure:

- Oracle VM Server for SPARC software is installed on each system Node1 and Node2.
- Shared storage is attached to each system.
- A logical domain (logical domain1) with same configuration details exists on both the nodes with a shared boot device.
- Each logical domain has an operating system installed.
- VCS is installed in the control domains of each node.
- Each guest domain has single-node VCS installed. VCS kernel components are not required.
- VCS service group exists inside the guest domain for the application running inside the guest domain. VCS in the control domain uses this service group to manage the applications using RemoteGroup resource.

- Service group with RemoteGroup resource exists in the control domain to monitor the application service group in the guest domain.
- Service group with LDom resource exists in the control domain.
- An online global firm dependency exists from RemoteGroup service group to the LDom service group.

Figure 7-7 A logical domain resource depends on storage and network resources



You can configure VCS to keep the logical domains highly available. In addition to monitoring the logical domain, you can also configure VCS to monitor the applications that run in them.

You need to perform additional steps for VCS in the control domain to manage applications in the guest domains. After you install VCS in the control domain, you must create separate service groups for the RemoteGroup resource and logical domain resource with online global firm dependency.

Note: If you create the RemoteGroup resource as part of the logical domain service group, then the RemoteGroup resource state remains as UNKNOWN if the logical domain is down. VCS does not probe the service group and cannot bring the logical domain online. The online global firm dependency between the service groups allows VCS to fail over a faulted child logical domain service group independent of the state of the parent RemoteGroup service group.

Perform the following tasks to configure VCS to fail over a logical domain due to its failure:

- Review the configuration scenarios
See [“Configuration scenarios”](#) on page 165.
- Configure logical domains
See [“Configuring logical domain”](#) on page 167.
- Install VCS on control domain
See [“Installing Veritas Cluster Server inside the control domain”](#) on page 167.
- Create VCS service group for the logical domain

See [“Creating the Veritas Cluster Server service groups for logical domains”](#) on page 168.


Perform the following additional tasks to configure VCS to fail over a logical domain on an application failure:

- Install single-node VCS on guest domain
See [“Installing single-node Veritas Cluster Server inside the guest domain”](#) on page 173.
- Configure VCS in control domain to monitor the application in guest domain
See [“Configuring Veritas Cluster Server to monitor the application in the guest domain”](#) on page 173.


[Figure 7-8](#) depicts the workflow to configure VCS to manage the failure of a logical domain or the failure of an application that runs in an logical domain.

Figure 7-8 Workflow to configure VCS to fail over a logical domain on a failure

For VCS to monitor the LDom:



For VCS to monitor the application in guest domain:



Configuring Veritas Cluster Server for application monitoring

You must perform the following procedures to configure VCS to monitor the application in the guest domain:

- See [“Installing single-node Veritas Cluster Server inside the guest domain”](#) on page 173.
- See [“Configuring Veritas Cluster Server to monitor the application in the guest domain”](#) on page 173.

Installing single-node Veritas Cluster Server inside the guest domain

Perform the following steps to install one-node Veritas Cluster Server (VCS) inside the guest domain:

To install and configure one-node Veritas Cluster Server inside the logical domain

- 1 Install one-node VCS (no kernel components required) in the guest domain.
See the *Veritas Cluster Server Installation Guide* to perform a single-node VCS installation in the logical domains.
- 2 Start the VCS engine.


Configuring Veritas Cluster Server to monitor the application in the guest domain

Perform the following steps to configure Veritas Cluster Server (VCS) in the control domain to monitor the application in the guest domain.

To configure Veritas Cluster Server to monitor the application in the guest domain

- 1 Configure a VCS service group (asg1) for the application.
The ManualOps attribute of the service group must remain set to true, the default value.
- 2 Add a VCS user (asg1 -admin) with the minimum privilege as the group operator of the VCS service group (asg1).
- 3 Configure a RemoteGroup service group (rsg1) in the control domain to monitor the VCS service group (asg1) that was configured in 1.
- 4 Set the value of the following RemoteGroup resource attributes as follows:
 - RestartLimit attribute of the resource or type to 1 or higher
 - OfflineWaitLimit attribute of the resource or type to 1
 - ToleranceLimit attribute of the resource or type to 1
- 5 Create the dependencies between the groups and resources as shown in [Figure 7-9](#).

Figure 7-9 Group and resource dependency diagram



Note: RemoteGroup and Application service groups are required only when you want to configure VCS to monitor the application in the guest domain.

RemoteGroup resource definition

The resource definition for the RemoteGroup resource is as follows:


```
RemoteGroup rsg1 (  
    GroupName = asg1  
    IPAddress = <IP address of logical domain1>  
    ControlMode = OnOff  
    Username = asg1-admin  
    Password = <asg1-admin's password>  
)
```

See the *Veritas Cluster Server Bundled Agents Reference Guide* for more information on the RemoteGroup agent.

Veritas Cluster Server setup to fail over an Application running inside logical domain on a failure of Application

Figure 7-10 illustrates a typical VCS setup to provide high availability for applications that run in guest domains.

Figure 7-10 Typical setup for applications high availability with Veritas Cluster Server installed in guest domains



A typical two-node VCS configuration that fails over the applications to keep the applications that run in logical domains highly available has the following infrastructure:

- Oracle VM Server for SPARC software is installed on each system Node1 and Node2.
- Shared storage is attached to each system.
- Logical domains are created on both the nodes that may have local boot devices.
- Each LDom has an operating system installed.
- VCS is installed in the guest domains of each node.

Workflow:

- Set up guest domain and install Solaris OS
- Install VCS on the guest domain
- Create Application service group in the guest domain

Configuring Veritas Cluster Server to fail over an application on a failure

You must install and configure Veritas Cluster Server (VCS) in the guest domains of each system to enable VCS to manage applications in the guest domains.

To configure Veritas Cluster Server to manage applications in the guest domains

- 1 Install and configure VCS in the guest domains of each system.
See the *Veritas Cluster Server Installation Guide* for installation and configuration instructions.
- 2 Create two virtual NICs using private virtual switches for private interconnects.
You can configure virtual switches with no physical network interfaces if you want the failover across logical domains in the same control domain.
- 3 Configure VCS service group for the application that you want to monitor.
 - Configure Mount and Disk resources to monitor the storage.
 - Configure NIC resources to monitor the network.
 - Configure application resources using the application-specific agent.See the *Veritas Cluster Server Administrator's Guide* for more details on configuring applications and resources in VCS.
See the *Veritas Cluster Server Bundled Agents Reference Guide* for details on the storage and networking bundled agents.

Oracle VM Server for SPARC guest domain migration in VCS environment

VCS supports cold, warm, and live migration, also known as domain migration, for Oracle VM Server for SPARC guest domains.

Domain migration enables you to migrate a guest domain from one host system to another host system. The system on which the migration is initiated is the source system. The system to which the domain is migrated is the target system.

While a migration operation is in progress, the domain that you want to migrate transfers from the source system to the migrated domain on the target system.

The domain migration until Oracle VM Server for SPARC 2.0 release is a warm migration. A warm migration is where the domain that you want to migrate enters a suspended state before the migration.

The Oracle VM Server for SPARC 2.1 introduces live migration, which provides performance improvements that enable an active domain to migrate while it continues to run.

In addition to live migration, you can migrate bound or inactive domains. This migration is a cold migration.

You can use domain migration to perform tasks such as the following:

- Balancing the load between systems
- Performing hardware maintenance while a guest domain continues to run

Overview of a warm migration

The Logical Domains Manager on the source system accepts the request to migrate a domain and establishes a secure network connection with the Logical Domains Manager running on the target system. Once this connection has been established, the migration occurs.

The migration operation occurs in the following phases:

- Phase 1** After connecting with the Logical Domains Manager running in the target host, information about the source system and domain are transferred to the target host. The Logical Domains Manager on the target host uses this information to perform a series of checks to determine whether a migration is possible. The checks differ depending on the state of the source domain. For example, if the source domain is active the Logical Domains Manager performs a different set of checks than if the domain is bound or inactive.
- Phase 2** When all checks in Phase 1 have passed, the source and target systems prepare for the migration. The Logical Domains Manager on the source suspends the source domain. On the target system, the Logical Domains Manager creates a domain to receive the source domain.
- Phase 3** For an active domain, the next phase is to transfer all the runtime state information for the domain to the target. The Logical Domains Manager retrieves this information from the hypervisor. On the target, the Logical Domains Manager installs the state information in the hypervisor.

Phase 4 Handoff—after all state information is transferred, the handoff occurs when the target domain resumes execution (if the source was active). The Logical Domain Manager on the source destroys the source domain. From this point on, the target domain is the sole version of the domain running.

Overview of a live migration

The Logical Domains Manager on the source system accepts the request to migrate a domain and establishes a secure network connection with the Logical Domains Manager that runs on the target system. The migration occurs after this connection has been established.

The migration operation occurs in the following phases:

Phase 1 After the source system connects with the Logical Domains Manager that runs in the target system, the Logical Domains Manager transfers information about the source system and the domain to be migrated to the target system. The Logical Domains Manager uses this information to perform a series of checks to determine whether a migration is possible. The Logical Domains Manager performs state-sensitive checks on the domain that you plan to migrate. The checks it performs is different for an active domain than for bound or inactive ones.

Phase 2 When all checks in Phase 1 have passed, the source and target systems prepare for the migration. On the target system, the Logical Domains Manager creates a domain to receive the domain. If the domain that you plan to migrate is inactive or bound, the migration operation proceeds to Phase 5.

Phase 3 If the domain that you want to migrate is active, its runtime state information is transferred to the target system. The domain continues to run, and the Logical Domains Manager simultaneously tracks the modifications that the operating system makes to this domain. The Logical Domains Manager on the source retrieves this information on the source from the source hypervisor and sends the information to the Logical Domains Manager on the target. The Logical Domains Manager on the target installs this information in the hypervisor for the target.

Phase 4 The Logical Domains Manager suspends the domain that you want to migrate. At this time, all of the remaining modified state information is re-copied to the target system. In this way, there should be little or no perceivable interruption to the domain. The amount of interruption depends on the workload.

Phase 5 A handoff occurs from the Logical Domains Manager on the source system to the Logical Domains Manager on the target system. The handoff occurs when the migrated domain resumes execution (if the domain to be migrated was active), and the domain on the source system is destroyed. From this point forward, the migrated domain is the sole version of the domain running.

With Oracle VM Server for SPARC 2.1, the default domain migration attempted is Live Migration. If the installed version of Oracle VM Server for SPARC is 2.0, the domain migration defaults to warm migration. For more details on supported configurations, read Chapter 9, Migrating Domains in the *Oracle® VM Server for SPARC 2.1 Administration Guide*.

VCS supports the following three varieties of Oracle VM Server for SPARC domain migration:

- Guest migration from one VCS node to other VCS node in the cluster, for example:

```
sys1# ldm migrate logical domain1 sys2
```

- Guest migration from a VCS node to a non-VCS node, for example:

```
sys1# ldm migrate logical domain1 sys3
```

- Renaming the logical domain during the migration to the target system, for example:

```
sys1# ldm migrate logical domain1 sys2:logical domain2
```

Prerequisites before you perform domain migration

Perform the following prerequisites before you perform a domain migration:

- Verify that the value of IntentionalOffline attribute for LDom type is 1. Note that 1 is the default value.
- Make sure that the LDom resource for the LDom that you plan to migrate is in an ONLINE or OFFLINE steady state.
- To rename the logical domain when you migrate it, make sure that the LDomName attribute for the LDom resource in VCS is localized with the target LDom name for the target node. When you rename it, VCS can continue to monitor the LDom after migration.
- Make sure that CfgFile attribute for LDom is configured before migration.

- Make sure that `RemoveLDomConfigForMigration` attribute is set before migration. If this attribute is set, the LDom Agent removes the LDom configuration from the system on which an `offline` or `clean` is called. This arrangement helps in the scenario when a LDom is failed-over to a target node and is migrated back to the source node. In the presence of LDom configuration on the source node, migration would not be possible. Refer to the LDom Agent attribute description in the *Bundled Agents Reference Guide* for Solaris for more information.

Supported deployment models for Oracle VM Server for SPARC domain migration with VCS

The following are the supported deployment models for Oracle VM Server for SPARC domain migration with VCS:

- See [“Migrating Oracle VM guest when VCS is installed in the control domain that manages the guest domain”](#) on page 180.
- See [“Migrating Oracle VM guest when VCS is installed in the control domain and single-node VCS is installed inside the guest domain to monitor applications inside the guest domain”](#) on page 181.
- See [“Migrating Oracle VM guest when VCS cluster is installed in the guest domains to manage applications for Oracle VM Server for SPARC version 2.1 and above”](#) on page 183.
- See [“Migrating Oracle VM guest when VCS cluster is installed in the guest domains to manage applications for Oracle VM Server for SPARC version 2.0”](#) on page 183.

Migrating Oracle VM guest when VCS is installed in the control domain that manages the guest domain

Use the following information to migrate when you have VCS installed in the control domain that manages the guest domain.

To perform a migration of an LDom when VCS is installed in the control domain

- ◆ Use the `ldm` command for migration.


```
ldm migrate [-f] [-n] [-p password_file] source_ldom \  
[user@target_host[:target_ldom]
```

For example:

```
Sys1# ldm migrate ldom1 Sys2
```

Figure 7-11 illustrates a logical domain migration when VCS is clustered between control domains.

Figure 7-11 Logical domain migration when VCS is clustered between control domains



Migrating Oracle VM guest when VCS is installed in the control domain and single-node VCS is installed inside the guest domain to monitor applications inside the guest domain

Use the following information to migrate when you have:

- VCS installed in the control domain
- The VCS in control domain manages the application in the guest domain, and
- Single-node VCS installed in the guest domain monitors the application in guest domain.

To perform a migration of the LDom when VCS is installed in the control domain that manages the applications in the guest domains

- ◆ Use the `ldm` command for migration.


```
ldm migrate [-f] [-n] [-p password_file] source_ldom \  
[user@target_host[:target_ldom]
```

For example:

```
Sys1# ldm migrate ldom1 Sys2
```

Figure 7-11 illustrates a logical domain migration when VCS is clustered between control domains and single-node VCS in the guest domain monitors applications.

Figure 7-12 Logical domain migration when VCS is clustered between control domains and single-node VCS in the guest domain monitors applications



Migrating Oracle VM guest when VCS cluster is installed in the guest domains to manage applications for Oracle VM Server for SPARC version 2.1 and above

Perform one of the following procedures when you want a migration of guest domain when VCS cluster is configured between guest domains.

To perform a migration of the LDom when VCS is installed in the guest domain that manages the applications in the guest domains for Oracle VM Server for SPARC version 2.1 and above

- ◆ Use the `ldm` command for migration.

```
ldm migrate [-f] [-n] [-p password_file] source_ldom \  
[user@target_host[:target_ldom]
```

For example:

```
Sys1# ldm migrate ldom1 Sys2
```

Migrating Oracle VM guest when VCS cluster is installed in the guest domains to manage applications for Oracle VM Server for SPARC version 2.0

The domain migration is a warm migration.

Note: You do not have to start and stop LLT and GAB. In a warm migration, LLT and GAB restart themselves gracefully.

To perform a domain migration for an LDom when VCS is installed in guest domains

- 1 Stop VCS engine. Use the `hastop -local -force` command on the system that has the logical domain that you plan to migrate. Perform this step so that GAB does not have to kill the VCS engine process when the migration is complete. GAB wants all clients to reconfigure and restart when the configuration is not in sync with other members in the cluster.
- 2 If CVM is configured inside the logical domain, perform this step. Set the value of the LLT peerinact parameter to sufficiently high value on all nodes in the cluster. You set the value to very high value so that while the logical domain is in migration, the system is not thrown out of the cluster by the other members in the cluster. If the CVM stack is unconfigured, the applications can stop.

See the *Veritas Cluster Server Administrator's Guide* for LLT tunable parameter configuration instructions.

- 3 If fencing is configured in single instance mode inside the logical domain, perform this step. Unconfigure and unload the vxfen module in the logical domain. Perform this step so that GAB does not panic the node when the logical domain migration is complete.
- 4 Migrate the logical domain from the control domain using the `ldm` interface. Wait for migration to complete.

```
ldm migrate [-f] [-n] [-p password_file] source_ldom \  
[user@target_host[:target_ldom]
```

For example:


```
Sys1# ldm migrate ldom1 Sys2
```

- 5 Perform this step if you performed step 3. Load and configure vxfen module in the logical domain. See the *Veritas Cluster Server Administrator's Guide* for information about I/O fencing and its administration.
- 6 Perform this step if you performed step 2. Reset the value of the LLT peerinact parameter to its original value on all nodes in the cluster.

See the *Veritas Cluster Server Administrator's Guide* for LLT tunable parameter configuration instructions.
- 7 Use the `hastart` command to start VCS engine inside the logical domain.

[Figure 7-13](#) illustrates a logical domain migration when VCS is clustered between control domains and single-node VCS in the guest domain monitors applications.


Figure 7-13 The logical domain migration when VCS is clustered between guest domains



About configuring Veritas Cluster Server for Oracle VM Server for SPARC with multiple I/O domains

With Oracle VM Server for SPARC virtualization technology, you can create multiple I/O domains (control domain and alternate I/O domain) to provide redundant storage and network services to a guest Logical Domain. A typical cluster-setup configured to use multiple I/O domains has two physical systems. On each physical system, the control domain and alternate I/O domain provide I/O services from back-end storage and network devices to a Logical Domain.

Figure 7-14 with guest Logical Domain on System A and System B using storage and network services from the control domain and alternate I/O domain



If there is a failure of storage or network services from one of the domains, the guest Logical Domain continues to function on the same physical system because it gets I/O services from the other I/O domain. However, when there is failure of services from both the I/O domains on a physical system, the Logical Domain on the physical system fails.

Configure VCS on multiple I/O domains to manage a Logical Domain. VCS fails over the Logical Domain from one system to a Logical Domain on another system when services from both the domains fail.

Note: Failover happens when I/O services from all I/O domains fail or the control domain goes down.

About Alternate I/O domain

Alternate I/O domain, is an Oracle technology available on Oracle VM server for SPARC, which provides highly available storage and network services to guest domains on a physical system.

Setting up the Alternate I/O domain

While setting up a system to support Logical Domain, the control domain (primary domain) owns all the I/O devices on the physical system. To create alternate I/O domain, you need to relinquish ownership of one of the PCI Express bus from control domain and assign it to a Logical Domain.

For more information on creating alternate I/O domain, refer to the Oracle Solaris documentation.

Configuring VCS to manage a Logical Domain with multiple I/O domains

Proceed to configure VCS. See [“Configuring VCS to manage a Logical Domain using services from multiple I/O domains”](#) on page 187.

Configuring VCS to manage a Logical Domain using services from multiple I/O domains

VCS provides high availability to Logical Domains using I/O services from multiple I/O domains. When I/O services from the control domain and alternate I/O domain fail, VCS fails over the LDom from one system to another system. LDom continues to be functional on the same system and does not need a fail over if one of the I/O domain continues to provide service.


VCS uses service groups and resources to manage the storage and network services that are provided to a Logical Domain. These service groups are monitored by the AlternateIO resource. The AlternateIO service group provides the information about the state of the storage and network services to the LDom agent. VCS fails over the Logical Domain when services from both the I/O domains fail.

Perform the following tasks to configure VCS to manage a Logical Domain:

- Identify supported storage and network services
See [Identify supported storage and network services](#)
- Determine the number of nodes to form VCS cluster
See [Determine the number of nodes to form VCS cluster](#)
- Install and configure VCS inside the control and alternate I/O domains
See [Install and configure VCS inside the control domain and alternate I/O domain](#)
- Configure storage services
See [Configuring storage services](#)
- Configure storage service groups
See [Configure storage service groups](#)
- Configure network service groups
See [Configure network service groups](#)
- Configure service group to monitor services from multiple I/O domains
See [Configure a service group to monitor services from multiple I/O domains](#)
- Configure AlternateIO resource
See [Configure the AlternateIO resource](#)
- Configure Logical Domain service group

See [Configure the service group for a Logical Domain](#)


Figure 7-15 Workflow to configure VCS on a physical system to manage a Logical Domain



A typical setup for a Logical Domain with multiple I/O services

Guest logical domain using I/O services from multiple I/O domains.

Figure 7-16 shows VCS configuration to monitor a logical domain using I/O services from multiple I/O domains



System A, System B - T5440 servers

LDom SG - Logical Domain service group

AlternateIO SG - AlternateIO service group

Storage SG - Storage service group

Network SG - Network service group

Identify supported storage and network services

The following back-end storage and network services can be exported to Logical Domains.

I/O services	Back-end device	VCS agents to be used
Storage	LUN, shared disk	Disk
	Flat file	Mount
	zpool	Zpool
	Veritas CVM volume	CVMVoIDG
Network	NIC	NIC

Determine the number of nodes to form VCS cluster

The total number of nodes that form a VCS cluster depends on the number of physical systems times the the control domain and alternate I/O domain on each physical system.

For example, if you have two physical systems, each having a control domain and an alternate I/O domain, you need to configure VCS as a four node cluster.

Install and configure VCS inside the control domain and alternate I/O domain

Install and configure VCS inside the control domain and alternate I/O domain

For more details, refer to the *Veritas™ Cluster Server Installation Guide*.

Configuring storage services

Depending upon the storage service, the configuration procedure differs.

- LUN, Shared Disk, or CVM volume
See [“About virtual disk multipathing for storage services”](#) on page 191.
See [“Configuring virtual disk multipathing for LUN, Shared Disk, or CVM Volume”](#) on page 191.
- ZFS volume
See [“Configuring storage services when back-end device is a ZFS volume”](#) on page 192.
- Flat file
For more information, refer to the LDom Administrator’s guide.
- Zpool
For more information, refer to the LDom Administrator’s guide.

About virtual disk multipathing for storage services

You must configure virtual disk multipathing only if the storage back-end device is a LUN, Shared Disk, or CVM volume.

Virtual disk multipathing enables you to configure a virtual disk on a guest Logical Domain to access its back-end storage by more than one path. This feature ensures that the virtual disk accessed by the guest logical domain remains accessible as long as services from one of the I/O domain are available.

For example, if you set up a virtual disk multipathing configuration to access a physical disk from a shared storage that is connected to more than one service domain. So, when the guest domain accesses the virtual disk, the virtual disk driver goes through one of the service domains to access the back-end storage. If the virtual disk driver cannot connect to the service domain, the virtual disk attempts to reach the back-end storage through a different service domain.

Configuring virtual disk multipathing for LUN, Shared Disk, or CVM Volume

To enable virtual disk multipathing, you must export a virtual disk back-end path from each service domain and add the virtual disks to the same multipathing group (mpgroup). The mpgroup is identified by a name and is configured when you export the virtual disk back-end.

To configure virtual disk multipathing

- 1 Add the physical disk back-end path of the disk service to the primary domain.

```
# ldm add-vdsdev mpgroup=data backend_path1 volume@primary-vds0
```

where `backend_path1`, is the path to the virtual disk back end from the primary domain.

- 2 Add the physical disk back-end path of the disk service to the alternate domain for disk added in Step 1.

```
# ldm add-vdsdev mpgroup=data backend_path2 volume@alternate-vds0
```

where `backend_path2`, is the path to the virtual disk back end from the alternate domain.

- 3 Export the virtual disk to the guest domain.

```
# ldm add-vdisk disk_name volume@primary-vds0 ldom_name
```

where `disk_name` is the name of the virtual storage device and `ldom_name` is the name of the Logical Domain.

Note: Do not set the value of the **Options** attribute to `exclusive`; **excl**. If set to `exclusive`, Logical Domain cannot use the multipathing functionality.

For more details on configuring virtual disk multipathing, refer to the *Oracle VM server for SPARC Administration Guide*.

Configuring storage services when back-end device is a ZFS volume

If you export ZFS volume as a back-end storage to Logical Domain, you need to

- 1 Export ZFS volume created in the control domain.
You do not need to configure `mpgroup`.
- 2 Export ZFS volume created in the alternate I/O domain.
You do not need to configure `mpgroup`.

Note: Ensure the ZFS volume size created in both domains matches.


- 3 Create ZFS root pool mirror inside the Logical Domain from the volumes exported from control domain and alternate I/O domain.

Configure storage service groups

VCS agents manage storage services that are made available to a guest Logical Domain. Depending on the back-end storage device, use the appropriate VCS agent. For more information on supported VCS agents, see [Identify supported storage and network services](#).

Note: You must configure a storage service group on each physical system in the cluster.

Figure 7-17 shows storage service groups in the control domain and alternate I/O domain on a physical system



Configuration parameter	Description
Localize resource attribute value	<p>You may need to localize VCS resource attributes depending on the type of back-end storage device.</p> <p>For example, for Disk resource, if the back-end storage paths from the control and alternate I/O domains are different, you need to localize the partition attribute.</p> <pre>Disk disk1 (Partition @primary = "/dev/rdisk/c3t50060E8000C46C50d2s2" Partition @alternate = "/dev/rdisk/c1t50060E8000C46C50d2s2")</pre>
Service group type	<p>Service groups that manage storage services in the control domain and alternate I/O domain must be configured as a parallel service group.</p>
Configure the SystemList attribute	<p>Modify the SystemList attribute of the service group to add hostnames of the control domain and alternate I/O domain configured on the physical system.</p>
Configure Phantom resource	<p>If all the resources are of the type Disk, configure a Phantom resource.</p> <p>The Disk resource is of the type OnOnly and does not contribute to determine the state of the service group. The Phantom resource enables VCS to determine the state of parallel service groups that do not include OnOff resources.</p> <p>For more information on the Phantom agent, refer to the Veritas™ Cluster Server Bundled Agents Reference Guide.</p>

An example of storage service group configuration from main.cf configuration (for a setup that has two physical systems)

Control domain host names – primary1, primary2

Alternate domain host names – alternate1, alternate2

```
group primary1-strsg (
  SystemList = { primary1 = 0, alternate1 = 1 }
  AutoStartList = { primary1, alternate1 }
  Parallel = 1
)
```

```
Disk disk1
(
Partition @primary1 = "/dev/rdisk/c3t50060E8000C46C50d2s2"
Partition @alternate1 = "/dev/rdisk/c1t50060E8000C46C50d2s2"
)

Phantom ph1 (
)

group primary2-strsg (
SystemList = { primary2 = 0, alternate2 = 1 }
AutoStartList = { primary2, alternate2 }
Parallel = 1
)

Disk disk2
(
Partition @primary2 = "/dev/rdisk/c3t50060E8000C46C50d2s2"
Partition @alternate2 = "/dev/rdisk/c1t50060E8000C46C50d2s2"
)


Phantom ph2 (
)
```

Configure network service groups

VCS agents manage network resources that are made available to a guest Logical Domain. Depending on the back-end storage device, use appropriate VCS agent. For more information, see [Identify supported storage and network services](#).

Note: You must configure a network service group on each physical system in the cluster.

Figure 7-18 shows network service groups in the control domain and alternate I/O domain



Perform the configuration steps for the network service group on each physical system.

Configuration parameter	Description
Localize network resource attribute	<p>You may need to localize VCS resources depending on the back-end network device.</p> <p>For example, for disk agent, if the network device exported from control and alternate I/O domain are different, you need to localize the Device attribute.</p> <pre>NIC primary1-network (Device @primary = nxge3 Device @alternate = nxge4)</pre>

Configuration parameter	Description
Service group type	Service groups that manage network services in the control domain and alternate I/O domain must be configured as a parallel service group.
Configure the SystemList attribute	Modify the SystemList attribute in the service group to add host names of the control domain and alternate I/O domain configured on the physical system.
Configure Phantom resource	<p>If all the resources are of the type NIC, configure a Phantom resource.</p> <p>The NIC resource is of the type OnOnly and does not contribute to determine the state of the service group. The Phantom resource enables VCS to determine the state of parallel service groups that do not include OnOff resources.</p> <p>For more information on the Phantom agent, refer to the Veritas™ Cluster Server Bundled Agents Reference Guide.</p>

An example of network service group configuration from main.cf (for a setup that has two physical systems)

Control domain host names – primary1, primary2

Alternate domain host names – alternate1, alternate2

```
group primary1-nwsg (
    SystemList = { primary1 = 0, alternate1 = 1 }
    AutoStartList = { primary1, alternate1 }
    Parallel = 1
)

NIC nicres1 (
    Device @primary1 = nxge3
    Device @alternate1 = nxge1
)

Phantom ph3 (
)

group primary2-nwsg (
    SystemList = { primary2= 0, alternate2 = 1 }
    AutoStartList = { primary2, alternate2 }
    Parallel = 1
)
```

```
NIC nicres2(  
    Device @primary2= nxge3  
    Device @alternate2 = nxge1  
)  
  
Phantom ph4 (  
)
```

Configure a service group to monitor services from multiple I/O domains

Configure a service group for the AlternateIO resource to monitor storage and network services that are exported from back-end devices to a Logical Domain.

Configuration notes for the service group:

- Configure the service group as a parallel or a failover service group. See, Type of service group configuration for the AlternateIO resource.
- If multiple storage services are exported to a Logical Domain, you can configure separate service groups to monitor each of the storage services. For example, you can configure separate service groups to monitor LUN and ZFS volume storage services.
- The SystemList attribute of the service group must contain only host names of the control domains present on each physical system in the cluster.
- Localize the StorageSG attribute of the service group with the list of the storage service groups configured for each node.
- Enable preonline trigger for a fail over type service group

```
# hagrps -modify aiosg TriggerPath bin/AlternateIO
```

where aiosg is the name of the service group

```
# hagrps -modify aiosg TriggersEnabled PREONLINE
```

Type of service group configuration for the AlternateIO resource

Service group type	Condition
--------------------	-----------

Parallel	<p>If storage services are simultaneously accessible to all nodes in the cluster, the service group of the AlternateIO resource must be configured as a parallel service group.</p> <p>For example, shared LUNs, shared Disks, CVM Volume.</p>
Fail over	<p>If storage services must be accessible only on one physical system (control domain and alternate I/O domain) in the cluster, configure the service group of the AlternateIO resource as a failover service group.</p> <p>For example, zpool.</p>

Configure the AlternatelO resource

The AlternateIO resource monitors storage and network services that are exported to a guest Logical Domain. The AlternateIO resource is not dependent on storage or network resources. However, its state depends upon the state of storage or network service groups.

Figure 7-19 shows that the AlternatelO resource does not have any dependency on storage or network resources.



Configuration parameter	Description
StorageSG attribute	<p>This attribute is a key value pair. A storage service group is the key and the value of the key can either be 0 or 1.</p> <p>Set the value of the key to 1 to bring the service group online when the AlternateIo resource comes online and to take the service group offline when the AlternateIo resource goes offline.</p> <p>Localize the StorageSG attribute of the AlternateIO resource with the list of storage service groups that are configured on each node.</p> <pre>AlternateIO altiores1 (StorageSG @primary1 = { primary1-strsg1 = 1 } StorageSG @primary2 = { primary2-strsg1 = 1 })</pre>
NetworkSG attribute	<p>This attribute is a key value pair. A network service group is the key and the value of the key can either be 0 or 1.</p> <p>Set the value of the key to 1 to bring the service group online when the AlternateIo resource comes online and to take the service group offline when the AlternateIo resource goes offline.</p> <p>Localize the NetworkSG attribute of the AlternateIO resource with the list of network service groups that are configured on each node.</p> <pre>AlternateIO altiores1 (NetworkSG @primary1 = { primary1-nwsg = 0 } NetworkSG @primary2 = { primary2-nwsg = 0 })</pre>

Configuration parameter	Description
Preonline trigger	<p>For any of the service groups configured in the StorageSG or NetworkSG attributes, if you set the value to 1, configure the preonline trigger at the service group level.</p> <p>Configuring the preonline trigger ensures that service groups listed in the StorageSG attributes are offline on all systems except onto the system where failover or a manual switch over is initiated.</p> <p>For information on enabling the preonline trigger, see Configure service group to monitor services from multiple I/O domains.</p>

Sample service group configuration for the AlternateIO resource

Assumption – Storage and network service groups are of the type parallel.


```
group aiosg (
    SystemList = { primary1 = 0, primary2 = 1 }
    AutoStartList = { primary1, primary2 }
    Parallel = 1
)

AlternateIO aiores1 (
    StorageSG @primary1 = { primary1-strsg = 0 }
    StorageSG @primary2 = { primary2-strsg = 0 }
    NetworkSG @primary1 = { primary1-nwsg = 0 }
    NetworkSG @primary2 = { primary2-nwsg = 0 }
)
```

Configure the service group for a Logical Domain

VCS uses the LDom agent to manage a guest logical domain. The Logical Domain resource has an online local hard dependency on the AlternateIO resource.

Figure 7-20 shows the dependency of LDom service group on the AlternateIO service group.



Configuration notes:

- Configure the service group as a fail over type service group.
- The SystemList attribute in the LDom service group must contain only host names of the control domains from each physical system in the cluster.
- The LDom service group must have online local hard dependency with the AlternateIO service group.

Sample configuration for LDom service group

The LDom service group must have online local hard dependency with the AlternateIO service group.

```
group ldmsg (  
    SystemList = { primary1 = 0, primary2 = 1 }  
    AutoStartList = { primary1, primary2 }  
)  
  
LDom ldmres (  
    LDomName = ldg1  
)
```

Failover scenarios

Scenario	Control domain	Alternate I/O domain	VCS behavior
State of each storage service group	Online	Online	No fail over
	Offline/FAULT	Online	No fail over
	Online	Offline/FAULT	No fail over
	Offline/FAULT	Offline/FAULT	Fail over
State of each network service group	Online	Online	No fail over
	Offline/FAULT	Online	No fail over
	Online	Offline/FAULT	No fail over
	Offline/FAULT	Offline/FAULT	Fail over
Domain state	Up	Up	No fail over
	Up	down	No fail over
	Down	Up	Fail over
	Down	down	Fail over

Recommendations while configuring VCS and Oracle VM Server for SPARC with multiple I/O domains

- Online and offline operations for service groups in the StorageSG attribute
 To manually bring online or take offline service groups that are configured in the StorageSG attribute do not use the AlternateIO resource or its service group.
 Instead, use service groups configured in the StorageSG attribute.
- Freeze the service group for the AlternateIO resource
 Freeze the AlternateIO service group before you bring online or take offline service groups configured in the StorageSG attribute of the AlternateIO resource. If you do not freeze the service group, the behavior of the Logical Domain is unknown as it is dependent on the AlternateIO service group.
- Configuring preonline trigger for storage service groups
 You must configure preonline trigger in the following scenario:
 When the service groups configured in the StorageSG attribute of the AlternateIO resource are of fail over type, and if you accidentally bring storage service groups online on another physical system in the cluster.

It is possible to bring the storage service groups online on another physical system because resources configured to monitor back-end storage services are present in different service groups on each physical system. Thus, VCS cannot prevent resources coming online on multiple systems. This may cause data corruption.

To configure preonline trigger for each service group listed in the StorageSG attribute, run the following commands:

- # hagrpl -modify *stg-sg* TriggerPath bin/AlternateIO/StorageSG
where *stg-sg* is the name of the storage service group
- # hagrpl -modify *stg-sg* TriggersEnabled PREONLINE

Note: Perform this procedure for storage service groups on each node.

- Set connection time out period for virtual disks

When a disk device is not available, I/O services from the guest domain to the virtual disks are blocked.

Symantec recommends to set a connection time out period for each virtual disk so that applications times out after the set period instead of waiting indefinitely.

```
# ldm add-vdisk timeout=seconds disk_name volume_name@service_name
ldom
```

Sample VCS configuration for AlternateIO resource configured as a fail over type

```
include "types.cf"
cluster altio-cluster (
  UserNames = { admin = XXXXXXXXXXXX }
  Administrators = { admin }
  HacliUserLevel = COMMANDROOT
)

system primary1 (
)

system alternatel (
)

system primary2 (
)
```

```
system alternate2 (
)

group aiosg (
  SystemList = { primary1 = 0, primary2 = 1 }
  AutoStartList = { primary1 }
  TriggerPath = "bin/AlternateIO"
  TriggersEnabled @primary1 = { PREONLINE }
  TriggersEnabled @primary2 = { PREONLINE }
)

AlternateIO altiories (
  StorageSG @primary1 = { primary1-strsg = 1 }
  StorageSG @primary2 = { primary2-strsg = 1 }
  NetworkSG @primary1 = { primary1-nwsg = 0 }
  NetworkSG @primary2 = { primary2-nwsg = 0 }
)

// resource dependency tree
//
// group aiosg
// {
// AlternateIO altiories
// }

group ldomsg (
  SystemList = { primary1 = 0, primary2 = 1 }
  AutoStartList = { primary1 }
)

LDom ldmguest (
  LDomName = ldg1
)

requires group aiosg online local hard

// resource dependency tree
//
```

```
// group ldomsg
// {
// LDom ldg1
// }

group primary1-strsg (
    SystemList = { primary1 = 0, alternatel = 1 }
    AutoStart = 0
    Parallel = 1
    TriggerPath = "bin/AlternateIO/StorageSG"
    TriggersEnabled @primary1 = { PREONLINE }
    TriggersEnabled @alternatel = { PREONLINE }
    AutoStartList = { primary1, alternatel }
)

Zpool zpres1 (
    PoolName @primary1= zfsprim
    PoolName @alternatel = zfsmirr
    ForceOpt = 0
)

// resource dependency tree
//
//     group primary1-strsg
//     {
//     Zpool zpres1
//     }

group primary1-nwsg (
    SystemList = { primary1 = 0, alternatel = 1 }
    Parallel = 1
)

Phantom ph1 (
)

NIC nicres1 (
    Device @primary1 = nxge3
```

```
        Device @alternate1 = nxge4
    )

// resource dependency tree
//
// group primary1-nwsg
// {
//   Phantom ph1
//   Proxy nicres1
// }

group primary2-strsg (
    SystemList = { primary2 = 0, alternate2 = 1 }
    Parallel = 1
    TriggerPath = "bin/AlternateIO/StorageSG"
    TriggersEnabled @primary2 = { PREONLINE }
    TriggersEnabled @alternate2 = { PREONLINE }
)

    Zpool zpres2 (
        PoolName @ primary2 = zfsprim
        PoolName @ alternate2 = zfsmirr
        ForceOpt = 0
    )

// resource dependency tree
//
//     group primary2-strsg
//     {
//     Zpool zpres2
//     }

group primary2-nwsg (
    SystemList = { primary2 = 0, alternate2 = 1 }
    Parallel = 1
)
```

```
Phantom ph2 (  
  )  
  
NIC nicres2 (  
    Device @primary2 = nxge3  
    Device @alternate2 = nxge4  
  )  
  
// resource dependency tree  
//  
// group primary2-nwsg  
// {  
//   Phantom ph2  
//   Proxy nicres2  
// }
```


Symantec ApplicationHA: Configuring Oracle VM Server for SPARC for high availability

This chapter includes the following topics:

- [About Symantec ApplicationHA](#)
- [Why Symantec ApplicationHA](#)
- [LDom configurations with Symantec ApplicationHA](#)
- [Symantec ApplicationHA in the guest domains \(LDoms\)](#)
- [VCS in the control domain and Symantec ApplicationHA in the guest domain \(LDom\)](#)
- [Installing and configuring ApplicationHA for application availability](#)
- [Additional documentation](#)

About Symantec ApplicationHA

Oracle VM Server for SPARC is a virtualization and partitioning solution supported on Oracle Solaris CoolThreads technology-based servers. Oracle VM Server for SPARC lets you create multiple virtual systems called logical domains (also called guest domains), on a single physical host.

Symantec ApplicationHA provides monitoring capabilities for applications running inside logical domains in the Oracle VM Server for SPARC virtualization environment. Symantec ApplicationHA adds a layer of application awareness to the core high availability (HA) functionality offered by Veritas™ Cluster Server (VCS) in the control domain.

Symantec ApplicationHA is based on VCS and uses similar concepts such as agents, resources, and service groups. However, it does not include the high availability cluster components such as the Group Membership and Atomic Broadcast (GAB), Low Latency Transport (LLT), Asynchronous Monitoring Framework (AMF), and Veritas Fencing (VxFEN). Symantec ApplicationHA has a lightweight server footprint that allows faster installation and configuration.

Before you install the product, read the *Symantec ApplicationHA Release Notes*. To install the product, follow the instructions in the *Symantec ApplicationHA Installation Guide*.

Why Symantec ApplicationHA

Symantec ApplicationHA provides the following key benefits:

- Out of the box integration with VCS.
- Full visibility and control over applications with the ability to start, stop, and monitor applications running inside guest domains.
- High availability of the application as well as the guest domain inside which the application runs.
- Graded application fault-management responses such as:
 - Application restart
 - ApplicationHA-initiated, graceful internal reboot (soft reboot) of a guest domain
 - VCS-initiated, external reboot (hard reboot) of guest domain
 - Failover of the guest domain to another VCS node
- Standardized way to manage applications using a single interface that is integrated with the Veritas Operations Manager (VOM) console.
- Specialized Application Maintenance mode, in which ApplicationHA allows you to intentionally take an application out of its purview for maintenance or troubleshooting.

LDom configurations with Symantec ApplicationHA


Symantec ApplicationHA supports the following LDom configurations:

- Symantec ApplicationHA in the guest domain.
- VCS in the control domain and Symantec ApplicationHA in the guest domain.

Symantec ApplicationHA in the guest domains (LDoms)

Symantec ApplicationHA can run within each guest domain to provide application monitoring and fault handling of applications running within the LDom. ApplicationHA manages and controls the applications and services that run inside the LDoms. This configuration provides restart of the application within the LDom, but not failover between the control domains or physical servers. In this configuration, the LDoms do not form a cluster.

Figure 8-1 provides an example of Symantec ApplicationHA in the guest domain.



For more information on Symantec ApplicationHA features, refer to the *Symantec ApplicationHA User's Guide*.

VCS in the control domain and Symantec ApplicationHA in the guest domain (LDom)

Using Symantec Application HA in the LDom in combination with Veritas Cluster Server (VCS) by Symantec in the control domain provides an end-to-end availability solution for LDom and their resources.

Symantec ApplicationHA provides the following for Applications in the LDom:

- Full visibility and control over applications with the ability to start, stop, and monitor applications running inside guest domains.
- Graded application fault-management responses such as:
 - Application restart
 - ApplicationHA-initiated, graceful internal reboot (soft reboot) of a guest domain
- Standardized way to manage applications using a single interface that is integrated with the Veritas Operations Manager (VOM) console.
- Specialized Application Maintenance mode, in which ApplicationHA allows you to intentionally take an application out of its purview for maintenance or troubleshooting.

VCS provides the following for LDom:

- VCS in the host (control domain) enables logical domain availability.
- VCS-initiated, external reboot (hard reboot) of guest domain
- Failover of the guest domain to another VCS node.

ApplicationHA running in the LDom can notify VCS running in the control domain to trigger a logical domain (LDom) failover.

The following figure illustrates how Symantec ApplicationHA and VCS are deployed in a typical Oracle VM Server for SPARC virtualization environment.

Figure 8-2 Symantec ApplicationHA in the guest domain and Veritas Cluster Server in the control domain





Figure 8-3 VCS in the control domain and ApplicationHA in the guest domain



For more information on Symantec ApplicationHA features, refer to the *Symantec ApplicationHA User's Guide*.

For more information on Veritas Cluster Server features, refer to the *Veritas Cluster Server Administrator's Guide*.

Installing and configuring ApplicationHA for application availability

The following procedure applies for the following LDom configurations:

- Symantec ApplicationHA in the guest domain.
- VCS in the control domain and Symantec ApplicationHA in the guest domain.

To set up a logical domain (LDom) environment with Symantec ApplicationHA:

- 1 Install ApplicationHA.
- 2 Configure ApplicationHA.

For installation and configuration information, refer to *Symantec ApplicationHA Installation Guide*.

Additional documentation

This section provides additional documentation.

Oracle Solaris documentation

See <http://www.oracle.com/us/technologies/virtualization/index.html>.

Symantec documentation

For Symantec product installation and configuration information:

- *Veritas Dynamic Multi-Pathing Installation Guide*
- *Veritas Storage Foundation Installation Guide*
- *Veritas Storage Foundation High Availability Installation Guide*
- *Veritas Storage Foundation for Cluster Server High Availability Installation Guide*
- *Veritas Cluster Server High Availability Installation Guide*
- *Veritas Cluster Server Bundled Agents Reference Guide*
- *Symantec ApplicationHA Installation Guide*

To locate Symantec product guides:

- Symantec Operations Readiness Tools (SORT):
<https://sort.symantec.com/documents>
- Storage Foundation DocCentral Site:
<http://sfdoccentral.symantec.com/>

