

Cluster Server Agent for Tibco EMS Server Installation and Configuration Guide

AIX, Linux, Solaris

6.2

Cluster Server Agent for Tibco EMS Server Installation and Configuration Guide

The software described in this book is furnished under a license agreement and may be used only in accordance with the terms of the agreement.

Agent Version: 6.2

Document version: 6.2 Rev 1

Legal Notice

Copyright © 2015 Symantec Corporation. All rights reserved.

Symantec, the Symantec Logo, the Checkmark Logo, Veritas, the Veritas Logo, InfoScale, CommandCentral, NetBackup, Enterprise Vault, and LiveUpdate are trademarks or registered trademarks of Symantec Corporation or its affiliates in the U.S. and other countries. Other names may be trademarks of their respective owners.

The product described in this document is distributed under licenses restricting its use, copying, distribution, and decompilation/reverse engineering. No part of this document may be reproduced in any form by any means without prior written authorization of Symantec Corporation and its licensors, if any.

THE DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID. SYMANTEC CORPORATION SHALL NOT BE LIABLE FOR INCIDENTAL OR CONSEQUENTIAL DAMAGES IN CONNECTION WITH THE FURNISHING, PERFORMANCE, OR USE OF THIS DOCUMENTATION. THE INFORMATION CONTAINED IN THIS DOCUMENTATION IS SUBJECT TO CHANGE WITHOUT NOTICE.

The Licensed Software and Documentation are deemed to be commercial computer software as defined in FAR 12.212 and subject to restricted rights as defined in FAR Section 52.227-19 "Commercial Computer Software - Restricted Rights" and DFARS 227.7202, "Rights in Commercial Computer Software or Commercial Computer Software Documentation", as applicable, and any successor regulations. Any use, modification, reproduction release, performance, display or disclosure of the Licensed Software and Documentation by the U.S. Government shall be solely in accordance with the terms of this Agreement.

Symantec Corporation
350 Ellis Street
Mountain View, CA 94043

<http://www.symantec.com>

Technical Support

Symantec Technical Support maintains support centers globally. Technical Support's primary role is to respond to specific queries about product features and functionality. The Technical Support group also creates content for our online Knowledge Base. The Technical Support group works collaboratively with the other functional areas within Symantec to answer your questions in a timely fashion. For example, the Technical Support group works with Product Engineering and Symantec Security Response to provide alerting services and virus definition updates.

Symantec's support offerings include the following:

- A range of support options that give you the flexibility to select the right amount of service for any size organization
- Telephone and/or Web-based support that provides rapid response and up-to-the-minute information
- Upgrade assurance that delivers software upgrades
- Global support purchased on a regional business hours or 24 hours a day, 7 days a week basis
- Premium service offerings that include Account Management Services

For information about Symantec's support offerings, you can visit our website at the following URL:

www.symantec.com/business/support/index.jsp

All support services will be delivered in accordance with your support agreement and the then-current enterprise technical support policy.

Contacting Technical Support

Customers with a current support agreement may access Technical Support information at the following URL:

www.symantec.com/business/support/contact_techsupp_static.jsp

Before contacting Technical Support, make sure you have satisfied the system requirements that are listed in your product documentation. Also, you should be at the computer on which the problem occurred, in case it is necessary to replicate the problem.

When you contact Technical Support, please have the following information available:

- Product release level
- Hardware information

- Available memory, disk space, and NIC information
- Operating system
- Version and patch level
- Network topology
- Router, gateway, and IP address information
- Problem description:
 - Error messages and log files
 - Troubleshooting that was performed before contacting Symantec
 - Recent software configuration changes and network changes

Licensing and registration

If your Symantec product requires registration or a license key, access our technical support Web page at the following URL:

www.symantec.com/business/support/

Customer service

Customer service information is available at the following URL:

www.symantec.com/business/support/

Customer Service is available to assist with non-technical questions, such as the following types of issues:

- Questions regarding product licensing or serialization
- Product registration updates, such as address or name changes
- General product information (features, language availability, local dealers)
- Latest information about product updates and upgrades
- Information about upgrade assurance and support contracts
- Information about the Symantec Buying Programs
- Advice about Symantec's technical support options
- Nontechnical presales questions
- Issues that are related to CD-ROMs or manuals

Support agreement resources

If you want to contact us regarding an existing support agreement, please contact the support agreement administration team for your region as follows:

Asia-Pacific and Japan customercare_apj@symantec.com

Europe, Middle-East, and Africa semea@symantec.com

North America and Latin America [supportolutions@symantec.com](mailto:supportsolutions@symantec.com)

Documentation

Product guides are available on the media in PDF format. Make sure that you are using the current version of the documentation. The document version appears on page 2 of each guide. The latest product documentation is available on the Symantec website.

<https://sort.symantec.com/documents>

Your feedback on product documentation is important to us. Send suggestions for improvements and reports on errors or omissions. Include the title and document version (located on the second page), and chapter and section titles of the text on which you are reporting. Send feedback to:

doc_feedback@symantec.com

For information regarding the latest HOWTO articles, documentation updates, or to ask a question regarding product documentation, visit the Storage and Clustering Documentation forum on Symantec Connect.

<https://www-secure.symantec.com/connect/storage-management/forums/storage-and-clustering-documentation>

About Symantec Connect

Symantec Connect is the peer-to-peer technical community site for Symantec's enterprise customers. Participants can connect and share information with other product users, including creating forum posts, articles, videos, downloads, blogs and suggesting ideas, as well as interact with Symantec product teams and Technical Support. Content is rated by the community, and members receive reward points for their contributions.

<http://www.symantec.com/connect/storage-management>

Contents

Technical Support	3	
Chapter 1	Introducing the agent for Tibco EMS Server	9
	About the Cluster Server agent for Tibco EMS Server	9
	Supported software	10
	Features of the agent	10
	How the agent makes Tibco EMS Server highly available	10
	How the agent supports intelligent resource monitoring	38
	Tibco EMS Server agent functions	12
	Online	12
	Offline	12
	Monitor	13
	Clean	14
Chapter 2	Installing and configuring Tibco EMS Server for high availability	15
	About Tibco EMS	15
	Uniquely identifying Tibco EMS Server server instances	16
	Configuring the Tibco EMS Server for high availability	16
	Synchronizing accounts and services	16
	Removing physical host dependencies	16
Chapter 3	Installing, upgrading, and removing the agent for Tibco EMS Server	17
	Before you install the Cluster Server agent for Tibco EMS Server	17
	Prerequisites for enabling i18n support	18
	About the ACC library	18
	Installing the ACC library	19
	Installing the ACC library IPS package on Oracle Solaris 11 systems	20
	Installing the ACC library package on Solaris brand non-global zones	20
	Installing the agent in a VCS environment	21

	Installing the agent IPS package on Oracle Solaris 11 systems	22
	Installing agent packages on Solaris brand non-global zones	23
	Installing the agent in a Solaris 10 brand zone	24
	Uninstalling the agent in a VCS environment	25
	Removing the ACC library	26
Chapter 4	Configuring the agent for Tibco EMS Server	27
	About configuring the Cluster Server agent for Tibco EMS Server	27
	Importing the agent types file in a VCS environment	27
	Importing the agent types file using Cluster Manager (Java Console)	28
	Importing the agent types file using the CLI	28
	Tibco EMS Server agent attributes	29
Chapter 5	Enabling the agent for Tibco EMS Server to support IMF	37
	About Intelligent Monitoring Framework	37
	Benefits of IMF	38
	How the agent supports intelligent resource monitoring	38
	Agent functions for the IMF functionality	39
	imf_init	39
	imf_getnotification	39
	imf_register	39
	Attributes that enable IMF	39
	IMF	39
	IMFRegList	41
	Before you enable the agent to support IMF	41
	Enabling the agent to support IMF	41
	If VCS is in a running state	42
	If VCS is not in a running state	43
	Disabling intelligent resource monitoring	44
	Sample IMF configurations	44
Chapter 6	Configuring the service groups for Tibco EMS Server using the CLI	46
	About configuring service groups for Tibco EMS Server	46
	Before configuring the service groups for Tibco EMS Server	46
	Configuring service groups for Tibco EMS Server	47
	Failover configuration for Tibco EMS Server	47

	Cluster File System (CFS) based fault tolerant configuration for Tibco EMS Server	48
	Creating service groups for Tibco EMS Server under Solaris non-global zones	49
Chapter 7	Troubleshooting the agent for Tibco EMS Server	50
	Using the correct software and operating system versions	50
	Meeting prerequisites	50
	Configuring Tibco EMS Server resources	51
	Starting the Tibco EMS Server instance outside a cluster	51
	Reviewing error log files	51
	Reviewing cluster log files	52
	Using trace level logging	52
	Using Tibco EMS Server log files	53
Appendix A	Sample Configurations	54
	About sample configurations for the agents for Tibco EMS Server	54
	Sample agent type definition	55
	Sample resource configuration	56
	Sample service group configuration for Tibco EMS server in Failover setup	57
	Sample service group configuration for Tibco EMS server in Failover setup with Solaris Zones	59
	Sample resource dependency in a Failover configuration for Tibco EMS server	61
	Sample resource dependency in a Failover configuration for Tibco EMS server with Solaris Zones	62
	Sample service group configuration for Tibco EMS server in CFS based fault tolerant setup	63
	Sample resource dependency in a CFS based fault tolerant configuration for Tibco EMS server	67
	Service group dependency in a CFS based fault tolerant configuration for Tibco EMS Server	71
Index		73

Introducing the agent for Tibco EMS Server

This chapter includes the following topics:

- [About the Cluster Server agent for Tibco EMS Server](#)
- [Supported software](#)
- [Features of the agent](#)
- [How the agent makes Tibco EMS Server highly available](#)
- [How the agent supports intelligent resource monitoring](#)
- [Tibco EMS Server agent functions](#)

About the Cluster Server agent for Tibco EMS Server

Cluster Server (VCS) agents monitor specific resources within an enterprise application. They determine the status of resources and start or stop them according to external events.

The Cluster Server agent for Tibco EMS Server provides high availability for EMS server in a clustered environment. The agent brings specific instances of the EMS Server online, monitors the instance, and brings it offline. The agent monitors the processes of the EMS Server instance and shuts down the EMS Server in case of a failure.

See the Agent Pack Release Notes for the latest updates or software issues for this agent.

Supported software

For information on the software versions that the Cluster Server agent for Tibco EMS Server supports, see the Symantec Operations Readiness Tools (SORT) site: <https://sort.symantec.com/agents>.

Features of the agent

The following are the features of the Cluster Server agent for Tibco EMS Server:

- Support for validation of attributes that are based on the agent functions
The agent can validate attributes in each agent function before the actual data processing starts.
- Support for First Failure Data Capture (FFDC)
In case of a fault, the agent generates a huge volume of the debug logs that enable troubleshooting of the fault.
- Support for Fast First Level Monitor (FFLM)
The agent maintains PID files based on search patterns to expedite the monitoring process.
- Support for external user-supplied monitor utilities
The agent enables user-specified monitor utilities to be plugged in, in addition to the built-in monitoring logic. This enables administrators to completely customize the monitoring of the application.
- Support for intelligent resource monitoring and poll-based monitoring
The agent supports the Cluster Server Intelligent Monitoring Framework (IMF) feature. IMF allows the agent to register the resources to be monitored with the IMF notification module so as to receive immediate notification of resource state changes without having to periodically poll the resources. See *“Enabling the agent for Tibco EMS Server to support IMF”* on page 37.
- Delayed agent function
The agent manages the first monitor after online for slow initializing applications.

How the agent makes Tibco EMS Server highly available

The Cluster Server agent for Tibco EMS Server continuously monitors the EMS Server processes to verify that they function properly.

The agent mainly provides the following levels of application monitoring:

- **Primary or Basic monitoring**
 This mode has Process check monitoring option. With the default Process check option, the agent verifies that the Tibco EMS Server process is present in the process table. Process check cannot detect whether process is in hung or stopped state.
- **Optional Secondary or Detail monitoring**
 In this mode, the agent runs a tibemsadmin utility to verify the status of Tibco EMS Server. The agent reports the application as online if the tibemsadmin utility agent is able to connect to the Tibco EMS server, otherwise the monitoring routine reports the application as offline.
- **Custom Monitoring**
 In this mode, the agent can perform a customized check using a user-supplied monitoring utility. The agent detects application failure if the monitoring routine reports an improper function of the Tibco EMS server processes. When this application failure occurs, the Tibco EMS Server service group could be failed over to another node in the cluster.
 Thus, the agent ensures high availability for Tibco EMS Server.

How the agent supports intelligent resource monitoring

With Intelligent Monitoring Framework (IMF), VCS supports intelligent resource monitoring in addition to the poll-based monitoring. Poll-based monitoring polls the resources periodically whereas intelligent monitoring performs asynchronous monitoring.

When an IMF-enabled agent starts up, the agent initializes the Asynchronous Monitoring Framework (AMF) kernel driver. After the resource is in a steady state, the agent registers with the AMF kernel driver, the details of the resource that are required to monitor the resource. For example, the agent for Tibco EMS Server registers the PIDs of the Tibco EMS Server processes with the AMF kernel driver. The agent's `imf_getnotification` function waits for any resource state changes. When the AMF kernel driver module notifies the `imf_getnotification` function about a resource state change, the agent framework runs the monitor agent function to ascertain the state of that resource. The agent notifies the state change to VCS, which then takes appropriate action.

Refer to the *Cluster Server Administrator's Guide* for more information.

Tibco EMS Server agent functions

The agent consists of resource type declarations and agent executables. The agent executables implement online, offline, monitor, and clean operations.

Online

The online function performs the following tasks:

- Verifies whether the required attributes are set correctly.
- Performs the preliminary check to ensure that the Tibco EMS server is not online on the specified node in the cluster.
- Attempts to start the Tibco EMS server instance with the following command:
EMSHomeDir/tibemsd -config ConfigFile StartOptions &
The command is always executed in the context of the User.
- Uses the `tibemsd` command available at the `EMSHomeDir` attribute value to start the Tibco EMS server.
The startup parameters to `tibemsd` command are passed using the `StartOptions` attribute value.
- Sources a file that the `EnvFile` attribute specifies. This environment file ensures that the required shell environment variables are properly set before executing the start script.
- Ensures that the Tibco EMS server instance is up and running successfully.
The operation uses the wait period that the `OnlineTimeout` attribute specifies, to enable the Tibco EMS server instance to initialize fully before allowing the monitor function to probe the resource.

Offline

The offline operation performs the following tasks:

- Verifies that the Tibco EMS server instance is not already offline.
- Attempts to stop the Tibco EMS server instance with the following command.
*EMSHomeDir/tibemsadmin -server TibEmsServerUrl -user TibUser
TibemsadminOptions << EOF
TibPassword
shutdown
yes
exit
EOF*

After connecting to the EMS server using the `tibemsadmin` command, the agent issues shutdown command.

- Sources a file that the `EnvFile` attribute specifies. This environment file ensures that the required shell environment variables are properly set before executing the stop script.

Note: The `TibEmsServerUrl` attribute specifies the server URL, when connecting to Tibco EMS server. The server uses the `TibUser` attribute and the `TibPassword` attribute values for authentication while connecting to the EMS server.

- Uses the `TibemsadminOptions` attribute to pass the optional parameters to the `tibemsadmin` command.
- Ensures that the TibcoEMS server is offline. The operation uses a wait period that the `OfflineTimeout` attribute specifies, to allow the Tibco EMS server instance to complete the offline sequence before allowing further probing of the resource.

Monitor

The monitor function monitors the states of the EMS Server instance running on all nodes within the cluster.

The monitor operation performs following tasks:

- Conducts a first level check to determine that the EMS Server processes that the user specified in the `TibUser` attribute owns, are running on the system in the cluster. If the first level check does not find these processes running on the node, the check exits immediately, and reports the instance as OFFLINE.
The agent for Tibco EMS Server also supports Intelligent Monitoring Framework (IMF) in the first-level check. IMF enables intelligent resource monitoring. The agent for Tibco EMS Server is IMF-aware and uses the asynchronous monitoring framework (AMF) kernel driver for resource state change notifications. See [“How the agent supports intelligent resource monitoring”](#) on page 38. You can use the `MonitorFreq` key of the IMF attribute to specify the frequency at which the agent invokes the monitor function. See [“MonitorFreq”](#) on page 40.
- Uses the `ConfigFile` attribute value to uniquely identify the Tibco EMS server instance, when multiple Tibco EMS server instances are running on the same node.
- If the `SecondLevelMonitor` attribute is set to greater than 0, the monitor function performs a second-level check to determine the status of the EMS Server instance. The second level check tries to connect to Tibco EMS server instance

using tibemsadmin command to ensure that the processes are truly available for Tibco EMS server instance.

- Depending upon the MonitorProgram attribute, the monitor function can perform a customized check using a user-supplied monitoring utility.

Clean

In case of a failure or after an unsuccessful attempt to online or offline EMS Server, the clean function removes any EMS Server processes remaining in the system.

The clean operation performs following tasks:

- Attempts to gracefully shut down the EMS Server instance.
- If a graceful shutdown fails, the clean function looks for all the processes running for the EMS Server instance, and ends the processes using the kill command.

Note: For information about the additional functions of the agent for Tibco EMS Server when IMF is enabled: See [“Agent functions for the IMF functionality”](#) on page 39.

Installing and configuring Tibco EMS Server for high availability

This chapter includes the following topics:

- [About Tibco EMS](#)
- [Uniquely identifying Tibco EMS Server server instances](#)
- [Configuring the Tibco EMS Server for high availability](#)

About Tibco EMS

TIBCO Enterprise Message Service software is a messaging software. It provides Java Message Service (JMS) compliant communications across platforms and application technologies. It provides distributed and reliable architecture, with support for load-balancing, routing, and fault tolerant configurations that together remove single points of failure. It supports request and reply and publish and subscribe interactions, synchronous and asynchronous messaging, multicast deployments and different levels of reliable messaging. These capabilities enable developers and administrators to support different types of service protocols on the same platform.

It allows different resources from different vendors to participate in a single transaction. It provides multi-protocol support. It supports many open standards. It offers native support for development technologies and platforms. It provides full SSL support for client-to-server and server-to-server connectivity and plug-in security capability for custom-built authentication (JAAS) and authorization. Its built-in monitoring and management capabilities provide detailed administrative functions

and statistics and support automation through an administrative API or command-line shell.

Uniquely identifying Tibco EMS Server server instances

For multiple TibcoEMS server instance running concurrently on a single node, the Cluster Server agent must be able to uniquely identify each of the TibcoEMS instance on that system. Each TibcoEMS server has a unique configuration file. The agent uses the `ConfigFile` attribute value to identify the TibcoEMS server instance uniquely.

Differentiating TibcoEMS server instances is important to identify each TibcoEMS server uniquely. When the Cluster Server agent kills the processes of a non-responsive or failed TibcoEMS instance in the absence of unique `ConfigFile` for each TibcoEMS Server instance, the agent may kill processes for more than one TibcoEMS server instance during a clean operation.

Configuring the Tibco EMS Server for high availability

This section provides the information about the tasks you must perform to configure Tibco EMS Server for high availability.

Synchronizing accounts and services

Ensure that you synchronize accounts and services in the following ways:

- Synchronize the TibcoEMS installation user accounts user name, UNIX uid, group name, and UNIX gid across all nodes in the cluster.
- The `/etc/services` entries should be consistent on all cluster nodes.

Removing physical host dependencies

Perform the following tasks to remove the physical host dependencies:

- Update the `listen` tag in the main Tibco configuration file specified as part of the `ConfigFile` attribute. The form is for `listen` tag is `tcp://hostname:port`.
- The `listen` tag value should be specified as part of the `TibEmsServerUrl` attribute.

Installing, upgrading, and removing the agent for Tibco EMS Server

This chapter includes the following topics:

- [Before you install the Cluster Server agent for Tibco EMS Server](#)
- [About the ACC library](#)
- [Installing the ACC library](#)
- [Installing the agent in a VCS environment](#)
- [Uninstalling the agent in a VCS environment](#)
- [Removing the ACC library](#)

Before you install the Cluster Server agent for Tibco EMS Server

You must install the Cluster Server agent for Tibco EMS Server on all the systems that will host Tibco EMS Server service groups.

Before you install the agent for Tibco EMS Server, ensure that the following prerequisites are met.

- Install and configure Cluster Server.
For more information on installing and configuring Cluster Server, refer to the Cluster Server installation and configuration guides.
- Install the latest version of ACC Library.

To install or update the ACC Library package, locate the library and related documentation in the Agent Pack tarball,
See [“Installing the ACC library”](#) on page 19.

Prerequisites for enabling i18n support

Perform the following steps to enable i18n support to the agent:

- Install ACCLib version 5.1.2.0 or later.
See [“Installing the ACC library”](#) on page 19.
- For VCS 5.0 and earlier releases, copy the latest `ag_i18n_inc.pm` module from the following location on the agent pack disc.

Note: Review the `readme.txt` for instructions to copy this module.

VCS 5.0	<code>cd1/platform/arch_dist/vcs/application/i18n_support/5.0</code>
VCS 4.1	<code>cd1/platform/arch_dist/vcs/application/i18n_support/4.1</code>
VCS 4.0	<code>cd1/platform/arch_dist/vcs/application/i18n_support/4.0</code>

where `arch_dist` takes the following values:

'sol_sparc' for Solaris SPARC

'generic' for Linux

Note: `arch_dist` is not applicable to AIX.

About the ACC library

The operations of a Cluster Server agent depend on a set of Perl modules known as the ACC library. The library must be installed on each system in the cluster that runs the agent. The ACC library contains common, reusable functions that perform tasks, such as process identification, logging, and system calls.

Instructions to install or remove the ACC library on a single system in the cluster are given in the following sections. The instructions assume that the ACCLib tar file has already been extracted.

Note: The LogDbg attribute should be used to enable debug logs for the ACCLib-based agents when the ACCLib version is 6.2.0.0 or later and VCS version is 6.2 or later.

Installing the ACC library

Install the ACC library on each system in the cluster that runs an agent that depends on the ACC library.

To install the ACC library

- 1 Log in as a superuser.
- 2 Download ACC Library.

You can download either the complete Agent Pack tar file or the individual ACCLib tar file from the Symantec Operations Readiness Tools (SORT) site (<https://sort.symantec.com/agents>).

- 3 If you downloaded the complete Agent Pack tar file, navigate to the directory containing the package for the platform running in your environment.

```
AIX          cd1/aix/vcs/application/acc_library/version_library/pkgcs
Linux        cd1/linux/generic/vcs/application/acc_library/version_library/rpms
Solaris      cd1/solaris/dist_arch/vcs/application/acc_library/version_library/pkgcs
              where dist_arch is sol_sparc.
```

- 4 If you downloaded the individual ACCLib tar file, navigate to the pkgcs directory (for AIX and Solaris), or rpms directory (for Linux).
- 5 Install the package. Enter **Yes**, if asked to confirm overwriting of files in the existing package.

```
AIX          # installp -ac -d VRTSaccclib.bff VRTSaccclib
Linux        # rpm -i \
              VRTSaccclib-VersionNumber-GA_GENERIC.noarch.rpm
Solaris      # pkgadd -d VRTSaccclib.pkg
```

Note: The LogDbg attribute should be used to enable debug logs for the ACCLib-based agents when the ACCLib version is 6.2.0.0 or later and VCS version is 6.2 or later.

Installing the ACC library IPS package on Oracle Solaris 11 systems

To install the ACC library IPS package on an Oracle Solaris 11 system

1 Copy the `VRTSaccplib.p5p` package from the `pkgs` directory to the system in the `/tmp/install` directory.

2 Disable the publishers that are not reachable as package install may fail, if any, of the already added repositories are unreachable.

```
# pkg set-publisher --disable <publisher name>
```

3 Add a file-based repository in the system.

```
# pkg set-publisher -g /tmp/install/VRTSaccplib.p5p Symantec
```

4 Install the package.

```
# pkg install --accept VRTSaccplib
```

5 Remove the publisher from the system.

```
# pkg unset-publisher Symantec
```

6 Enable the publishers that were disabled earlier.

```
# pkg set-publisher --enable <publisher name>
```

Installing the ACC library package on Solaris brand non-global zones

With Oracle Solaris 11, you must install the ACC library package inside non-global zones. The native non-global zones are called Solaris brand zones.

To install the ACC library package on Solaris brand non-global zones

1 Ensure that the SMF service

```
svc:/application/pkg/system-repository:default and  
svc:/application/pkg/zones-proxyd:default are online on the global  
zone.
```

```
# svcs svc:/application/pkg/system-repository:default
```

```
# svcs svc:/application/pkg/zones-proxyd:default
```

2 Log on to the non-global zone as a superuser.

3 Ensure that the SMF service

```
svc:/application/pkg/zones-proxy-client:default is online inside the  
non-global zone:
```

```
# svcs svc:/application/pkg/zones-proxy-client:default
```

4 Copy the `VRTSaccplib.p5p` package from the `pkgs` directory to the non-global zone (for example, at the `/tmp/install` directory).

- 5 Disable the publishers that are not reachable, as package install may fail if any of the already added repositories are unreachable.

```
# pkg set-publisher --disable <publisher name>
```

- 6 Add a file-based repository in the non-global zone.

```
# pkg set-publisher -g/tmp/install/VRTSacclib.p5p Symantec
```

- 7 Install the package.

```
# pkg install --accept VRTSacclib
```

- 8 Remove the publisher on the non-global zone.

```
# pkg unset-publisher Symantec
```

- 9 Clear the state of the SMF service, as setting the file-based repository causes the SMF service `svc:/application/pkg/system-repository:default` to go into the maintenance state.

```
# svcadm clear svc:/application/pkg/system-repository:default
```

- 10 Enable the publishers that were disabled earlier.

```
# pkg set-publisher --enable <publisher>
```

Note: Perform steps 2 through 10 on each non-global zone.

Installing the agent in a VCS environment

Install the agent for Tibco EMS Server on each node in the cluster.

To install the agent in a VCS environment

- 1 Download the agent from the Symantec Operations Readiness Tools (SORT) site: <https://sort.symantec.com/agents>.

You can download either the complete Agent Pack tar file or an individual agent tar file.

- 2 Uncompress the file to a temporary location, say /tmp.

- 3 If you downloaded the complete Agent Pack tar file, navigate to the directory containing the package for the platform running in your environment.

```
AIX      cd1/aix/vcs/application/tibco_agent/  
        vcs_version/version_agent/pkggs
```

```
Linux   cd1/linux/generic/vcs/application/tibco_agent/  
        vcs_version/version_agent/rpms
```

```
Solaris cd1/solaris/dist_arch/vcs/application/tibco_agent/  
        vcs_version/version_agent/pkggs
```

If you downloaded the individual agent tar file, navigate to the `pkggs` directory (for AIX and Solaris), or `rpms` directory (for Linux).

- 4 Log in as a superuser.
- 5 Install the package.

```
AIX      # installp -ac -d  
        VRTSvcs_tib.rte.bff VRTSvcs_tib.rte
```

```
Linux   # rpm -ihv \  
        VRTSvcs_tib-AgentVersion-GA_GENERIC.noarch.rpm
```

```
Solaris # pkgadd -d . VRTSvcs_tib
```

- 6 After installing the agent package, you must import the agent type configuration file. See [“Importing the agent types file in a VCS environment”](#) on page 27.

Installing the agent IPS package on Oracle Solaris 11 systems

To install the agent IPS package on an Oracle Solaris 11 system

- 1 Copy the `VRTSvcs_tib.p5p` package from the `pkggs` directory to the system in the `/tmp/install` directory.
- 2 Disable the publishers that are not reachable as package install may fail if any of the already added repositories are unreachable.

```
# pkg set-publisher --disable <publisher name>
```

where the publisher name is obtained using the `pkg publisher` command.

3 Add a file-based repository in the system.

```
# pkg set-publisher -g /tmp/install/VRTSvcstib.p5p Symantec
```

4 Install the package.

```
# pkg install --accept VRTSvcstib
```

5 Remove the publisher from the system.

```
# pkg unset-publisher Symantec
```

6 Enable the publishers that were disabled earlier.

```
# pkg set-publisher --enable <publisher name>
```

Installing agent packages on Solaris brand non-global zones

With Oracle Solaris 11, you must install the agent package inside non-global zones. The native non-global zones are called Solaris brand zones.

To install the agent package on Solaris brand non-global zones**1** Ensure that the SMF service

```
svc:/application/pkg/system-repository:default and  
svc:/application/pkg/zones-proxyd:default are online on the global  
zone.
```

```
# svcs svc:/application/pkg/system-repository:default
```

```
# svcs svc:/application/pkg/zones-proxyd:default
```

2 Log on to the non-global zone as a superuser.**3** Ensure that the SMF service

```
svc:/application/pkg/zones-proxy-client:default is online inside  
non-global zone:
```

```
# svcs svc:/application/pkg/zones-proxy-client:default
```

4 Copy the `VRTSvcstib.p5p` package from the `pkgs` directory to the non-global zone (for example, at the `/tmp/install` directory).**5** Disable the publishers that are not reachable, as package install may fail if any of the already added repositories are unreachable.

```
# pkg set-publisher --disable <publisher name>
```

6 Add a file-based repository in the non-global zone.

```
# pkg set-publisher -g/tmp/install/VRTSvcstib.p5p Symantec
```

7 Install the package.

```
# pkg install --accept VRTSvcstib
```

8 Remove the publisher on the non-global zone.

```
# pkg unset-publisher Symantec
```

9 Clear the state of the SMF service, as setting the file-based repository causes the SMF service `svc:/application/pkg/system-repository:default` to go into the maintenance state.

```
# svcadm clear svc:/application/pkg/system-repository:default
```

10 Enable the publishers that were disabled earlier.

```
# pkg set-publisher --enable <publisher>
```

Note: Perform steps [2](#) through [10](#) on each non-global zone.

Installing the agent in a Solaris 10 brand zone

To install the Tibco EMS Server agent in a Solaris 10 brand zone:

- Ensure that the ACC library package, `VRTSacclib`, is installed in the non-global zone.

To install `VRTSacclib` in the non-global zone, run the following command from the global zone:

```
# pkgadd -R /zones/zone1/root -d VRTSacclib.pkg
```

- To install the agent package in the non-global zone, run the following command from the global zone:

```
# pkgadd -R zone-root/root -d . VRTSvcstib
```

For example: `# pkgadd -R /zones/zone1/root -d . VRTSvcstib`

Note: You can ignore the following messages that might appear:

```
## Executing postinstall script.  
  
ln: cannot create /opt/VRTSagents/ha/bin/TibcoEMS/imf_getnotification:  
File exists  
  
ln: cannot create /opt/VRTSagents/ha/bin/TibcoEMS/imf_register: File  
exists  
  
or ## Executing postinstall script.  
  
ln: cannot create /opt/VRTSagents/ha/bin/TibcoEMS/imf_getnotification:  
No such file or directory  
  
ln: cannot create /opt/VRTSagents/ha/bin/TibcoEMS/imf_register: No  
such file or directory
```

Uninstalling the agent in a VCS environment

You must uninstall the agent for Tibco EMS Server from a cluster while the cluster is active.

To uninstall the agent in a VCS environment

- 1 Log in as a superuser.
- 2 Set the cluster configuration mode to read/write by running the following command from any node in the cluster:

```
# haconf -makerw
```

- 3 Remove all Tibco EMS Server resources from the cluster. Run the following command to verify that all resources have been removed:

```
# hares -list Type=TibcoEMS
```

- 4 Remove the agent type from the cluster configuration by running the following command from any node in the cluster:

```
# hatype -delete TibcoEMS
```

Removing the agent's type file from the cluster removes the include statement for the agent from the `main.cf` file, but the agent's type file is not removed from the cluster configuration directory. You can remove the agent's type file later from the cluster configuration directory.

- 5 Save these changes. Then set the cluster configuration mode to read-only by running the following command from any node in the cluster:

```
# haconf -dump -makero
```

- 6 Use the platform's native software management program to remove the agent for Tibco EMS Server from each node in the cluster.

Run the following command to uninstall the agent:

```
AIX # installp -u VRTSvcstib.rte
```

```
Linux # rpm -e VRTSvcstib
```

```
Solaris # pkgrm VRTSvcstib
```

Note: To uninstall the agent IPS package on a Solaris 11 system, run the following command:

```
# pkg uninstall VRTSvcstib
```

Removing the ACC library

Perform the following steps to remove the ACC library.

To remove the ACC library

- 1 Ensure that all agents that use ACC library are removed.
- 2 Run the following command to remove the ACC library package.

```
AIX # installp -u VRTSacclib
```

```
Linux # rpm -e VRTSacclib
```

```
Solaris # pkgrm VRTSacclib
```

Note: To uninstall the ACCLib IPS package on a Solaris 11 system, run the following command:

```
# pkg uninstall VRTSacclib
```

Configuring the agent for Tibco EMS Server

This chapter includes the following topics:

- [About configuring the Cluster Server agent for Tibco EMS Server](#)
- [Importing the agent types file in a VCS environment](#)
- [Tibco EMS Server agent attributes](#)

About configuring the Cluster Server agent for Tibco EMS Server

After installing the Cluster Server agent for Tibco EMS Server, you must import the agent type configuration file. After importing this file, review the attributes table that describes the resource type and its attributes, and then create and configure Tibco EMS Server resources.

To view the sample agent type definition and service groups configuration:

See [“About sample configurations for the agents for Tibco EMS Server”](#) on page 54.

Importing the agent types file in a VCS environment

To use the agent for Tibco EMS Server, you must import the agent types file into the cluster.

You can import the agent types file using Cluster Manager (Java Console) or using the command line interface.

Importing the agent types file using Cluster Manager (Java Console)

To import the agent types file using Cluster Manager (Java Console)

- 1 Start the Cluster Manager (Java Console) and connect to the cluster on which the agent is installed.
- 2 Click **File > Import Types**.
- 3 In the **Import Types** dialog box, select the following file:

VCS 4.x	<ul style="list-style-type: none"> ■ AIX ■ Linux ■ Solaris 	<pre>/etc/VRTSvcs/conf/sample_TibcoEMS/ TibcoEMSTypes.cf</pre>
VCS 5.x or later	<ul style="list-style-type: none"> ■ AIX ■ Linux 	<pre>/etc/VRTSagents/ha/conf/TibcoEMS/ TibcoEMSTypes.cf</pre>
VCS 5.0	Solaris SPARC	<pre>/etc/VRTSagents/ha/conf/TibcoEMS/ TibcoEMSTypes50.cf</pre>
VCS 5.1 or later	Solaris SPARC	<pre>/etc/VRTSagents/ha/conf/TibcoEMS/ TibcoEMSTypes51.cf</pre>

- 4 Click **Import**.
- 5 Save the VCS configuration.

The Tibco EMS agent type is now imported to the VCS engine.

You can now create Tibco EMS Server resources.

For additional information about using the VCS CLI, refer to the *Cluster Server Administrator's Guide*.

Importing the agent types file using the CLI

To import the agent types file using the command line interface (CLI):

- 1 If VCS is running, run the `/etc/VRTSagents/ha/conf/TibcoEMS/TibcoEMSTypes.cmd` file from the command line.
- 2 If VCS is not running, perform the following steps:
 1. Copy the agent types file from the `/etc/VRTSagents/ha/conf/<AgentTypes_file>` directory to the `/etc/VRTSvcs/conf/config` directory.

Where, <AgentTypes_file> is chosen according to the following table:

VCS 4.x	<ul style="list-style-type: none"> ■ AIX ■ Linux ■ Solaris 	<p>/etc/VRTSvcs/conf/sample_TibcoEMS/ TibcoEMSTypes.cf</p>
VCS 5.x or later	<ul style="list-style-type: none"> ■ AIX ■ Linux 	<p>/etc/VRTSagents/ha/conf/TibcoEMS/ TibcoEMSTypes.cf</p>
VCS 5.0	Solaris SPARC	<p>/etc/VRTSagents/ha/conf/TibcoEMS/ TibcoEMSTypes50.cf</p>
VCS 5.1 or later	Solaris SPARC	<p>/etc/VRTSagents/ha/conf/TibcoEMS/ TibcoEMSTypes51.cf</p>

2. Include the agent types file in the main.cf file.
3. Start HAD.

Tibco EMS Server agent attributes

Refer to the required attributes and optional attributes while configuring the agent for Tibco EMS Server.

[Table 4-1](#) lists the required attributes for the Tibco agent.

Table 4-1 Required attributes

Required attributes	Description
EMSHomeDir	<p>Specifies any one of the following:</p> <ul style="list-style-type: none"> ■ The full path of the directory where the tibemspd binary file is located. In this case, the agent uses the tibemspd binary by default. ■ The full path of the Tibco EMS binary — tibemspd or tibemspd64. <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example 1: /home/tibco/ems/bin</p> <p>Example 2: /home/tibco64/tibco/ems/8.0/bin/tibemspd64</p>

Table 4-1 Required attributes (*continued*)

Required attributes	Description
ConfigFile	<p>Specifies the full path and the file name of the main configuration file tibemsd.conf for the Tibco Enterprise Message Server.</p> <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example: /home/tibco/ems/bin/tibemsd.conf</p>
User	<p>UNIX user name that the VHA agent will use to execute the programs for managing a Tibco Enterprise Message Server.</p> <p>The user name must be synchronized across the systems in the cluster. In other words, the user name must resolve to the same UID and have the same default shell on each system in the cluster. VHA Agent entry points use the getpwnam (3c) function call to obtain UNIX user attributes. As a result, the user can be defined locally or can be defined in a common repository (that is, NIS, NIS+, or LDAP). In the latter case, the agent will fail if the access to this repository fails.</p> <p>The supported shell environments are: ksh, sh, and csh.</p> <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example: tibco</p>

Table 4-1 Required attributes (*continued*)

Required attributes	Description
ResLogLevel	<p>Specifies the logging detail performed by the agent for the resource.</p> <p>The valid values are as follows:</p> <ul style="list-style-type: none"> ■ ERROR: Only logs error messages. ■ WARN: Logs above plus warning messages. ■ INFO: Logs above plus informational messages. ■ TRACE: Logs above plus trace messages. TRACE is very verbose and should only be used during initial configuration or for troubleshooting and diagnostic operations. <p>Type and Dimension: string-scalar</p> <p>Default: INFO</p> <p>Example: TRACE</p> <p>Note: The use of the ResLogLevel attribute is deprecated from VCS version 6.2 onwards. You must use the LogDbg attribute instead of the ResLogLevel attribute to enable debug logs for the ACCLib-based agents, when the ACCLib version is 6.2.0.0 or later. The agent captures the first failure data of the unexpected events and automatically logs debug messages in their respective agent log files.</p>
TibEmsServerUrl	<p>Description: Tibco EMS server URL, default is local server. During Offline and second-level monitoring, this URL is used to specify the -server parameter for the tibemsadmin utility.</p> <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example: <code>tcp://virtualhost:7222</code></p>
TibUser	<p>Tibco user name to connect to server. During Offline and second-level monitoring, this TibUser is used to specify the -user parameter for tibemsadmin utility.</p> <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example: admin</p>

Table 4-1 Required attributes (*continued*)

Required attributes	Description
TibPassword	<p>Password of the Tibco operator who is connecting to EMS server. During Offline and second-level monitoring, this Password is used to specify the -password parameter for the tibemsadmin utility. The value of this attribute need to be encrypted using VCS provided \$VCSHOME/bin/vcscrypt utility</p> <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example: HTlvKTITNnINjNKnL</p>

Table 4-2 lists the optional attributes for the Tibco agent.

Table 4-2 Optional attributes

Optional attributes	Description
LogDbg	<p>For ACCLib-based agents, you must use the LogDbg resource type attribute to enable the debug logs when the ACCLib version is 6.2.0.0 or later and the VCS version is 6.2 or later.</p> <p>Set the LogDbg attribute to DBG_5 to enable debug logs for ACCLIB based agent. By default, setting the LogDbg attribute to DBG_5 enables debug logs for all TibcoEMS resources in the cluster. If debug logs must be enabled for a specific TibcoEMS resource, override the LogDbg attribute.</p> <p>Type and dimension: string-keylist</p> <p>Default: {} (none)</p> <p>For more information on how to use the LogDbg attribute, refer to the <i>Cluster Server Administrator's Guide</i>.</p>

Table 4-2 Optional attributes (*continued*)

Optional attributes	Description
SecondLevelMonitor	<p>Used to enable second-level monitoring. Second-level monitoring is a deeper, more thorough state check of the configured TibcoEMS instance. The numeric value specifies how often the monitoring routines are run. 0 means never run the second-level monitoring routines, 1 means run routines every monitor interval, 2 means run routines every second monitor interval. This interpretation may be extended to other values.</p> <p>Note: Exercise caution while setting SecondLevelMonitor to large numbers. For example, if the MonitorInterval is set to 60 seconds and the SecondLevelMonitor is set to 100, then the second level check is executed every 100 minutes, which may not be as often as intended. For maximum flexibility, no upper limit is defined for SecondLevelMonitor. You can run the second level check once a month, if required.</p> <p>Also, verify the second level monitoring utility before enabling second level monitor.</p> <p>Type and Dimension: integer-scalar</p> <p>Default: 0</p> <p>Example: 1</p>

Table 4-2 Optional attributes (*continued*)

Optional attributes	Description
LevelTwoMonitorFreq	<p>Specifies the frequency at which the agent for this resource type must perform second-level or detailed monitoring. You can also override the value of this attribute at the resource level. The value indicates the number of monitor cycles after which the agent will monitor the Tibco EMS Server in detail.</p> <p>For example, the value 5 indicates that the agent will monitor the Tibco EMS Server in detail after every five online monitor intervals.</p> <p>Note: This attribute is applicable to VCS version 5.1 SP1 or later with Tibco EMS Server agent version 5.1.2.0 or later. If the VCS version is earlier than VCS 5.1 SP1 and the Tibco EMS Server agent version is earlier than 5.1.2.0, the SecondLevelMonitor attribute should be used.</p> <p>If you upgraded the VCS version to VCS 5.1 SP1 or later and the Tibco EMS Server agent version to 5.1.2.0 (or later), and if you had enabled detail monitoring in the previous version, then do the following:</p> <ul style="list-style-type: none"> ■ Set the value of the LevelTwoMonitorFreq attribute to the same value as that of the SecondLevelMonitor attribute. <p>Type and dimension: integer-scalar</p> <p>Default: 0</p>

Table 4-2 Optional attributes (*continued*)

Optional attributes	Description
MonitorProgram	<p>Specifies the full path and file name of an external, user-supplied monitor program. If specified, the monitor entry point executes this file to perform an additional server state check. There are no restrictions for the actions the external monitor program performs to determine the state of a TibcoEMS instance server. The only constraint is that the external monitor program must return one of the following integer values:</p> <ul style="list-style-type: none"> ■ If the exit code is 0 the TibcoEMS server is online. ■ If the exit code is 110 the TibcoEMS server is online. ■ If the exit code is 100 the TibcoEMS server is offline. ■ If the exit code is 1 the TibcoEMS server is offline. ■ All other: TibcoEMS server is unknown. <p>Symantec recommends storing the external monitor utility on the shared disk directory to ensure the file is always available on the online system. Arguments are supported.</p> <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example: <code>/home/tibco/ems/myMonitor.sh</code></p>
StartOptions	<p>List of tibemsd startup parameters. During startup of Tibco Enterprise Message Server, these startup parameters will be passed to the tibemsd command. The command options to tibemsd are similar to the parameters you specify in tibemsd.conf, and the command options override any value specified in the parameters. By default, the agent specifies -config parameter, hence this parameter should not be specified as part of StartOptions again.</p> <p>Type and Dimension: association-scalar</p> <p>Default: No default value</p> <p>Example: <code>-ft_active tcp://tibhost:7245 -ssl_trace</code></p>

Table 4-2 Optional attributes (*continued*)

Optional attributes	Description
EnvFile	<p>Specifies the full path to the file that must be sourced with the UNIX shell. Source this file to set the environment before executing Tibco Enterprise Message Service command. Symantec recommends to store the file on a shared disk.</p> <p>The shell environments supported are: ksh, sh, and csh.</p> <p>Type and Dimension: string-scalar</p> <p>Default: No default value</p> <p>Example: /home/Tibco/ems/envfile</p>
TibemsadminOptions	<p>List of tibemsadmin command startup parameters. During offline and second-level monitoring, these startup parameters will be passed to the tibemsadmin utility. By default, the agent specifies the -server, -user, and -password parameters, hence these parameter should not be specified as part of TibemsadminOptions again.</p> <p>Type and Dimension: association-scalar</p> <p>Default: No default value</p> <p>Example: -ssl_trusted /home/tibco/ssl/certificate1 -ssl_identity /home/tibco/ssl/certificate2 -ssl_trace</p>

Note: For information about the additional attributes of the agent for Tibco EMS Server when IMF is enabled: See [“Attributes that enable IMF”](#) on page 39.

Enabling the agent for Tibco EMS Server to support IMF

This chapter includes the following topics:

- [About Intelligent Monitoring Framework](#)
- [How the agent supports intelligent resource monitoring](#)
- [Agent functions for the IMF functionality](#)
- [Attributes that enable IMF](#)
- [Before you enable the agent to support IMF](#)
- [Enabling the agent to support IMF](#)
- [Disabling intelligent resource monitoring](#)
- [Sample IMF configurations](#)

About Intelligent Monitoring Framework

With the IMF feature, VCS supports intelligent resource monitoring in addition to the poll-based monitoring. Poll-based monitoring polls the resources periodically whereas intelligent monitoring performs asynchronous monitoring. You can enable or disable the intelligent resource monitoring functionality of the Tibco EMS Server agent.

VCS process and mount-based agents use the AMF kernel driver that provides asynchronous event notifications to the agents that are enabled for IMF.

You can enable the Tibco EMS Server agent for IMF, provided the following software versions are installed:

- Cluster Server (VCS) 5.1 SP1 or later
- Cluster Server agent for Tibco EMS Server version 5.1.2.0 or later

Refer to the *Cluster Server Administrator's Guide* for more information about IMF notification module functions and administering the AMF kernel driver.

Benefits of IMF

IMF offers the following benefits:

- Performance
Enhances performance by reducing the monitoring of each resource at a default of 60 seconds for online resources, and 300 seconds for offline resources. IMF enables the agent to monitor a large number of resources with a minimal effect on performance.
- Faster detection
Asynchronous notifications would detect a change in the resource state as soon as it happens. Immediate notification enables the agent to take action at the time of the event.

How the agent supports intelligent resource monitoring

With Intelligent Monitoring Framework (IMF), VCS supports intelligent resource monitoring in addition to the poll-based monitoring. Poll-based monitoring polls the resources periodically whereas intelligent monitoring performs asynchronous monitoring.

When an IMF-enabled agent starts up, the agent initializes the Asynchronous Monitoring Framework (AMF) kernel driver. After the resource is in a steady state, the agent registers with the AMF kernel driver, the details of the resource that are required to monitor the resource. For example, the agent for Tibco EMS Server registers the PIDs of the Tibco EMS Server processes with the AMF kernel driver. The agent's `imf_getnotification` function waits for any resource state changes. When the AMF kernel driver module notifies the `imf_getnotification` function about a resource state change, the agent framework runs the monitor agent function to ascertain the state of that resource. The agent notifies the state change to VCS, which then takes appropriate action.

Refer to the *Cluster Server Administrator's Guide* for more information.

Agent functions for the IMF functionality

If the Tibco EMS Server is enabled for IMF support, the agent supports the following functions, in addition to the functions mentioned in [Tibco EMS Server agent functions](#).

imf_init

This function initializes the Tibco EMS Server agent to interface with the AMF kernel driver, which is the IMF notification module for the agent for Tibco EMS Server. This function runs when the agent starts up.

imf_getnotification

This function gets notifications about resource state changes. This function runs after the agent initializes with the AMF kernel module. This function continuously waits for notification and takes action on the resource upon notification.

imf_register

This function registers or unregisters resource entities with the AMF kernel module. This function runs for each resource after the resource goes into a steady state—online or offline.

Attributes that enable IMF

If the agent for Tibco EMS Server is enabled for IMF support, the agent uses the following type-level attributes in addition to the attributes described in [Tibco EMS Server agent attributes](#).

IMF

This resource type-level attribute determines whether the Tibco EMS Server agent must perform intelligent resource monitoring. You can also override the value of this attribute at the resource level.

This attribute includes the following keys:

Mode

Define this attribute to enable or disable intelligent resource monitoring. Valid values are as follows:

- 0—Does not perform intelligent resource monitoring

- 1—Performs intelligent resource monitoring for offline resources and performs poll-based monitoring for online resources
- 2—Performs intelligent resource monitoring for online resources and performs poll-based monitoring for offline resources
- 3—Performs intelligent resource monitoring for both online and for offline resources.

Note: The agent for Tibco EMS Server supports intelligent resource monitoring for online resources only. Hence, Mode should be set to either 0 or 2.

Type and dimension: integer-association

Default: 0 for VCS 5.1 SP1, 3 for VCS 6.0 and later.

MonitorFreq

This key value specifies the frequency at which the agent invokes the monitor agent function. The value of this key is an integer.

Default: 1

You can set this key to a non-zero value for cases where the agent requires to perform both poll-based and intelligent resource monitoring.

If the value is 0, the agent does not perform poll-based process check monitoring.

After the resource registers with the AMF kernel driver, the agent calls the monitor agent function as follows:

- After every (MonitorFreq x MonitorInterval) number of seconds for online resources
- After every (MonitorFreq x OfflineMonitorInterval) number of seconds for offline resources

RegisterRetryLimit

If you enable intelligent resource monitoring, the agent invokes the `imf_register` agent function to register the resource with the AMF kernel driver.

The value of the RegisterRetryLimit key determines the number of times the agent must retry registration for a resource. If the agent cannot register the resource within the limit that is specified, then intelligent monitoring is disabled until the resource state changes or the value of the Mode key changes.

Default: 3.

IMFRegList

An ordered list of attributes whose values are registered with the IMF notification module.

Type and dimension: string-vector

Default: No default value

Note: The attribute values can be overridden at the resource level.

Before you enable the agent to support IMF

Before you enable the Tibco EMS Server agent to support IMF, ensure that the AMF kernel module is loaded and AMF is configured. For details, refer to the 'Administering the AMF kernel driver' section of the *Cluster Server Administrator's Guide*. For details about the commands you can configure AMF using the `amfconfig -h` command.

Enabling the agent to support IMF

In order to enable the Tibco EMS Server agent to support IMF, you must make the following configuration changes to the attributes of the agent:

- AgentFile: Set the AgentFile attribute to **Script51Agent**
- IMF Mode: Set the IMF Mode attribute to **2**
- IMFRegList: Update the IMFRegList attribute

The following sections provide more information about the commands you can use to make these configuration changes, depending on whether VCS is in a running state or not.

Note: If you have upgraded VCS from an earlier version to version 5.1 SP1 or later, and you already have Tibco EMS Server agent 5.1.2.0 installed, ensure that you run the following commands to create appropriate symbolic links:

```
# cd /opt/VRTSagents/ha/bin/TibcoEMS
# ln -s /opt/VRTSamf/imf/imf_getnotification imf_getnotification
# ln -s /opt/VRTSagents/ha/bin/TibcoEMS/monitor imf_register
```

If VCS is in a running state

To enable the Tibco EMS Server resource for IMF when VCS is in a running state:

- 1 Make the VCS configuration writable.

```
# haconf -makerw
```

- 2 Run the following command to update the AgentFile attribute.

```
# hatype -modify TibcoEMS AgentFile\  
/opt/VRTSvcs/bin/Script51Agent
```

- 3 For VCS version 6.0 or later, run the following commands to add the IMF attributes:

```
# haattr -add -static TibcoEMS IMF -integer -assoc Mode 0 \  
MonitorFreq 1 RegisterRetryLimit 3
```

```
# haattr -add -static TibcoEMS IMFRegList -string -vector
```

Note: Run these commands only once after you first enable IMF support for the agent.

- 4 Run the following command to update the IMF attribute.

```
# hatype -modify TibcoEMS IMF Mode num MonitorFreq num  
RegisterRetryLimit num
```

For example, to enable intelligent monitoring of online resources, with the MonitorFreq key set to 5, and the RegisterRetryLimit key is set to 3, run the following command:

```
# hatype -modify TibcoEMS IMF Mode 2 MonitorFreq 5 \  
RegisterRetryLimit 3
```

Note: The valid values for the Mode key of the IMF attribute are 0 (disabled) and 2 (online monitoring).

- 5 Run the following command to update the IMFRegList attribute:

```
# hatype -modify TibcoEMS IMFRegList EMSHomeDir ConfigFile User
```

- 6 Save the VCS configuration.

```
# haconf -dump -makero
```

- 7 If the Tibco EMS Server agent is running, restart the agent.

For information on the commands you can use to restart the agent, see [Restarting the agent](#).

Restarting the agent

To restart the agent:

- 1 Run the following command to stop the agent forcefully:

```
# haagent -stop TibcoEMS -force -sys <system>
```

Note: Stopping the agent forcefully eliminates the need to take the resource offline.

- 2 Run the following command to start the agent:

```
# haagent -start TibcoEMS -sys <system>.
```

If VCS is not in a running state

To change the TibcoEMS type definition file when VCS is not in a running state:

- 1 Update the AgentFile attribute.

```
static str AgentFile = "/opt/VRTSvcs/bin/Script51Agent"
```

- 2 Update the IMF attribute.

The valid values for the Mode key of the IMF attribute are 0 (disabled) and 2 (online monitoring).

```
static int IMF{} = { Mode=num, MonitorFreq=num,  
RegisterRetryLimit=num }
```

For example, to update the IMF attribute such that the Mode key is set to 2, the MonitorFreq key is set to 5, and the RegisterRetryLimit key is set to 3:

```
static int IMF{} = { Mode=2, MonitorFreq=5, RegisterRetryLimit=3  
}
```

- 3 Update the IMFRegList attribute.

```
static str IMFRegList[] = { EMSHomeDir, ConfigFile, User }
```

Disabling intelligent resource monitoring

To disable intelligent resource monitoring

- 1 Make the VCS configuration writable.
- 2 To disable intelligent resource monitoring for all the resources of a certain type, run the following command:

```
# haconf -makerw
```

```
# hatype -modify TibcoEMS IMF -update Mode 0
```

- 3 To disable intelligent resource monitoring for a specific resource, run the following command:

```
# hares -override resource_name IMF
```

```
# hares -modify resource_name IMF -update Mode 0
```

- 4 Save the VCS configuration.

```
# haconf -dump -makero
```

Sample IMF configurations

An example of a type definition file for a Tibco EMS Server agent that is IMF-enabled is as follows.

In this example, the IMF-related attributes are set to the following values:

```
AgentFile                /opt/VRTSvcs/bin/Script51Agent
IMF{}                    { Mode=2, MonitorFreq=5, RegisterRetryLimit=3 }
IMFRegList[]             { EMSHomeDir, ConfigFile, User }
LevelTwoMonitorFreq      25
```

```
type TibcoEMS (
    static int IMF{} = { Mode=2, MonitorFreq=3, RegisterRetryLimit=3 }
    static str IMFRegList[] = { EMSHomeDir, ConfigFile, User }
    static str AgentDirectory = "/opt/VRTSagents/ha/bin/TibcoEMS"
    static str AgentFile = "/opt/VRTSvcs/bin/Script51Agent"
    static int LevelTwoMonitorFreq = 2
    static keylist LogDbg = { DBG_1, DBG_2, DBG_3, DBG_4, DBG_5 }
    static str ArgList[] = { ResLogLevel, State, IState, User, EnvFile,
    EMSHomeDir, ConfigFile, TibEmsServerUrl, SecondLevelMonitor, TibUser,
```

```
TibPassword, MonitorProgram, StartOptions, TibemsadminOptions }  
static boolean AEPTIMEOUT = 1  
str ResLogLevel = INFO  
str User  
str EnvFile  
str EMSHomeDir  
str ConfigFile  
str TibEmsServerUrl  
int SecondLevelMonitor  
str TibUser  
str TibPassword  
str MonitorProgram  
str StartOptions  
str TibemsadminOptions  
)
```

A sample resource configuration from the `/etc/VRTSvcs/conf/config/main.cf` file is as follows:

```
TibcoEMS tibco_res (  
    Critical = 0  
    ResLogLevel = TRACE  
    User = tibco  
    EMSHomeDir = "/home/tibco/tibco/ems/6.3/bin"  
    ConfigFile = "/home/tibco/TIBCO_HOME/tibco/  
    cfgmgmt/ems/data/tibemsd.conf"  
    TibEmsServerUrl = "tcp://tuxedovml:7222"  
    TibUser = admin  
    TibPassword = gumSjuJ  
)
```

Configuring the service groups for Tibco EMS Server using the CLI

This chapter includes the following topics:

- [About configuring service groups for Tibco EMS Server](#)
- [Before configuring the service groups for Tibco EMS Server](#)
- [Configuring service groups for Tibco EMS Server](#)
- [Creating service groups for Tibco EMS Server under Solaris non-global zones](#)

About configuring service groups for Tibco EMS Server

Configuring the Tibco EMS Server service group involves creating the Tibco EMS service group, its resources, and defining attribute values for the configured resources. You must have administrator privileges to create and configure a service group.

You can configure the service groups using the Cluster Manager (Java console).

Before configuring the service groups for Tibco EMS Server

Before you configure the Tibco EMS Server service group, you must:

- Verify that Cluster Server is installed and configured on all nodes in the cluster where you will configure the service group.
For more information on installing and configuring Cluster Server, refer to the Cluster Server installation and configuration guides.
- Verify that Tibco EMS server is installed and configured on all the systems in the cluster on the same path that will host a Tibco EMS service group.
- Verify that the Cluster Server agent for Tibco EMS Server is installed on all nodes in the cluster.
See [“Installing the agent in a VCS environment”](#) on page 21.
- Verify that the type definition for the Cluster Server agent for Tibco EMS Server is imported into the VCS engine.

Configuring service groups for Tibco EMS Server

A cluster handles Tibco EMS server failover scenarios. It provides application failover by encapsulating the application resources required into a service group. A service group is a logical setup containing all the resources that support Tibco EMS Server instance in a clustered environment. A service group can contain a set of dependent resources such as disk groups, file systems, IP addresses, NIC cards, and dependent application processes.

A cluster can start, stop, monitor, and switch service groups within the cluster, depending upon server or resource faults. An administrator can proactively move a service group between cluster nodes to perform preventative maintenance or to apply patches. The service group includes logical information about the dependencies between the application components.

In a clustered environment, you can configure a Tibco EMS server in the following configuration:

- [Failover configuration for Tibco EMS Server](#)
- [Cluster File System \(CFS\) based fault tolerant configuration for Tibco EMS Server](#)

Failover configuration for Tibco EMS Server

In a failover configuration, when the Tibco EMS server faults on one node, the storage infrastructure is moved to the failover node and the EMS server is started on the failover node. Tibco EMS server is fully operational once the Tibco EMS resource is online on failover node. The storage resources, the network resources, and the TibcoEMS resources are part of the same service group which fails over across VCS nodes.

Cluster File System (CFS) based fault tolerant configuration for Tibco EMS Server

In a Cluster File System based configuration, you can arrange TIBCO Enterprise Message Service servers for fault-tolerant operation by configuring a pair of servers, one primary and one backup. The primary server accepts client connections and interacts with clients to deliver messages. If the primary server fails, the backup server resumes operation in its place. However, it does not support more than two servers.

Separate service groups are used to configure the Tibco EMS servers. These application service groups depend on underlying storage, which is CFS based and it is shared across VCS nodes. Storage resources are configured as part of Tibco infrastructure group. When the primary Tibco EMS server faults, the backup server readily resumes operation in its place. Since the storage infrastructure is already available to backup server, the failover time is reduced in this configuration.

The various `ft_*` parameters in the `tibemsd.conf` file dictate how fault tolerance is set up. To enable fault tolerance, you must set the `server`, `store`, and `ft_activate` parameters. The `server` parameter is set to an arbitrary name (TIBCO Enterprise Message Service server name). It should be identical in the configuration file for both the primary server and the standby server. The shared data store is designated by the `store` argument and it should point to a shared file system or a clustered file system. The `ft_active` parameter should point to the other server in a primary or standby pair, such that on the primary it should point to the standby and on the standby it should point to the primary. During the startup, the servers communicate with each other and decide the current primary server and the current standby server. By default, the first node that starts is the primary server.

The main configuration files excerpts are as follows:

- Primary `tibemsd_tibems01.conf`

```
server = EMS01
store = /home/tibco/ems01/datastore
listen = tcp://tibhostpri:7222
ft_active = tcp://tibhostsec:7225
```

- Secondary `tibemsd_tibems02.conf`

```
server = EMS01
store = /home/tibco/ems01/datastore
listen = tcp://tibhostsec:7225
ft_active = tcp://tibhostpri:7222
```

For details about other features, refer to the *TIBCO Enterprise Message Service User's Guide*.

For details about CFS based fault tolerant configuration for Tibco EMS server, refer to the application note at <http://www.symantec.com/docs/TECH61384>.

See “[Sample service group configuration for Tibco EMS server in Failover setup](#)” on page 57.

See “[Sample service group configuration for Tibco EMS server in CFS based fault tolerant setup](#)” on page 63.

Creating service groups for Tibco EMS Server under Solaris non-global zones

To configure zones on each cluster node:

- 1 Set up the non-global zone configuration.

```
hazonesetup servicegroup_name zoneres_name zone_name password
systems
```

For example:

```
hazonesetup -g servicegroup_name -r zoneres_name -z zone_name
-p password -s systems
```

- 2 Verify the non-global zone configuration.

```
hazoneverify servicegroup_name
```

- 3 Whenever you make a change that affects the zone configuration, run the `hazonesetup` command to reconfigure the zones in VCS.

- 4 Make sure that the zone configuration files are consistent on all nodes at all times. The file is located at `/etc/zones/zone_name.xml`.

- 5 Make sure that the application is identical on all nodes. If you update the application configuration on one node, apply the same updates to all nodes.

- 6 Configure the service groups for Tibco EMS Server.

Troubleshooting the agent for Tibco EMS Server

This chapter includes the following topics:

- [Using the correct software and operating system versions](#)
- [Meeting prerequisites](#)
- [Configuring Tibco EMS Server resources](#)
- [Starting the Tibco EMS Server instance outside a cluster](#)
- [Reviewing error log files](#)

Using the correct software and operating system versions

Ensure that you use correct software and operating system versions.

For information on the software versions that the agent for Tibco EMS Server supports, see the Symantec Operations Readiness Tools (SORT) site: <https://sort.symantec.com/agents>.

Meeting prerequisites

Before installing the agent for Tibco EMS Server, ensure that the following prerequisites are met.

For example, you must install the ACC library on VCS before installing the agent for Tibco EMS Server.

See [“Before you install the Cluster Server agent for Tibco EMS Server”](#) on page 17.

Configuring Tibco EMS Server resources

Before using Tibco EMS Server resources, ensure that you configure the resources properly. For a list of attributes used to configure all Tibco EMS Server resources, refer to the agent attributes.

Starting the Tibco EMS Server instance outside a cluster

If you face problems while working with a resource, you must disable the resource within the cluster framework. A disabled resource is not under the control of the cluster framework, and so you can test the Tibco EMS Server instance independent of the cluster framework. Refer to the cluster documentation for information about disabling a resource.

You can then restart the Tibco EMS Server instance outside the cluster framework.

Note: Use the same parameters that the resource attributes define within the cluster framework while restarting the resource outside the cluster framework.

A sample procedure to start a EMS server instance outside the cluster framework, is described as follows.

To restart the Tibco EMS server outside the framework

- 1 Log in to the Tibco EMS node as an User.

```
# su User
```

- 2 Source the environment file.

```
# . EnvFile
```

- 3 Start the Tibco EMS server.

```
# cd EMSHomeDir
```

```
# EMSHomeDir/tibemsd -config config-file StartOptions
```

If the Tibco EMS server works properly outside the cluster framework, you can then attempt to implement the Tibco EMS server within the cluster framework.

Reviewing error log files

If you face problems while using Tibco EMS Server or the agent for Tibco EMS Server, use the log files described in this section to investigate the problems.

Reviewing cluster log files

You can also access the Tibco EMS Server agent log file for more detailed information. The agent log file is located at `/var/VRTSvcs/log/TibcoEMS_A.log`

Using trace level logging

The `ResLogLevel` attribute controls the level of logging that is written in a cluster log file for each Tibco EMS Server resource. You can set this attribute to `TRACE`, which enables very detailed and verbose logging.

If you set `ResLogLevel` to `TRACE`, a very high volume of messages are produced. Symantec recommends that you localize the `ResLogLevel` attribute for a particular resource.

The `LogDbg` attribute should be used to enable the debug logs for the ACCLib-based agents when the ACCLIB version is 6.2.0.0 or later and the VCS version is 6.2 or later.

To localize `ResLogLevel` attribute for a resource

1 Identify the resource for which you want to enable detailed logging.

2 Localize the `ResLogLevel` attribute for the identified resource:

```
# hares -local Resource_Name ResLogLevel
```

3 Set the `ResLogLevel` attribute to `TRACE` for the identified resource:

```
# hares -modify Resource_Name ResLogLevel TRACE -sys SysA
```

4 Note the time before you begin to operate the identified resource.

5 Test the identified resource. The function reproduces the problem that you are attempting to diagnose.

6 Note the time when the problem is reproduced.

7 Set the `ResLogLevel` attribute back to `INFO` for the identified resource:

```
# hares -modify Resource_Name ResLogLevel INFO -sys SysA
```

8 Save the configuration changes.

```
# haconf -dump
```

9 Review the contents of the log file.

Use the time noted in Step 4 and Step 6 to diagnose the problem.

You can also contact Symantec support for more help.

To enable debug logs for all resources of type TibcoEMS

- ◆ Enable the debug log.

```
# hatype -modify TibcoEMS LogDbg DBG_5
```

To override the LogDbg attribute at resource level

- ◆ Override the LogDbg attribute at the resource level and enable the debug logs for the specific resource.

```
# hares -override TibcoEMS LogDbg
# hares -modify TibcoEMS LogDbg DBG_5
```

Using Tibco EMS Server log files

By default the log file is disabled in Tibco EMS server. To enable logging, update the Tibco EMS server configuration file.

For more details about Tibco log file and tracing parameters, refer to the Tibco documentation.

Sample Configurations

This appendix includes the following topics:

- [About sample configurations for the agents for Tibco EMS Server](#)
- [Sample agent type definition](#)
- [Sample resource configuration](#)
- [Sample service group configuration for Tibco EMS server in Failover setup](#)
- [Sample service group configuration for Tibco EMS server in Failover setup with Solaris Zones](#)
- [Sample resource dependency in a Failover configuration for Tibco EMS server](#)
- [Sample resource dependency in a Failover configuration for Tibco EMS server with Solaris Zones](#)
- [Sample service group configuration for Tibco EMS server in CFS based fault tolerant setup](#)
- [Sample resource dependency in a CFS based fault tolerant configuration for Tibco EMS server](#)
- [Service group dependency in a CFS based fault tolerant configuration for Tibco EMS Server](#)

About sample configurations for the agents for Tibco EMS Server

The sample configuration graphically depicts the resource types, resources, and resource dependencies within the service group. Review these dependencies carefully before configuring the agents for Tibco EMS Server. For more information

about these resource types, refer to the *Cluster Server Bundled Agents Reference Guide*.

Sample agent type definition

This section lists the sample agent type definition files for EMS Server agent on different versions of VCS.

For VCS 4.x

```
type TibcoEMS (
    static str ContainerType = Zone
    static str ArgList[] = { ResLogLevel, State, IState, User, EnvFile,
    EMHomeDir, ConfigFile, TibEmsServerUrl, SecondLevelMonitor, TibUser,
    TibPassword, MonitorProgram, StartOptions, TibemsadminOptions }
    str ResLogLevel = INFO
    str User
    str EnvFile
    str EMHomeDir
    str ConfigFile
    str TibEmsServerUrl
    int SecondLevelMonitor = 0
    str TibUser
    str TibPassword
    str MonitorProgram
    str StartOptions
    str TibemsadminOptions
    str ContainerName
)
```

For VCS 5.0

```
type TibcoEMS (
    static boolean AEPTIMEOUT = 1
    static str ContainerType = Zone
    static str AgentFile = "/opt/VRTSvcs/bin/Script50Agent"
    static str AgentDirectory = "/opt/VRTSagents/ha/bin/TibcoEMS"
    static str ArgList[] = { ResLogLevel, State, IState, User, EnvFile,
    EMHomeDir, ConfigFile, TibEmsServerUrl, SecondLevelMonitor, TibUser,
    TibPassword, MonitorProgram, StartOptions, TibemsadminOptions }
    str ResLogLevel = INFO
    str User
    str EnvFile
    str EMHomeDir
```

```
str ConfigFile
str TibEmsServerUrl
int SecondLevelMonitor = 0
str TibUser
str TibPassword
str MonitorProgram
str StartOptions
str TibemsadminOptions
str ContainerName
)
```

For VCS 5.1

```
type TibcoEMS (
  static int ContainerOpts {} = { RunInContainer = 1, PassCInfo = 0 }
  static boolean AEPTIMEOUT = 1
  static str AgentFile = "/opt/VRTSvcs/bin/Script50Agent"
  static str AgentDirectory = "/opt/VRTSagents/ha/bin/TibcoEMS"
  static str ArgList[] = { ResLogLevel, State, IState, User, EnvFile,
    EMHomeDir, ConfigFile, TibEmsServerUrl, SecondLevelMonitor, TibUser,
    TibPassword, MonitorProgram, StartOptions, TibemsadminOptions }
  str ResLogLevel = INFO
  str User
  str EnvFile
  str EMHomeDir
  str ConfigFile
  str TibEmsServerUrl
  int SecondLevelMonitor = 0
  str TibUser
  str TibPassword
  str MonitorProgram
  str StartOptions
  str TibemsadminOptions
)
```

Sample resource configuration

This section lists the sample resource configuration when the ACCLib installed is 6.2.0.0 and the agent installed is 6.2.

```
tibco_grp (
  SystemList = { system01 = 0, system02 = 1 }
)
```

Sample service group configuration for Tibco EMS server in Failover setup

```

TibcoEMS tibco_res (
    User = tibco
    EMSHomeDir = "/home/tibco/ems/8.1/bin"
    ConfigFile = "/home/tibco/TIB/tibco/cfgmgmt/ems/data/tibemsd.co
    TibEmsServerUrl = "tcp://system01:7222"
    TibPassword = GUMsJUjKKmHMiMJ
    LogDbg = { DBG_5 }
)

```

Sample service group configuration for Tibco EMS server in Failover setup

This section provides a sample configuration for Tibco EMS server agent in failover setup. The sample configuration depicts a graphical view of the resource types, resources, and resource dependencies within the service group.

```

include "types.cf"
include "TibcoEMSTypes.cf"

cluster system01_02 (
    UserNames = { admin = IhiAhcHeiDiiGqiChf }
    Administrators = { admin }
    HacliUserLevel = COMMANDROOT
)

system system01 (
)

system system02 (
)

group TibcoSG (
    SystemList = { system01 = 0, system02 = 1 }
)

DiskGroup tib_dg (
    DiskGroup = tibco_diskgroup
)

IP tib_ip_res (
    Device = bge0
)

```

Sample service group configuration for Tibco EMS server in Failover setup

```

Address = "10.209.73.81"
NetMask = "255.255.252.0"
)

Mount tib_mnt (
  MountPoint = "/home/tibco"
  BlockDevice = "/dev/vx/dsk/tibco_diskgroup/tibco_vol"
  FSType = vxfs
  FsckOpt = "-y"
)

NIC tib_nic_res (
  Device = bge0
)

TibcoEMS tib_res (
  User = tibco
  EMSHomeDir = "/home/tibco/ems/bin"
  ConfigFile = "/home/tibco/ems/bin/tibemsd.conf"
  TibEmsServerUrl = "tcp://tibhost:7222"
  SecondLevelMonitor = 1
  TibUser = admin
  TibPassword = hvnTkvK
)

tib_ip_res requires tib_nic_res
tib_mnt requires tib_dg
tib_res requires tib_ip_res
tib_res requires tib_mnt

// resource dependency tree
//
// group TibcoSG
// {
//   TibcoEMS tib_res
//     {
//       Mount tib_mnt
//         {
//           DiskGroup tib_dg
//         }
//       IP tib_ip_res
//     }

```

Sample service group configuration for Tibco EMS server in Failover setup with Solaris Zones

```
//      NIC tib_nic_res
//      }
//      }
// }
```

Sample service group configuration for Tibco EMS server in Failover setup with Solaris Zones

This section provides a sample configuration for Tibco EMS server agent in failover setup with Solaris zone support.

```
include "types.cf"
include "TibcoEMSTypes.cf"

cluster system01_02 (
  UserNames = { admin = eLMeLGlIMhMMkUMgLJ }
  Administrators = { admin }
  HacliUserLevel = COMMANDROOT
)

system system01 (
)

system system02 (
)

group tibcoZoneSG (
  SystemList = { system01 = 0 }
  ContainerInfo @system01 = { Name = tibzone, Type = Zone, Enabled = 1 }
  AutoStartList = { system01 }
  Administrators = { z_zoneres_system01 }
)

DiskGroup tib_data_dg (
  DiskGroup = tibco_diskgroup
)

DiskGroup zone_dg (
  DiskGroup = zone_diskgroup
)

IP tib_ip (
```

Sample service group configuration for Tibco EMS server in Failover setup with Solaris Zones

```

Device = bge0
Address = "10.209.73.81"
NetMask = "255.255.252.0"
)

Mount tib_data_mnt (
MountPoint = "/tibco"
BlockDevice = "/dev/vx/dsk/tibco_diskgroup/tibco_vol"
FSType = vxfs
FsckOpt = "-y"
)

Mount zone_mnt (
MountPoint = "/root/zones/tibzone"
BlockDevice = "/dev/vx/dsk/zone_diskgroup/zone_vol"
FSType = vxfs
FsckOpt = "-y"
)

NIC tib_nic (
Device = bge0
)

TibcoEMS tib_zone_res (
User = root
EMSHomeDir = "/tibco/ems/bin"
ConfigFile = "/tibco/ems/bin/tibemsd.conf"
TibEmsServerUrl = "tcp://tibzone:7222"
TibUser = admin
TibPassword = CQIoFQf
)

Zone zonerres (
)

tib_data_mnt requires tib_data_dg
tib_ip requires zonerres
tib_zone_res requires tib_ip
zone_mnt requires zone_dg
zonerres requires tib_data_mnt
zonerres requires tib_nic
zonerres requires zone_mnt


```

```
// resource dependency tree
//
// group tibcoZoneSG
// {
// TibcoEMS tib_zone_res
//   {
//     IP tib_ip
//     {
//       Zone zoneress
//       {
//         Mount tib_data_mnt
//         {
//           DiskGroup tib_data_dg
//         }
//         NIC tib_nic
//         Mount zone_mnt
//         {
//           DiskGroup zone_dg
//         }
//       }
//     }
//   }
// }
```

Sample resource dependency in a Failover configuration for Tibco EMS server

This section includes resource dependencies of Tibco service group in a failover configuration.


Figure A-1 Sample resource dependency in failover configuration



Sample resource dependency in a Failover configuration for Tibco EMS server with Solaris Zones

This section includes sample service groups with Solaris zone support.

[Figure A-2](#) shows the resource dependencies of Tibco service group in a failover configuration with Solaris Zones.

Figure A-2 Sample service group with a Tibco EMS Server instance

Sample service group configuration for Tibco EMS server in CFS based fault tolerant setup

This section provides a sample configuration for Tibco EMS server agent in Cluster File System based fault tolerant setup. The sample configuration depicts a graphical view of the resource types, resources, and resource dependencies within the service group.

```

include "types.cf"
include "CFSTypes.cf"
include "CVMTypes.cf"
include "TibcoEMSTypes.cf"

cluster system01_02 (
  UserNames = { admin = ThiAhcHeiDiiGqiChf }
  Administrators = { admin }
  HacliUserLevel = COMMANDROOT
)

```

Sample service group configuration for Tibco EMS server in CFS based fault tolerant setup

```

system system01 (
)

system system02 (
)

group TibcoSG_Pri (
  SystemList = { system01 = 0, system02 = 1 }
)

IP tib_ip_res_pri (
  Device = bge0
  Address = "10.209.73.81"
  NetMask = "255.255.252.0"
)

NIC tib_nic_res_pri (
  Device = bge0
)

TibcoEMS tib_res_pri (
  ResLogLevel = TRACE
  User = root
  EMSHomeDir = "/home/tibco/ems/bin"
  ConfigFile = "/home/tibco/ems/bin/tibemsd5.conf"
  TibEmsServerUrl = "tcp://tibhost:7222"
  SecondLevelMonitor = 1
  TibUser = admin
  TibPassword = hvnTkVK
  StartOptions = "-ft_active tcp://tibhostsec:7225"
)

requires group Tibco_infra online local firm
tib_ip_res_pri requires tib_nic_res_pri
tib_res_pri requires tib_ip_res_pri

// resource dependency tree
//
// group TibcoSG_Pri
// {
// TibcoEMS tib_res_pri

```

Sample service group configuration for Tibco EMS server in CFS based fault tolerant setup

```

//      {
//      IP tib_ip_res_pri
//      {
//      NIC tib_nic_res_pri
//      }
//      }
// }

group TibcoSG_Sec (
  SystemList = { system01 = 0, system02 = 1 }
)

IP tib_ip_res_sec (
  Device = bge0
  Address = "10.209.73.82"
  NetMask = "255.255.252.0"
)

NIC tib_nic_res_sec (
  Device = bge0
)

TibcoEMS tib_res_sec (
  User = root
  EMSHomeDir = "/home/tibco/ems/bin"
  ConfigFile = "/home/tibco/ems/bin/tibemsdl.conf"
  TibEmsServerUrl = "tcp://tibhostsec:7225"
  TibUser = admin
  TibPassword = hvnTkvK
  StartOptions = "-ft_active tcp://tibhost:7222"
)

requires group Tibco_infra online local firm
tib_ip_res_sec requires tib_nic_res_sec
tib_res_sec requires tib_ip_res_sec

// resource dependency tree
//
// group TibcoSG_Sec
// {
// TibcoEMS tib_res_sec

```

Sample service group configuration for Tibco EMS server in CFS based fault tolerant setup

```

//      {
//      IP tib_ip_res_sec
//      {
//      NIC tib_nic_res_sec
//      }
//      }
// }

group Tibco_infra (
  SystemList = { system01 = 0, system02 = 1 }
  Parallel = 1
)

CFSMount tibcfs_mnt (
  MountPoint = "/home/tibco"
  BlockDevice = "/dev/vx/dsk/tibco_install_dg/tibco_install_vol"
)

CVMVolDg tibcfs_voldg (
  CVMDiskGroup = tibco_install_dg
  CVMVolume = { tibco_install_vol }
  CVMActivation = sw
)

requires group cvm online local firm
tibcfs_mnt requires tibcfs_voldg

// resource dependency tree
//
// group Tibco_infra
// {
// CFSMount tibcfs_mnt
// {
// CVMVolDg tibcfs_voldg
// }
// }

group cvm (
  SystemList = { system01 = 0, system02 = 1 }
  AutoFailOver = 0
)

```

Sample resource dependency in a CFS based fault tolerant configuration for Tibco EMS server

```

Parallel = 1
AutoStartList = { system01, system02 }
)

CFSfsckd vxfsckd (
)

CVMCluster cvm_clus (
  CVMClustName = system01_075
  CVMNodeId = { system01 = 0, system02 = 1 }
  CVMTransport = gab
  CVMTimeout = 200
)

CVMVxconfigd cvm_vxconfigd (
  CVMVxconfigdArgs = { syslog }
)

cvm_clus requires cvm_vxconfigd
vxfsckd requires cvm_clus

// resource dependency tree
//
// group cvm
// {
//   CFSfsckd vxfsckd
//   {
//     CVMCluster cvm_clus
//     {
//       CVMVxconfigd cvm_vxconfigd
//     }
//   }
// }

```

Sample resource dependency in a CFS based fault tolerant configuration for Tibco EMS server

This section includes resource dependencies of Tibco service group in a CFS based fault tolerant configuration.

Sample resource dependency in a CFS based fault tolerant configuration for Tibco EMS server

Figure A-3 depicts the sample resource dependency of primary Tibco service group TibcoSG_Pri in a CFS based fault tolerant configuration.

Figure A-3 Sample resource dependency of primary Tibco service group in a CFS based fault tolerant configuration




Figure A-4 depicts the sample resource dependency of secondary Tibco service group TibcoSG_Sec in a CFS based fault tolerant configuration.

Sample resource dependency in a CFS based fault tolerant configuration for Tibco EMS server

Figure A-4 Sample resource dependency of secondary Tibco service group in a CFS based fault tolerant configuration




Figure A-5 The following diagram depicts the sample resource dependency of Tibco infrastructure service group TibcoSG_infra in a CFS based fault tolerant configuration.

Sample resource dependency in a CFS based fault tolerant configuration for Tibco EMS server

Figure A-5 Sample resource dependency of Tibco infrastructure service group in a CFS based fault tolerant configuration





Figure A-6 The following diagram depicts the sample resource dependency of cvm service group in a CFS based fault tolerant configuration.


Figure A-6 Sample resource dependency of cvm service group in a CFS based fault tolerant configuration



Service group dependency in a CFS based fault tolerant configuration for Tibco EMS Server

This section includes service groups that show the group dependency in a CFS based fault tolerant configuration for Tibco EMS Server.

Figure A-7 Sample service group dependency



Index

A

- about
 - configuring service groups 46
- about ACC library 18
- ACC library
 - installing 19
 - removing 26
- Agent
 - Tibco EMS 15
- agent
 - features 10
 - i18n support 18
 - importing agent types files 27
 - installing, VCS environment 21
 - optional attributes 32
 - overview 9
 - required attributes 29
 - uninstalling, VCS environment 25
- agent attributes 29
 - ConfigFile 30
 - EMSHomeDir 29
 - EnvFile 36
 - MonitorProgram 35
 - ResLogLevel 31
 - SecondLevelMonitor 33–34
 - StartOptions 35
 - TibemsadminOptions 36
 - TibEmsServerUrl 31
 - TibPassword 32
 - TibUser 31
 - User 30
- agent configuration file
 - importing 27
- agent functions 12
 - clean 14
 - imf_getnotification 39
 - imf_init 39
 - imf_register 39
 - monitor 13
 - offline 12
 - online 12

- agent installation
 - general requirements 17
 - steps to install 21

B

- before
 - configuring the service groups 46

C

- Configuring
 - Tibco EMS Server 16

I

- Intelligent Monitoring Framework (IMF)
 - about 37
 - agent functions 39
 - attributes 39
 - configuring 41

L

- logs
 - reviewing cluster log files 52
 - reviewing error log files 51
 - using trace level logging 52

S

- Sample
 - service group dependency 71
- sample
 - resource dependency 61, 67
 - service group configuration 57, 63
- sample agent type definition 55
- service group
 - sample configurations, Solaris zone support 59, 62
- service groups
 - Tibco EMS server 47
- starting the Tibco EMS Server instance outside a cluster 51

T

Tibco EMS Server

- configuring resources 51

- starting instance outside cluster 51

troubleshooting

- meeting prerequisites 50

- reviewing error log files 51

 - reviewing cluster log files 52

 - using trace level logging 52

- using correct software 50

- Using Tibco EMS log files 53

U

- uninstalling agent, VCS environment 25